
Orbix Programming Reference C++

V6.3.14

Table of Contents

Preface	15
Audience	15
Organization of this Reference	15
Related Documentation	15
Introduction	16
Interface Repository Quick Reference	16
DII and DSI Quick Reference	18
Value Type Quick Reference	19
About Standard Functions for all Interfaces	21
About Reference Types <code>_ptr</code> , <code>_var</code> , and <code>_out</code>	24
About Sequences	27
About Value Boxes	31
CORBA::AbstractInterfaceDef Interface	35
CORBA Overview	35
CORBA::AliasDef Interface	87
CORBA::Any Class	89
CORBA::ArrayDef Interface	103
CORBA::AttributeDef Interface	105
CORBA::ConstantDef Interface	108
CORBA::ConstructionPolicy Interface	110
CORBA::Contained Interface	112
CORBA::Container Interface	118
CORBA::Context Class	138
CORBA::ContextList Class	143
CORBA::CustomMarshal Value Type	146
CORBA::DataInputStream Value Type	148
CORBA::DataOutputStream Value Type	162
CORBA::DomainManager Interface	181
CORBA::EnumDef Interface	183

CORBA::Environment Class	184
CORBA::Exception Class	187
CORBA::ExceptionDef Interface	188
CORBA::ExceptionList Class	190
CORBA::FixedDef Interface	193
CORBA.InterfaceDefPackage.FullInterfaceDescription Class	194
CORBA::IDLType Interface	195
CORBA::InterfaceDef Interface	197
CORBA::IObject Interface	204
CORBA::ModuleDef Interface	205
CORBA::NamedValue Class	206
CORBA::NativeDef Interface	208
CORBA::NVList Class	209
CORBA::Object Class	217
CORBA::OperationDef Interface	231
CORBA::ORB Class	234
CORBA::Policy Interface	269
Quality of Service Framework	270
Policy Methods	271
CORBA::PolicyCurrent Class	274
CORBA::PolicyManager Class	277
CORBA::PrimitiveDef Interface	282
CORBA::Repository Interface	283
CORBA::Request Class	291
CORBA::SequenceDef Interface	301
CORBA::ServerRequest Class	303
CORBA::String_var Class	307
CORBA::StringDef Interface	312
CORBA::StructDef Interface	313
CORBA::TypeCode Class	315
CORBA::TypedefDef Interface	328

CORBA::UnionDef Interface	329
CORBA::ValueBase Class	331
CORBA::ValueBoxDef Interface	335
CORBA::ValueDef Interface	336
CORBA::ValueFactory	348
CORBA::ValueFactory Type	348
CORBA::ValueFactoryBase Class	349
CORBA::ValueMemberDef Interface	352
CORBA::WString_var Class	354
CORBA::WstringDef Interface	359
CosEventChannelAdmin Module	361
CosEventChannelAdmin Exceptions	361
CosEventComm Module	362
CosEventComm Exceptions	362
CosNaming Overview	363
CosNaming::BindingIterator Interface	367
CosNaming::NamingContext Interface	370
CosNaming::NamingContextExt Interface	385
CosNotification Module	390
CosNotification Data Types	390
QoS and Administrative Constant Declarations	391
QoS and Admin Data Types	393
QoS and Admin Exceptions	396
CosNotification::AdminPropertiesAdmin Interface	397
CosNotification::QoSAdmin Interface	399
CosNotifyChannelAdmin Module	401
CosNotifyChannelAdmin Data Types	401
CosNotifyChannelAdmin Exceptions	405
CosNotifyChannelAdmin::ConsumerAdmin Interface	407
CosNotifyChannelAdmin::EventChannel Interface	415
CosNotifyChannelAdmin::ProxyConsumer Interface	421

CosNotifyChannelAdmin::ProxyPullConsumer Interface	424
CosNotifyChannelAdmin::ProxyPullSupplier Interface	426
CosNotifyChannelAdmin::ProxyPushConsumer Interface	428
CosNotifyChannelAdmin::ProxyPushSupplier Interface	430
CosNotifyChannelAdmin::ProxySupplier Interface	433
CosNotifyChannelAdmin::SequenceProxyPullConsumer Interface	437
CosNotifyChannelAdmin::SequenceProxyPushConsumer Interface	439
CosNotifyChannelAdmin::SequenceProxyPullSupplier Interface	441
CosNotifyChannelAdmin::SequenceProxyPushSupplier Interface	443
CosNotifyChannelAdmin::StructuredProxyPullConsumer Interface	446
CosNotifyChannelAdmin::StructuredProxyPullSupplier Interface	448
CosNotifyChannelAdmin::StructuredProxyPushConsumer Interface	450
CosNotifyChannelAdmin::StructuredProxyPushSupplier Interface	452
CosNotifyChannelAdmin::SupplierAdmin Interface	455
CosNotifyComm Module	462
CosNotifyComm Exceptions	463
CosNotifyComm::NotifyPublish Interface	464
CosNotifyComm::NotifySubscribe Interface	466
CosNotifyComm::PullConsumer Interface	468
CosNotifyComm::PullSupplier Interface	469
CosNotifyComm::PushConsumer Interface	470
CosNotifyComm::PushSupplier Interface	471
CosNotifyComm::SequencePullConsumer Interface	472
CosNotifyComm::SequencePullSupplier Interface	473
CosNotifyComm::SequencePushConsumer Interface	476
CosNotifyComm::SequencePushSupplier Interface	478
CosNotifyComm::StructuredPullConsumer Interface	479
CosNotifyComm::StructuredPullSupplier Interface	480
CosNotifyComm::StructuredPushConsumer Interface	483
CosNotifyComm::StructuredPushSupplier Interface	485

CosNotifyFilter Module	486
CosNotifyFilter Data Types	486
CosNotifyFilter Exceptions	489
CosNotifyFilter::Filter Interface	491
CosNotifyFilter::FilterAdmin Interface	499
CosNotifyFilter::FilterFactory Interface	502
CosNotifyFilter::MappingFilter Interface	504
CosTrading Module	512
CosTrading Data Types	512
CosTrading Exceptions	517
CosTrading::Admin Interface	521
CosTrading::ImportAttributes Interface	531
CosTrading::Link Interface	534
CosTrading::Link Exceptions	536
CosTrading::LinkAttributes Interface	541
CosTrading::Lookup Interface	542
CosTrading::OfferIdIterator Interface	548
CosTrading::OfferIterator Interface	550
CosTrading::Proxy Interface	552
CosTrading::Register Interface	558
CosTrading::SupportAttributes Interface	567
CosTrading::TraderComponents Interface	568
CosTrading::Dynamic Module	569
CosTradingDynamic::DynamicPropEval Interface	571
CosTradingRepos Module	572
CosTradingRepos::ServiceTypeRepository Interface	573
CosTransactions Overview	584
Overview of Classes	584
General Exceptions	585
General Data Types	588
CosTransactions::Control Class	595

CosTransactions::Coordinator Class	597
CosTransactions::RecoveryCoordinator Class	609
CosTransactions::Resource Class	611
Two-phase Commit	612
One-phase Commit	613
Rollback Transaction	613
Forget Transaction	613
CosTransactions::SubtransactionAwareResource Class	614
Commit Subtransaction	615
Rollback Subtransaction	615
CosTransactions::Synchronization Class	616
Before Completion	616
After Completion	617
CosTransactions::Terminator Class	618
CosTransactions::TransactionalObject Class	620
CosTransactions::TransactionFactory Class	621
CosTypedEventChannelAdmin Module	623
CosTypedEventChannelAdmin Exceptions	623
CosTypedEventChannelAdmin Data Types	623
CosTypedEventChannelAdmin::TypedConsumerAdmin Interface	624
Unsupported Operations	625
CosTypedEventChannelAdmin::TypedEventChannel Interface	626
CosTypedEventChannelAdmin::TypedProxyPushConsumer Interface	627
Unsupported Operations	627
CosTypedEventChannelAdmin::TypedSupplierAdmin Interface	628
Unsupported Operations	629
CosTypedEventComm Module	630
CosTypedEventComm::TypedPushConsumer Interface	631
CSI Overview	632
CSIIOP Overview	636
DsEventLogAdmin Module	640

DsEventLogAdmin::EventLogFactory Interface	641
DsLogAdmin Module	643
DsLogAdmin Exceptions	643
DsLogAdmin Constants	645
DsLogAdmin Datatypes	646
DsLogAdmin::BasicLog Interface	653
DsLogAdmin::BasicLogFactory Interface	654
DsLogAdmin::Iterator Interface	656
DsLogAdmin::Log Interface	658
DsLogAdmin::LogMgr Interface	675
DsLogNotification Module	676
DsNotifyLogAdmin Module	681
Dynamic Module	682
DynamicAny Overview	684
DynamicAny::DynAny Class	693
DynamicAny::DynAnyFactory Class	734
DynamicAny::DynArray Class	740
DynamicAny::DynEnum Class	745
DynamicAny::DynFixed Class	749
DynamicAny::DynSequence Class	752
DynamicAny::DynStruct Class	758
DynamicAny::DynUnion Class	764
DynamicAny::DynValue Class	770
GSSUP Overview	776
IT_Buffer	778
IT_Buffer::Storage	778
IT_Buffer::Segment	780
IT_Buffer::Buffer	781
IT_Buffer::BufferManager	785
IT_Certificate Overview	788
IT_Certificate::AVA Interface	797

IT_Certificate::AVAList Interface	800
IT_Certificate::Certificate Interface	804
IT_Certificate::Extension Interface	805
IT_Certificate::ExtensionList Interface	807
IT_Certificate::X509Cert Interface	811
IT_Certificate::X509CertificateFactory Interface	818
IT_Config Overview	821
IT_Config::Configuration Interface	824
IT_Config::Listener Interface	831
IT_CORBA Overview	837
IT_CORBA::RefCountedLocalObject Class	838
IT_CORBA::RefCountedLocalObjectNC Class	840
IT_CORBA::WellKnownAddressingPolicy Class	842
IT_CORBASEC	844
IT_CORBASEC::ExtendedReceivedCredentials	846
IT_CosTransactions Module	850
IT_CSI Overview	851
IT_CSI::AttributeServicePolicy Interface	857
IT_CSI::AuthenticateGSSUPCredentials Interface	860
IT_CSI::AuthenticationServicePolicy Interface	863
IT_CSI::CSICredentials Interface	866
IT_CSI::CSICurrent Interface	867
IT_CSI::CSICurrent2 Interface	868
IT_CSI::CSIReceivedCredentials Interface	872
IT_EventChannelAdmin Module	874
IT_EventChannelAdmin Data Types	874
IT_EventChannelAdmin Exceptions	875
IT_EventChannelAdmin::EventChannelFactory Interface	876
IT_FPS Module	879
IT_FPS::InterdictionPolicy Interface	881

IT_GIOP	882
Interface IT_GIOP::ClientVersionConstraintsPolicy	883
Interface IT_GIOP::ClientCodeSetConstraintsPolicy	883
Interface IT_GIOP::Current	884
Interface IT_GIOP::Current2	887
IT_LoadBalancing Overview	891
IT_LoadBalancing::ObjectGroup Interface	894
IT_LoadBalancing::ObjectGroupFactory Interface	901
IT_Logging Overview	906
IT_Logging::EventLog Interface	915
IT_Logging::LogStream Interface	921
IT_MessagingAdmin Module	924
IT_MessagingAdmin::Manager Interface	925
IT_MessagingBridge Module	926
IT_MessagingBridge Data Types	926
IT_MessagingBridge Exceptions	928
IT_MessagingBridge::Endpoint Interface	930
IT_MessagingBridge::SinkEndpoint Interface	933
IT_MessagingBridge::SourceEndpoint Interface	934
IT_MessagingBridge::EndpointAdmin Interface	935
IT_MessagingBridgeAdmin Module	939
IT_MessagingBridgeAdmin Data Types	939
IT_MessagingBridgeAdmin Exceptions	940
IT_MessagingBridgeAdmin::Bridge Interface	942
IT_MessagingBridgeAdmin::BridgeAdmin Interface	944
IT_NotifyBridge Module	947
IT_NotifyBridge Exceptions	947
IT_NotifyBridge::SinkEndpoint Interface	948
IT_NamedKey	949
IT_NamedKey::NamedKeyRegistry	950
IT_Naming Module	954

IT_Naming::IT_NamingContextExt Interface	955
IT_NotifyChannelAdmin Module	956
IT_NotifyChannelAdmin::GroupProxyPushSupplier Interface	957
IT_NotifyChannelAdmin:GroupSequenceProxyPushSupplier Interface	959
IT_NotifyChannelAdmin::GroupStructuredProxyPushSupplier Interface	961
IT_NotifyComm Module	963
IT_NotifyComm::GroupNotifyPublish Interface	964
IT_NotifyComm::GroupPushConsumer Interface	966
IT_NotifyComm::GroupSequencePushConsumer Interface	968
IT_NotifyComm::GroupStructuredPushConsumer Interface	970
IT_NotifyLogAdmin Module	972
IT_NotifyLogAdmin::NotifyLog Interface	973
IT_NotifyLogAdmin::NotifyLogFactory Interface	974
IT_PlainTextKey	975
IT_PlainTextKey	975
IT_PlainTextKey::Forwarder	975
IT_PortableServer Overview	978
IT_PortableServer::DispatchWorkQueuePolicy Interface	981
IT_PortableServer::ObjectDeactivationPolicy Class	982
IT_PortableServer::PersistenceModePolicy Class	984
IT_TLS Overview	986
IT_TLS::CertValidator Interface	990
IT_TLS_API Overview	992
IT_TLS_API::CertConstraintsPolicy Interface	996
IT_TLS_API::CertValidatorPolicy Interface	997
IT_TLS_API::MaxChainLengthPolicy Interface	998
IT_TLS_API::SessionCachingPolicy Interface	999
IT_TLS_API::TLS Interface	1001
IT_TLS_API::TLSCredentials Interface	1002
IT_TLS_API::TLSReceivedCredentials Interface	1004
IT_TLS_API::TLSTargetCredentials Interface	1005

IT_TLS_API::TrustedCAListPolicy Interface	1006
IT_TypedEventChannelAdmin Module	1007
IT_TypedEventChannelAdmin Data Types	1007
IT_TypedEventChannelAdmin::TypedEventChannelFactory Interface	1008
IT_WorkQueue Module	1011
IT_WorkQueue::AutomaticWorkQueue Interface	1012
IT_WorkQueue::AutomaticWorkQueueFactory Interface	1014
IT_WorkQueue::ManualWorkQueue Interface	1017
IT_WorkQueue::ManualWorkQueueFactory Interface	1019
IT_WorkQueue::WorkItem Interface	1020
IT_WorkQueue::WorkQueue Interface	1021
IT_WorkQueue::WorkQueuePolicy Interface	1024
IT_ZIOP	1025
IT_ZIOP::Compressor	1026
IT_ZIOP::CompressorFactory	1028
IT_ZIOP::CompressionManager	1029
IT_ZIOP::CompressionComponent	1032
IT_ZIOP::CompressionComponentFactory	1032
IT_ZIOP::CompressionEnablingPolicy	1032
IT_ZIOP::CompressorIdPolicy	1033
Messaging Overview	1034
Messaging::ExceptionHolder Value Type	1040
Messaging::RebindPolicy Class	1046
Messaging::ReplyHandler Base Class	1049
Messaging::RoutingPolicy Class	1052
Messaging::SyncScopePolicy Class	1055
OrbixEventsAdmin Module	1058
OrbixEventsAdmin::ChannelManager	1059
Unsupported Operations	1062
PortableInterceptor Module	1063
PortableInterceptor::ClientRequestInfo Interface	1065

PortableInterceptor::ClientRequestInterceptor Interface	1073
PortableInterceptor::Interceptor Interface	1077
PortableInterceptor::IORInfo Interface	1078
PortableInterceptor::IORInterceptor Interface	1081
PortableInterceptor::ORBInitializer Interface	1083
PortableInterceptor::ORBInitInfo Interface	1085
PortableInterceptor::PolicyFactory Interface	1093
PortableInterceptor::RequestInfo Interface	1095
PortableInterceptor::ServerRequestInfo Interface	1104
PortableInterceptor::ServerRequestInterceptor Interface	1108
PortableServer Overview	1112
PortableServer conversion functions	1113
PortableServer Data Types, Constants, and Exceptions	1114
PortableServer::AdapterActivator Interface	1121
PortableServer::DynamicImplementation Class	1124
PortableServer::IdAssignmentPolicy Interface	1126
PortableServer::IdUniquenessPolicy Interface	1128
PortableServer::ImplicitActivationPolicy Interface	1130
PortableServer::POA Interface	1132
PortableServer::LifespanPolicy Interface	1157
PortableServer::POAManager Interface	1159
PortableServer::RequestProcessingPolicy Interface	1165
PortableServer::ServantActivator Interface	1168
PortableServer::ServantBase	1171
PortableServer::ServantLocator Interface	1174
PortableServer::ServantManager Interface	1178
PortableServer::ServantRetentionPolicy Interface	1179
PortableServer::ThreadPolicy Interface	1181
Security Overview	1183
SecurityLevel1 Overview	1194
SecurityLevel2 Overview	1195

SecurityLevel2::Credentials Interface	1196
SecurityLevel2::Current Interface	1202
SecurityLevel2::EstablishTrustPolicy Interface	1203
SecurityLevel2::InvocationCredentialsPolicy Interface	1204
SecurityLevel2::MechanismPolicy Interface	1205
SecurityLevel2::PrincipalAuthenticator Interface	1206
SecurityLevel2::QOPPolicy Interface	1210
SecurityLevel2::ReceivedCredentials Interface	1211
SecurityLevel2::SecurityManager Interface	1213
SecurityLevel2::TargetCredentials Interface	1217
System Exceptions	1218
Notices	1223
Copyright	1223
Trademarks	1223
Examples	1223
License agreement	1223
Corporate information	1224
Contacting Technical Support	1224
Country and Toll-free telephone number	1224

Preface

Orbix is a software environment for building and integrating distributed object-oriented applications. Orbix is a full implementation of the Common Object Request Broker Architecture (CORBA) from the Object Management Group (OMG). Orbix fully supports CORBA version 2.3.

This document is based on the CORBA 2.3 standard with some additional features and Orbix-specific enhancements.

Audience

The reader is expected to understand the fundamentals of writing a distributed application with Orbix. Familiarity with C++ is required.

Organization of this Reference

This reference presents core-product modules in alphabetical order, disregarding `IT_` prefixes in order to keep together related OMG-compliant and Orbix-proprietary modules. For example, modules `CORBA` and `IT_CORBA` are listed in sequence.

Modules that are specific to a service are also grouped together under the service's name—for example, modules `CosPersistentState`, `IT_PSS`, and `IT_PSS_DB` are listed under Persistent State Service.

Related Documentation

This document is part of a set that comes with the Orbix product. Other books in this set include:

- *Application Server Platform Administrator's Guide*
- *CORBA Programmer's Guide*
- *CORBA Code Generation Toolkit Guide*

Introduction

This describes all of the standard programmer's API for CORBA and Orbix. This introduction contains the following topics:

- [Interface Repository Quick Reference](#)
- [DII and DSI Quick Reference](#)
- [Value Type Quick Reference](#)
- [About Standard Functions for all Interfaces](#)
- [About Reference Types `\_ptr`, `\_var`, and `\_out`](#)
- [About Sequences](#)
- [About Value Boxes](#)

The rest of the *CORBA Programmer's Reference* contains the following modules and appendix:

CORBA	IT_PSS
CosNaming	IT_PSS_DB
CosPersistentState	Messaging
CosTransactions	PortableInterceptor
DynamicAny	PortableServer
IT_Config	
IT_CORBA	System Exceptions
IT_Logging	
IT_PolicyBase	
IT_PortableServer	

Interface Repository Quick Reference

The interface repository (IFR) is the component of Orbix that provides persistent storage of IDL definitions. Programs use the following API to query the IFR at runtime to obtain information about IDL definitions:

Table 1: Interface Repository API

CORBA Types	CORBA Sequences

ContextIdentifier	AttrDescriptionSeq
Identifier	ContainedSeq
RepositoryId	ContextIdSeq
ScopedName	ExceptionDefSeq
VersionSpec	ExcDescriptionSeq
ValueModifier	EnumMemberSeq
Visibility	InitializerSeq
ValueModifier	InterfaceDefSeq
Visibility	OpDescriptionSeq
	ParDescriptionSeq
	RepositoryIdSeq
	StructMemberSeq
	UnionMemberSeq
	ValueDefSeq
	ValueMemberSeq
CORBA Structures	CORBA Enumerated Types
AttributeDescription	AttributeMode
ConstantDescription	DefinitionKind
ExceptionDescription	OperationMode
Initializer	ParameterMode
InterfaceDescription	PrimitiveKind
ModuleDescription	TCKind
OperationDescription	
ParameterDescription	
StructMember	
TypeDescription	
UnionMember	
ValueDescription	
ValueMember	
CORBA Classes and Interfaces	Typecode Methods in CORBA::ORB

AliasDef	create_abstract_interface_tc()
ArrayDef	create_alias_tc()
AttributeDef	create_array_tc()
ConstantDef	create_enum_tc()
Contained	create_exception_tc()
Container	create_fixed_tc()
EnumDef	create_interface_tc()
ExceptionDef	create_native_tc()
Environment	create_recursive_tc()
FixedDef	create_sequence_tc()
IDLType	create_string_tc()
InterfaceDef	create_struct_tc()
IRObject	create_union_tc()
ModuleDef	create_value_box_tc()
NativeDef	create_value_tc()
OperationDef	create_wstring_tc()
PrimitiveDef	
Repository	
SequenceDef	
StringDef	
StructDef	
TypeCode	
TypedefDef	
UnionDef	
ValueBoxDef	
ValueDef	
ValueMemberDef	
WstringDef	

DII and DSI Quick Reference

The client-side dynamic invocation interface (DII) provides for the dynamic creation and invocation of requests for objects. The server-side counterpart to the DII is the dynamic Skeleton interface (DSI) which dynamically handles object invocations. This dynamic system uses the following data structures, interfaces, and classes:

Table 2: DII and DSI API

DII Classes	DSI Classes
<code>CORBA::Context</code> <code>CORBA::ContextList</code> <code>CORBA::ExceptionList</code> <code>CORBA::Request</code> <code>CORBA::TypeCode</code>	<code>CORBA::ServerRequest</code> <code>PortableServer::DynamicImplementation</code>
Key Data Types	DII-Related Methods
<code>CORBA::Any</code> <code>CORBA::Flags</code> <code>CORBA::NamedValue</code> <code>CORBA::NVList</code>	<code>CORBA::Object::_create_request()</code> <code>CORBA::ORB::create_list()</code> <code>CORBA::ORB::create_operation_list()</code> <code>CORBA::ORB::get_default_context()</code>

Value Type Quick Reference

A value type is the mechanism by which objects can be passed by value in CORBA operations. Value types use the following data structures, methods, and value types from the CORBA module:

Types

```
StringValue
ValueFactory
WStringValue
```

Value Types and Classes

```
CustomMarshal  
DataInputStream  
DataOutputStream  
ValueBase  
ValueFactory  
ValueFactoryBase  
ValueDef
```

Global Functions

```
add_ref()  
remove_ref()
```

Sequences

```
AnySeq
BooleanSeq
CharSeq
DoubleSeq
FloatSeq
OctetSeq
ShortSeq
UShortSeq
ULongLongSeq
ULongSeq
WCharSeq
```

About Standard Functions for all Interfaces

Every IDL interface also has generated helper functions:

`_duplicate()`

inline static `CLASS_ptr _duplicate(`

```
    CLASS_ptr p
);
```

This function returns a duplicate object reference and increments the reference count of the object. Use this function to create a copy of an object reference.

Parameters

`p`

The current object reference to duplicate.

Note

This is a standard function generated for all interfaces.

`_narrow()`

static `CLASS_ptr _narrow(`

```
CORBA::Object_ptr obj
);
```

This function returns a new object reference given an existing reference. Use this function to narrow an object reference.

Parameters

obj

A reference to an object. The function returns a nil object reference if this parameter is a nil object reference.

Note

This is a standard function generated for all interfaces.

When you have IDL interfaces that inherit from each other, you often need to convert a reference of one type to a related type. This is analogous to casting between pointers to classes which inherit from each other classes in C++. For example suppose you have the following interfaces:

```
// IDL
interface Base { ... };
interface Derived : Base { ... };
```

Now suppose you have a reference of type `Base` but it refers to an object which is actually of type `Derived`. Converting the `Base` reference to a `Derived` reference is called *narrowing* because you are converting from a more general type to a more specific, or narrow, type. Conversely converting a `Derived` reference to a `Base` reference is called *widening*. Note that narrowed or widened references still refer to the same object, they are simply different *views* of that object.

Always check the results of `_narrow()` with `CORBA::is_nil()`. The `_narrow()` function checks whether the reference actually refers to an object of the type you are narrowing to. If not, `_narrow()` returns a nil reference. The `_narrow()` function does an implicit duplicate, so you are responsible for releasing both the original reference and the new reference returned. The easiest way to do this is by assigning both to `_var` variables.

The `_narrow()` function can actually both narrow and widen references. It takes a `CORBA::Object_ptr` parameter and tests whether the requested interface is compatible with the actual most-derived interface implemented by the object, regardless of the inheritance relationships involved.

Exceptions A standard system exception can be raised in some unusual cases where a remote call occurs to the object being narrowed. However, normally `_narrow()` is a local function call and it can figure out the conversion based on information in the IDL compiler generated stub code.

See Also [_unchecked_narrow\(\)](#)

`_nil()`

```
inline static CLASS_ptr _nil();
```

Returns a nil object reference to the object.

Note

This is a standard function generated for all interfaces.

`_unchecked_narrow()`

```
static CLASS_ptr _unchecked_narrow(
```

```
    CORBA::Object_ptr obj
);
```

Returns a new object reference to the object given an existing reference. However, unlike `_narrow()`, this function does not verify that the actual type of the parameter at runtime can be widened to the requested interface's type.

Parameters

`obj`

A reference to an object.

Note

This is a standard function generated for all interfaces.

See Also [_narrow\(\)](#)

About Reference Types `_ptr`, `_var`, and `_out`

Every IDL interface has generated helper pointer types that you use as object references. The object reference pointer type names generated are based on the interface name and include:

<code>InterfaceName_ptr</code>	Use the <code>InterfaceName_ptr</code> type to reference <code>InterfaceName</code> objects in a manner similar to a C++ pointer.
<code>InterfaceName_var</code>	Use the <code>InterfaceName_var</code> type to reference objects so that the object's memory management is automatic.
<code>InterfaceName_out</code>	The <code>InterfaceName_out</code> type is used only in method signatures when referring to <code>InterfaceName</code> objects as out parameters. This type gives Orbix the ability to implicitly release a previous value of an <code>InterfaceName_var</code> when it is passed as an out parameter.

Reference Example

Assume the following interface for this discussion:

```
// IDL
interface InterfaceName {
    InterfaceName op(
        in  InterfaceName arg1,
        out InterfaceName arg2
    );
};
```

The following example shows the C++ pointer helper classes that the IDL compiler generates for the object reference pointer types. (No inline implementation details are shown):


```

class InterfaceName; // forward reference
typedef InterfaceName *InterfaceName_ptr;
class InterfaceName_var : public _var {
public:
    InterfaceName_var() : ptr_(InterfaceName::_nil()) { }
    InterfaceName_var(InterfaceName_ptr p) : ptr_(p) { }
    InterfaceName_var(const InterfaceName_var &a) :
        ptr_(InterfaceName::_duplicate(InterfaceName_ptr(a)) { }
    ~InterfaceName_var() { }
    InterfaceName_var &operator=(InterfaceName_ptr p) { }
    InterfaceName_var &operator=(const InterfaceName_var& a) { }
    InterfaceName_ptr in() const { }
    InterfaceName_ptr& inout() { }
    InterfaceName_ptr& out() { }
    InterfaceName_ptr _retn() { }
    operator const InterfaceName_ptr&() const { }
    operator InterfaceName_ptr&() { }
    InterfaceName_ptr operator->() const { }
protected:
    InterfaceName_ptr ptr_;
    void free() { }
    void reset(InterfaceName_ptr p) { }
private:
    ...
};

class InterfaceName_out {
public:
    InterfaceName_out(InterfaceName_ptr& p) : ptr_(p) { }
    InterfaceName_out(InterfaceName_var& p) : ptr_(p.ptr_) { }
    InterfaceName_out(InterfaceName_out& a) : ptr_(a.ptr_) { }
    InterfaceName_out& operator=(InterfaceName_out& a) { }
    InterfaceName_out& operator=(const InterfaceName_var& a) { }
    InterfaceName_out& operator=(InterfaceName_ptr p) { }
    operator InterfaceName_ptr&() { }
    InterfaceName_ptr& ptr() { }
    InterfaceName_ptr operator->() { }
private:
    ...
};

```

Widening and Narrowing References

As with C++ class pointers you can widen `_ptr` references by assignment. For example:

```
// C++
// This is legal, but be careful of memory management with _ptr!
Derived_ptr derived_ref = ...; // Get a Derived reference.
Base_ptr base_ref = derived_ref; // Widening assignment.
```

In general you should use `_var` references to avoid memory leaks. You cannot widen by direct assignment of `_var` types, instead you must use `_duplicate()` explicitly. This is because of C++ problems in implementing all the necessary conversion operators.

```
Derived_var derived_ref = ...;
Base_var base_ref = Base::_duplicate(derived_ref);
```

As in C++ you cannot narrow references by simple assignment or duplication. Note that it is *not* legal to use C++ casting to narrow CORBA object references (even if your compiler supports dynamic casts.) Instead you use the static `_narrow()` function on a class corresponding to the interface you want to narrow to. For example:

```
// C++
Base_var base_ref = ...; // Get a Base reference somehow.
Derived_var derived_ref = Derived::_narrow(base_ref);
if (CORBA::is_nil(derived_ref))
{
    // base_ref does not refer to an object of type Derived.
}
else
{
    // We can use derived_ref to call Derived operations.
}
```

About Sequences

An IDL sequence maps to a class of the same name. For example, an IDL sequence named `TypeSeq` which is made up of a sequence of `Type` IDL data types, has the class `TypeSeq` implemented.

```
// IDL
typedef sequence<Type> TypeSeq;
```

The implemented `TypeSeq` class contains the following functions:

```

// C++
class TypeSeq {
public:
    // default constructor
    TypeSeq();
    // initial maximum length constructor
    TypeSeq(ULong max);
    // data constructor
    TypeSeq(
        ULong max,
        ULong length,
        Type *data,
        Boolean release = FALSE
    );
    // copy constructor
    TypeSeq(const TypeSeq&);
    // destructor
    ~TypeSeq();
    // assignment operator
    TypeSeq &operator=(const TypeSeq&);
    ULong maximum() const;
    void length(ULong);
    ULong length() const;
    // subscript operators
    Type &operator[](ULong index);
    const Type &operator[](ULong index) const;
    Boolean release() const;
    void replace(
        ULong max,
        ULong length,
        Type *data,
        Boolean release = FALSE
    );
    // buffer reference
    Type* get_buffer(Boolean orphan = FALSE);
    // buffer access
    const Type* get_buffer() const;
};

```

Each function is described as follows.

<code>TypeSeq()</code>	A sequence has four possible constructors: - The default constructor sets the sequence length equal to 0. - The constructor with the single <code>max</code> parameter allows you to set the initial value for the maximum length of the sequence. This allows you to control how much buffer space is initially allocated by the sequence. This constructor also sets the length to 0 and the sequence release flag to TRUE. - The data constructor (the one with the <code>*data</code> parameter) lets you set the length and contents of the sequence. It also allows you to set the initial value for the maximum length. For this constructor, ownership of the buffer is determined by the release parameter. - The copy constructor creates a new sequence with the same maximum and length as the given sequence parameter, copies each of its current elements (items zero through length-1), and sets the sequence release flag to TRUE.
<code>~TypeSeq()</code>	For the destructor, if the sequence release flag equals TRUE the destructor destroys each of the current elements (items zero through length-1), and destroys the underlying sequence buffer. If the sequence release flag equals FALSE, the calling code is responsible for managing the buffer's storage.
<code>&operator =()</code>	The assignment operator (<code>=</code>) deep-copies the sequence, releasing old storage if necessary.
<code>maximum()</code>	The <code>maximum()</code> function returns the total number of sequence elements that can be stored in the current sequence buffer. This allows you to know how many items you can insert into an unbounded sequence without causing a reallocation.
<code>length()</code>	Use the <code>length()</code> functions to access and modify the length of the sequence. Increasing the length of a sequence adds new elements at the end. The newly-added elements behave as if they are default-constructed when the sequence length is increased.
<code>&operator []()</code>	The overloaded subscript operators (<code>[]</code>) return the item at the given index.

```
release(  
)
```

The `release()` function returns the state of the sequence release flag. FALSE means the caller owns the storage for the buffer and its elements, while TRUE means that the sequence manages its own storage for the buffer and its elements.

```
replace(  
)
```

The `replace()` function lets you replace the buffer underlying a sequence. The parameters to `replace()` are identical in type, order, and purpose to those for the data constructor for the sequence.

`get_buffer()`

The overloaded `get_buffer()` functions allow direct access to the buffer underlying a sequence. These can be very useful when sending large blocks of data as sequences and the per-element access provided by the overloaded subscript operators is not sufficient.

- The non-constant `get_buffer()` reference function allows read-write access to the underlying buffer. If its orphan argument is `FALSE` (the default), the sequence returns a pointer to its buffer, allocating one if it has not yet done so. The size of the buffer can be determined using the sequence's `maximum()` function. The number of elements in the buffer can be determined from the sequence's `length()` function. The sequence maintains ownership of the underlying buffer. Elements in the returned buffer may be directly replaced by your code. However, because the sequence maintains the length and size of the buffer, code that calls `get_buffer()` cannot lengthen or shorten the sequence by directly adding elements to or removing elements from the buffer.

- The const `get_buffer()` access function allows read-only access to the sequence buffer. The sequence returns its buffer, allocating one if one has not yet been allocated. No direct modification of the returned buffer is allowed by the calling code.

About Value Boxes

A value box is a value type that is a form of simple containment. It is like an additional namespace that contains only one name. A value box has no inheritance or operations and it contains a single state member. This allows it to be a concrete rather than abstract class.

The C++ mapping for a value box depends on the underlying type. CORBA contains the two string value boxes `StringValue` and `WStringValue`. The mapping as follows:

```
// IDL
valuetype StringTypeValue stringtype;
```

The implemented `StringTypeValue` class contains the following functions:

```
class StringTypeValue : public DefaultValueRefCountBase {
```

```

public:
    // constructors
    StringTypeValue();
    StringTypeValue(const StringTypeValue& val);
    StringTypeValue(char* str);
    StringTypeValue(const char* str);
    StringTypeValue(const String_var& var);
    // assignment operators
    StringTypeValue& operator=(char* str);
    StringTypeValue& operator=(const char* str);
    StringTypeValue& operator=(const String_var& var);
    // accessor
    const char* _value() const;
    // modifiers
    void _value(char* str);
    void _value(const char* str);
    void _value(const String_var& var);
    // explicit argument passing conversions for underlying string
    const char* _boxed_in() const;
    char*& _boxed_inout();
    char*& _boxed_out();
    // ...other String_var functions such as overloaded
    // subscript operators, etc....
    static StringTypeValue* _downcast(ValueBase* base);
protected:
    ~StringTypeValue();
    ...
};

```

In order to allow boxed strings to be treated as normal strings where appropriate, a boxed string provides most of the same interface as the `String_var` class.

The function of the value box class for strings are described as follows:

StringType Value()

Public constructors include:

- The default constructor initializes the underlying string to an empty string.
- One constructor takes a `char*` argument which is adopted.
- One constructor takes a `const char*` which is copied.
- One constructor takes a `const String_var&` from which the underlying string value is copied. If the `String_var` holds no string, the boxed string value is initialized to the empty string.

operator=()

There are three public assignment operators. Each returns a reference to the object being assigned to:

- one that takes a parameter of type `char*` which is adopted.
- One that takes a parameter of type `const char*` which is copied.
- One that takes a parameter of type `const String_var&` from which the underlying string value is copied. If the `String_var` holds no string, the boxed string value is set equal to the empty string.

_value()

Public accessor and modifier functions for the `StringValue`.

- The single accessor function takes no arguments and returns a `const char*`.

There are three modifier functions, each taking a single argument.

- One takes a `char*` argument which is adopted by the value box class.
- One modifier function takes a `const char*` argument which is copied.
- One takes a `const String_var&` from which the underlying string value is copied.

<code>_boxed_in()</code>	Allows the boxed value to be passed as an in parameter. This is the boxed string counterpart to the <code>String_var::in()</code> function.
<code>_boxed_inout()</code>	Allows the boxed value to be passed as an inout parameter. This is the boxed string counterpart to the <code>String_var::inout()</code> function.
<code>_boxed_out()</code>	Allows the boxed value to be passed as an out parameter. This is the boxed string counterpart to the <code>String_var::out()</code> function.
<code>operator[]()</code>	Note that even though the boxed string provides overloaded subscript operators, the fact that values are normally handled by pointer means that they must be dereferenced before the subscript operators can be used.
<code>_downcast()</code>	A downcast function.
<code>~StringVal ue()</code>	The destructor is not generally used.

CORBA::AbstractInterfaceDef Interface

`AbstractInterfaceDef` describes an abstract IDL interface in the interface repository. It inherits from the [InterfaceDef](#) interface.

```
// IDL
interface AbstractInterfaceDef : InterfaceDef
{
};
```

CORBA Overview

The CORBA namespace implements the IDL CORBA module. Additional introductory chapters describe the common methods and definitions found in the scope of the CORBA namespace.

- [Common CORBA Methods](#)
- [Common CORBA Data Types](#)

All classes or interfaces defined in the CORBA namespace are described in the following alphabetically ordered chapters:

AliasDef	ExceptionDef	Repository
Any	ExceptionList	Request
ArrayDef	FixedDef	SequenceDef
AttributeDef	IDLType	ServerRequest
ConstantDef	InterfaceDef	StringDef
ConstructionPolicy	IRObject	String_var
Contained	ModuleDef	StructDef
Container	NamedValue	TypeCode
Context	NativeDef	TypedefDef
ContextList	NVList	UnionDef
Current	Object	ValueBase
CustomMarshal	OperationDef	ValueBoxDef
DataInputStream	ORB	ValueDef
DataOutputStream	Policy	ValueFactory
DomainManager	PolicyCurrent	ValueMemberDef
EnumDef	PolicyManager	WstringDef
Environment	PrimitiveDef	WString_var

Some standard system exceptions are also defined in the CORBA module. However, these exceptions are described in [System Exceptions](#).

Common CORBA Methods

This section contains details of all common CORBA methods. The following alphabetically ordered list contains a link to the details of each method:

- [add_ref\(\)](#)
- [_duplicate\(\)](#)
- [is_nil\(\)](#)
- [_nil\(\)](#)
- [ORB_init\(\)](#)
- [release\(\)](#)
- [remove_ref\(\)](#)
- [string_alloc\(\)](#)
- [string_dup\(\)](#)
- [string_free\(\)](#)

CORBA::add_ref()

```
void add_ref(ValueBase* vb);
```

Increments the reference count of the `valuetype` instance pointed to by the method's argument. This method does nothing if the argument is null.

Parameters

vb

Pointer to the object reference for the `valuetype` instance.

This method is provided for consistency with the reference counting method for object references. Unlike the `ValueBase::_add_ref()` member method, `add_ref()` can be called with null `valuetype` pointers.

See Also `CORBA::remove_ref()`

```
CORBA::ValueBase::_remove_ref()
CORBA::ValueBase::_add_ref()
```

CORBA::_duplicate()

```
static Type_ptr _duplicate( Type_ptr p);
```

Increments the reference count of the object reference, `p` and returns a copy of the object reference. If `p` is nil, `_duplicate()` returns a nil object reference.

Parameters

p

Pointer to the object reference.

See Also `CORBA::Object::_duplicate()`

CORBA::is_nil()

```
Boolean is_nil( Type_ptr p);
```

Returns a true value if the object reference contains the special value for a nil object reference as defined by the ORB. Otherwise the method returns a false value.

Parameters

p

Pointer to the object reference.

Object references cannot be compared using `operator==`; therefore, `is_nil()` is the only compliant way an object reference can be checked to see if it is nil. A compliant program cannot attempt to invoke a method through a nil object reference, since a valid C++ implementation of a nil object reference is a null pointer.

Overloaded versions of this method are generated for each IDL interface, and for each pseudo object type. Object reference types include:

```
Context_ptr
Environment_ptr
NamedValue_ptr
NVList_ptr
Object_ptr
ORB_ptr
POA_ptr
Request_ptr
TypeCode_ptr
```

See Also CORBA::Object

```
CORBA::release()
CORBA::_nil()
```

[About Reference Types _ptr, _var, and _out](#)

CORBA::_nil()

static `Type_ptr` _nil();

Returns a nil object reference for the `Type` interface.

See Also CORBA::Object

```
CORBA::is_nil()
```

CORBA::ORB_init()

static ORB_ptr ORB_init(

```
int& argc,
char** argv,
const char* orb_identifier = ""
);
```

Initializes a client or server connection to an ORB.

Parameters

<code>argc</code>	Number of arguments in the argument list, <code>argv</code> .
<code>argv</code>	Pointer to an argument list of environment-specific data for the call. Valid ORB arguments include: - <code>-ORBdomain value</code> Where to get the ORB actual configuration information. - <code>-ORBid value</code> The ORB identifier. - <code>-ORBname value</code> The ORB name. Each ORB argument is a sequence of configuration strings or options in either of the following forms: - <code>-ORBsuffix value</code> - <code>-ORBsuffixvalue</code> The <code>suffix</code> is the name of the ORB option being set, and <code>value</code> is the value to which the option is set. Spaces between the <code>suffix</code> and <code>value</code> are optional. Any string in the argument list that is not in one of these formats is ignored by the <code>ORB_init()</code> method.
<code>orb_identifier</code>	The string identifier for the ORB initialized. For example, the string "Orbix" identifies the Orbix ORB from Rocket Software.

When an application requires a CORBA environment, it uses `ORB_init()` to get the ORB pseudo-object reference. This method first initializes an application in the ORB environment and then it

returns the ORB pseudo-object reference to the application for use in future ORB calls. Because applications do not initially have an object on which to invoke ORB calls, `ORB_init()` is a bootstrap call into the CORBA environment. Thus, the `ORB_init()` call is part of the CORBA module but not part of the `CORBA::ORB` class.

Applications can be initialized in one or more ORBs. Special ORB identifiers (indicated by either the `orb_identifier` parameter or the `-ORBid` argument) are intended to uniquely identify each ORB used within the same address space in a multi-ORB application. The ORB identifiers are allocated by the ORB administrator who is responsible for ensuring that the names are unambiguous. Note the following when assigning ORB identifiers in an `ORB_init()` call:

- If the `orb_identifier` parameter has a value, any `-ORBid` arguments in the `argv` are ignored. However, all other ORB arguments in `argv` might be significant during the ORB initialization process.
- If the `orb_identifier` parameter is null, then the ORB identifier is obtained from the `-ORBid` argument of `argv`.
- If the `orb_identifier` is null and there is no `-ORBid` argument in `argv`, the default ORB is returned in the call.

The `argv` arguments are also examined to determine if there are any other ORB arguments (arguments of the form `-ORBsuffix`). These ORB arguments are processed only by the `ORB_init()` method. In fact, before `ORB_init()` returns, it removes from `argv` all ORB arguments. This unique format for start-up arguments means that your servers do not have to be written to handle ORB arguments.

ORB initialization must occur before POA initialization.

Exceptions

`BAD_PARAM`

A string in `argv` that matches the ORB argument pattern `-ORBsuffix` is not recognized by the ORB.

See Also

`CORBA::ORB`

`CORBA::release()`

Indicates that the caller will no longer access the object reference so that associated resources can be deallocated.

Parameters

Type_ptr

Pointer to the object reference to be released.

If the given object reference is nil, `release()` does nothing.

Overloaded versions of this method are generated for each IDL interface, and for each pseudo object type. Object reference types include:

```

Context_ptr
Environment_ptr
NamedValue_ptr
NVList_ptr
Object_ptr
ORB_ptr
POA_ptr
Request_ptr
TypeCode_ptr

```

See Also CORBA::Object

CORBA::is_nil()

[About Reference Types _ptr, _var, and _out](#)

CORBA::remove_ref()

void remove_ref(ValueBase* vb);

Decrements the reference count of the `valuetype` instance pointed to by the parameter `vb`. If the parameter value is a null pointer, this method does nothing.

Parameters

vb

Pointer to the object reference for the `valuetype` instance.

Unlike the `_remove_ref()` method, `remove_ref()` can be called with null `valuetype` pointers.

See Also CORBA::add_ref()

```
CORBA::ValueBase::_remove_ref()
CORBA::ValueBase::_add_ref()
```

CORBA::string_alloc()

```
char *string_alloc(ULong len);
```

Dynamically allocates a string. The method returns a pointer to the start of the character array. It returns a zero pointer if it cannot perform the allocation. A conforming program should use this method to dynamically allocate a string that is passed between a client and a server.

Parameters

len

A string of length len + 1 is allocated.

See Also CORBA::string_free()

```
CORBA::string_dup()
```

CORBA::string_dup()

```
char* string_dup(const char* str);
```

Duplicates a string. The method returns a duplicate of the input string or it returns a zero pointer if it is unable to perform the duplication. CORBA::string_alloc() can be used to allocate space for the string.

Parameters

str

The string to be duplicated.

See Also CORBA::string_alloc()

```
CORBA::string_free()
```

CORBA::string_free()

```
void string_free(char* str);
```

Deallocates a string that was previously allocated using CORBA::string_alloc().

Parameters

`str`

The string to be freed.

See Also `CORBA::string_alloc()`

`CORBA::string_dup()`

Common CORBA Data Types

This chapter contains details of all common CORBA data types. [Table 3](#) consists of descriptions of the primitive C++ data types such as `Short`, `Long`, and so on. The following alphabetically ordered list contains a link to the details of each data type:

AnySeq	InvalidPolicies	ServiceOption
AttrDescriptionSeq	ModuleDescription	ServiceType
AttributeDescription	OctetSeq	SetOverrideType
AttributeMode	OpDescriptionSeq	ShortSeq
BooleanSeq	OperationDescription	StringValue
CharSeq	OperationMode	StructMember
ConstantDescription	ORBid	StructMembersSeq
ContainedSeq	ParameterDescription	TCKind
ContextIdentifier	ParameterMode	TypeDescription
ContextIdSeq	ParDescriptionSeq	ULongLongSeq
DefinitionKind	PolicyError	ULongSeq
DomainManagersList	PolicyErrorCode	UnionMember
DoubleSeq	PolicyList	UnionMemberSeq
EnumMemberSeq	PolicyType	UShortSeq
ExcDescriptionSeq	PolicyTypeSeq	ValueDefSeq
ExceptionDefSeq	PrimitiveKind	ValueDescription
ExceptionDescription	#p_d1956e1_d1957e1_d1958e1_d1959e1	ValueMember
Flags	RepositoryId	ValueMemberSeq
FloatSeq	RepositoryIdSeq	ValueModifier
Identifier	ScopedName	VersionSpec
Initializer	ServiceDetail	Visibility
InitializerSeq	ServiceDetailType	WCharSeq
InterfaceDefSeq	ServiceInformation	WStringValue
InterfaceDescription		

Primitive C++ types are defined as shown in [Table 3](#):

Table 3: Primitive C++ Data Types

Primitive C++ Type	C++ Definition
Boolean	<code>typedef unsigned char Boolean;</code> (Valid values are 1 for true or 0 for false.)
Boolean_out	<code>typedef Boolean& Boolean_out;</code>
Char	<code>typedef unsigned char Char;</code>
Char_out	<code>typedef Char& Char_out;</code>
Double	<code>typedef double Double;</code>
Double_out	<code>typedef Double& Double_out;</code>
Float	<code>typedef float Float;</code>
Float_out	<code>typedef Float& Float_out;</code>
Long	<code>typedef long Long;</code>
Long_out	<code>typedef Long& Long_out;</code>
LongDouble	<code>typedef long double LongDouble;</code>
LongDouble_out	<code>typedef LongDouble& LongDouble_out;</code>
LongLong	<code>typedef ... LongLong;</code>
LongLong_out	<code>typedef LongLong& LongLong_out;</code>
Octet	<code>typedef unsigned char Octet;</code>
Octet_out	<code>typedef Octet& Octet_out;</code>
Short	<code>typedef short Short;</code>
Short_out	<code>typedef Short& Short_out;</code>
ULong	<code>typedef unsigned long ULong;</code>
ULong_out	<code>typedef ULong& ULong_out;</code>
ULongLong	<code>typedef ... ULongLong;</code>
ULongLong_out	<code>typedef ULongLong& ULongLong_out;</code>

Primitive C++ Type	C++ Definition
UShort	<code>typedef unsigned short UShort;</code>
UShort_out	<code>typedef UShort& UShort_out;</code>
WChar	<code>typedef wchar_t WChar;</code>
WChar_out	<code>typedef WChar& WChar_out;</code>

CORBA::AnySeq Sequence

```
//IDL
typedef sequence<any> AnySeq;
```

```
//C++
```

```
class AnySeq {
    ...
};
```

A sequence of `Any` data values used for marshalling custom value types.

See Also `CORBA::DataOutputStream`

```
CORBA::DataInputStream
```

About Sequences

CORBA::AttrDescriptionSeq Sequence

```
//IDL
typedef sequence <AttributeDescription> AttrDescriptionSeq;
```

```
// C++
```

```
class AttrDescriptionSeq {
    ...
};
```

A sequence of AttributeDescription structures in the interface repository.

See Also CORBA::AttributeDescription

About Sequences

CORBA::AttributeDescription Structure

```
// IDL
struct AttributeDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
    AttributeMode mode;
};
```

```
struct AttributeDescription {
```

```
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
    AttributeMode mode;
};
```

The description of an interface attribute in the interface repository.

name	The name of the attribute.
id	The identifier of the attribute.
defined_in	The identifier of the interface in which the attribute is defined.
version	The version of the attribute.

<code>type</code>	The data type of the attribute.
<code>mode</code>	The mode of the attribute.

See Also CORBA::AttributeDef

CORBA::AttributeMode Enumeration

// IDL

```
enum AttributeMode {ATTR_NORMAL, ATTR_READONLY};
```

// C++

```
enum AttributeMode {ATTR_NORMAL, ATTR_READONLY};
typedef AttributeMode& AttributeMode_out;
```

The mode of an attribute in the interface repository.

<code>ATTR_NORMAL</code>	Mode is read and write.
<code>ATTR_READONLY</code>	Mode is read-only.

See Also CORBA::AttributeDef

CORBA::BooleanSeq Sequence

```
// IDL
typedef sequence<boolean> BooleanSeq;
```

// C++

```
class BooleanSeq {
    ...
};
```

A sequence of Boolean values used in marshalling custom value types.

See Also CORBA::DataOutputStream

CORBA::DataInputStream

About Sequences

CORBA::CharSeq Sequence

```
// IDL
typedef sequence<char> CharSeq;
```

// C++

```
class CharSeq {
    ...
};
```

A sequence of character (`char`) values used in marshalling custom value types.

See Also CORBA::DataOutputStream

CORBA::DataInputStream

About Sequences

CORBA::CompletionStatus Enumeration

// C++

```
enum CompletionStatus {
    COMPLETED_YES,
    COMPLETED_NO,
    COMPLETED_MAYBE
};
```

CORBA::ConstantDescription Structure

```
// IDL
struct ConstantDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
    any value;
};
```

// C++

```
struct ConstantDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
    any value;
};
```

The description of a constant in the interface repository.

name	The name of the constant.
id	The identifier of the constant.
defined_in	The identifier of the interface in which the constant is defined.
version	The version of the constant.
type	The data type of the constant.
value	The value of the constant.

See Also CORBA :: ConstantDef

CORBA::ContainedSeq Sequence

```
// IDL
typedef sequence <Contained> ContainedSeq;
```

```
// C++
```

```
class ContainedSeq {
    ...
};
```

A sequence of Contained objects in the interface repository.

See Also CORBA::Contained

[About Sequences](#)

CORBA::ContextIdentifier Type

```
// IDL
typedef Identifier ContextIdentifier;
```

```
// C++
```

```
typedef Identifier ContextIdentifier;
```

A context identifier used in an IDL operation in the interface repository.

An IDL operation's context expression specifies which elements of the client's context might affect the performance of a request by the object. The runtime system makes the context values in the client's context available to the object implementation when the request is delivered.

See Also CORBA::OperationDef

```
CORBA::ContextIdSeq
```

CORBA::ContextIdSeq Sequence

```
// IDL
typedef sequence <ContextIdentifier> ContextIdSeq;
```

```
// C++
```

```
class ContextIdSeq {
    ...
};
```

A sequence of ContextIdentifier values in the interface repository.

See Also CORBA :: ContextIdentifier

[About Sequences](#)

CORBA::DefinitionKind Enumeration

```
// IDL
```

```

enum DefinitionKind {
    dk_none, dk_all,
    dk_Attribute, dk_Constant, dk_Exception, dk_Interface,
    dk_Module, dk_Operation, dk_Typedef,
    dk_Alias, dk_Struct, dk_Union, dk_Enum,
    dk_Primitive, dk_String, dk_Sequence, dk_Array,
    dk_Repository,
    dk_Wstring, dk_Fixed,
    dk_Value, dk_ValueBox, dk_ValueMember,
    dk_Native
};
// C++
enum DefinitionKind {
    dk_none, dk_all,
    dk_Attribute, dk_Constant, dk_Exception, dk_Interface,
    dk_Module, dk_Operation, dk_Typedef,
    dk_Alias, dk_Struct, dk_Union, dk_Enum,
    dk_Primitive, dk_String, dk_Sequence, dk_Array,
    dk_Repository,
    dk_Wstring, dk_Fixed,
    dk_Value, dk_ValueBox, dk_ValueMember,
    dk_Native
};
typedef DefinitionKind& DefinitionKind_out;

```

Identifies the type of an interface repository object.

Each interface repository object has an attribute (`CORBA::IObject::def_kind`) of the type `DefinitionKind` that records the kind of the IFR object. For example, the `def_kind` attribute of an `InterfaceDef` object is `dk_interface`. The enumeration constants `dk_none` and `dk_all` have special meanings when searching for an object in a repository.

See Also `CORBA::IObject::def_kind`

```

CORBA::Contained
CORBA::Container

```

`CORBA::DomainManagersList` Sequence

```
// IDL
typedef sequence <DomainManager> DomainManagersList;
```

```
// C++
```

```
class DomainManagersList {
    ...
};
```

A sequence of DomainManager objects.

See Also CORBA::DomainManager

[About Sequences](#)

CORBA::DoubleSeq Sequence

```
// IDL
typedef sequence<double> DoubleSeq;
```

```
// C++
```

```
class DoubleSeq {
    ...
};
```

A sequence of Double values used in marshalling custom value types.

See Also CORBA::DataOutputStream

```
CORBA::DataInputStream
```

[About Sequences](#)

CORBA::EnumMemberSeq Sequence

```
// IDL
typedef sequence <Identifier> EnumMemberSeq;
```

```
// C++
```

```
class EnumMemberSeq {
    ...
};
```

A sequence of Identifier strings representing the members of an enumeration type in the interface repository.

See Also `CORBA::Identifier`

```
CORBA::ORB::create_enum_tc()
```

About Sequences

`CORBA::ExcDescriptionSeq` Sequence

```
// IDL
typedef sequence <ExceptionDescription> ExcDescriptionSeq;
```

```
// C++
```

```
class ExcDescriptionSeq {
    ...
};
```

A sequence of ExceptionDescription structures in the interface repository. This sequence is used only in the OperationDescription structure.

See Also `CORBA::ExceptionDescription`

```
CORBA::OperationDescription
```

About Sequences

CORBA::ExceptionDefSeq Sequence

```
// IDL
typedef sequence <ExceptionDef> ExceptionDefSeq;
```

```
// C++
```

```
class ExceptionDefSeq {
    ...
};
```

A sequence of ExceptionDef objects in the interface repository.

See Also CORBA::ExceptionDef

[About Sequences](#)

CORBA::ExceptionDescription

```
// C++
```

```
struct ExceptionDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
};
```

The description of an exception in the interface repository.

name	The name of the exception.
id	The identifier of the exception.
defined_in	The identifier of the interface in which the exception is defined.
version	The version of the exception.
type	The data type of the exception.

See Also CORBA::ExcDescriptionSeq

CORBA::ExceptionType Enumeration

```
// IDL
enum exception_type {
    NO_EXCEPTION,
    USER_EXCEPTION,
    SYSTEM_EXCEPTION};
```

CORBA::Flags Type

```
// IDL
typedef unsigned long Flags;
typedef string Identifier;
const Flags ARG_IN = 1;
const Flags ARG_OUT = 2;
const Flags ARG_INOUT = 3;
const Flags CTX_RESTRICT_SCOPE = 15;
```

//C++

```
typedef ULong Flags;
```

A flag value is a bitmask `long` used to identify one or more modes.

Most flag values identify the argument passing mode for arguments. The common argument passing flag values include:

<code>ARG_IN</code>	Indicates that the associated value is an input-only argument.
<code>ARG_INOUT</code>	Flag value indicating that the associated value is an input or output argument.
<code>ARG_OUT</code>	Flag value indicating that the associated value is an output-only argument.

Other flag values have specific meanings for request and list methods.

NVList methods that add a NamedValue to an NVList have a `flags` parameter used to specify features of an argument. These additional flag values include:

<code>IN_COPY_VAL</code> <code>UE</code>	Causes a copy of the argument value to be made and used instead of the argument.

<code>DEPENDENT_LIST</code>	If a list structure is added as an item such as in a sublist, this flag indicates that the sublist should be freed when the parent list is freed.

The Object `::_create_request()` method has a request flags parameter used to specify how storage is to be allocated for output parameters. The additional flag value is:

<code>OUT_LIST_MEMORY</code>	Indicates that any out argument memory is associated with the argument list of the requested IDL operation.

See Also `CORBA::NVList`

```
CORBA::NamedValue
CORBA::Object::_create_request()
CORBA::Context::get_values()
```

`CORBA::FloatSeq` Sequence

```
// IDL
typedef sequence<float> FloatSeq;
```

// C++

```
class FloatSeq {
    ...
};
```

A sequence of Float values used in marshalling custom value types.

See Also `CORBA::DataOutputStream`

```
CORBA::DataInputStream
```

[About Sequences](#)

`CORBA::Identifier` Type

// C++

```
typedef char* Identifier;
```

A simple name that identifies modules, interfaces, constants, typedefs, exceptions, attributes, and operations in the interface repository. An identifier is not necessarily unique within the entire interface repository; it is unique only within a particular Repository, ModuleDef, InterfaceDef, or OperationDef.

CORBA::Initializer Structure

```
// IDL
struct Initializer {
    StructMemberSeq members;
    Identifier name;
};
```

// C++

```
struct Initializer {
    StructMemberSeq members;
    Identifier name;
};
```

An initializer structure for a sequence in the interface repository.

members	The sequence of structure members.
name	The name of the initializer structure.

See Also CORBA::InitializerSeq

CORBA::InitializerSeq Sequence

// C++

```
class InitializerSeq {
    ...
};
```

A sequence of Initializer structures in the interface repository.

See Also CORBA::ValueDef

About Sequences

CORBA::InterfaceDefSeq Sequence

// C++

```
class InterfaceDefSeq {
    ...
};
```

A sequence of interface definitions in the interface repository.

See Also CORBA::InterfaceDef

```
CORBA::Container::create_interface()
CORBA::Container::create_value()
```

About Sequences

CORBA::InterfaceDescription Structure

```
// IDL
struct InterfaceDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    RepositoryIdSeq base_interfaces;
    boolean is_abstract;
};
```

// C++

```
struct InterfaceDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    RepositoryIdSeq base_interfaces;
    boolean is_abstract;
};
```

A description of an interface in the interface repository. This structure is returned by the inherited `describe()` method in the `InterfaceDef` interface. The structure members consist of the following:

<code>name</code>	The name of the interface.
<code>id</code>	The identifier of the interface.
<code>defined_in</code>	The identifier of where the interface is defined.
<code>version</code>	The version of the interface.
<code>base_interfaces</code>	The sequence of base interfaces from which this interface is derived.
<code>is_abstract</code>	A true value if the interface is an abstract one, a false value otherwise.

See Also `CORBA::InterfaceDef::describe()`

CORBA::InvalidPolicies Exception

// IDL

```
exception InvalidPolicies {
    sequence <unsigned short> indices;
};
```

This exception is thrown by operations that are passed a bad policy. The indicated policies, although valid in some circumstances, are not valid in conjunction with other policies requested or already overridden at this scope.

CORBA::ModuleDescription Structure

```
// IDL
struct ModuleDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
};
struct ModuleDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
};
```

The description of an IDL module in the interface repository. The structure members consist of the following:

<code>name</code>	The name of the module.
<code>id</code>	The identifier of the module.
<code>defined_in</code>	The identifier of where the module is defined.
<code>version</code>	The version of the module.

See Also `CORBA::ModuleDef`

`CORBA::OctetSeq` Sequence

// C++

```
class OctetSeq {
    ...
};
```

A sequence of Octet values used in marshalling custom value types.

See Also `CORBA::DataOutputStream`

```
CORBA::DataInputStream
```

About Sequences

CORBA::OpDescriptionSeq Sequence

// C++

```
class OpDescriptionSeq {
    ...
};
```

A sequence of OperationDescription structures in the interface repository that describe each IDL operation of an interface or value type.

See Also CORBA::OperationDescription

```
CORBA::InterfaceDef::FullInterfaceDescription
CORBA::ValueDef::FullValueDescription
```

About Sequences

CORBA::OperationDescription Structure

```
// IDL
struct OperationDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode result;
    OperationMode mode;
    ContextIdSeq contexts;
    ParDescriptionSeq parameters;
    ExcDescriptionSeq exceptions;
};
```

```
struct OperationDescription {
```

```

Identifier name;
RepositoryId id;
RepositoryId defined_in;
VersionSpec version;
TypeCode result;
OperationMode mode;
ContextIdSeq contexts;
ParDescriptionSeq parameters;
ExcDescriptionSeq exceptions;
};

```

This structure describes an IDL operation in the interface repository. The structure members consist of the following:

<code>name</code>	The name of the IDL operation.
<code>id</code>	The identifier of the IDL operation.
<code>defined_in</code>	The identifier of where the IDL operation is defined.
<code>version</code>	The version of the IDL operation.
<code>result</code>	The TypeCode of the result returned by the defined IDL operation.
<code>mode</code>	Specifies whether the IDL operation's mode is normal (OP_NORMAL) or one-way (OP_ONEWAY).
<code>contexts</code>	The sequence of context identifiers specified in the context clause of the IDL operation.
<code>parameters</code>	The sequence of structures that give details of each parameter of the IDL operation.
<code>exceptions</code>	The sequence of structures containing details of exceptions specified in the <code>raises</code> clause of the IDL operation.

See Also CORBA::OpDescriptionSeq

CORBA::OperationMode Enumeration

```
enum OperationMode {OP_NORMAL, OP_ONEWAY};
```



```
typedef OperationMode& OperationMode_out;
```

The mode of an IDL operation in the interface repository. An operation's mode indicates its invocation semantics.

<code>OP_NORMAL</code>	The IDL operation's invocation mode is normal.
<code>OP_ONeway</code>	The IDL operation's invocation mode is oneway which means the operation is invoked only once with no guarantee that the call is delivered.

CORBA::ORBid Type

```
// IDL
typedef string ORBid;
// C++
typedef char* ORBid;
```

The name that identifies an ORB. `ORBid` strings uniquely identify each ORB used within the same address space in a multi-ORB application. `ORBid` strings (except the empty string) are not managed by the OMG but are allocated by ORB administrators who must ensure that the names are unambiguous.

See Also `CORBA::ORB_init()`

CORBA::ParameterDescription Structure

```
// IDL
struct ParameterDescription {
    Identifier name;
    TypeCode type;
    IDLType type_def;
    ParameterMode mode;
};
```

```
struct ParameterDescription {
```

```

    Identifier name;
    TypeCode type;
    IDLType type_def;
    ParameterMode mode;
};

```

This structure describes an IDL operation's parameter in the interface repository. The structure members consist of the following:

<code>name</code>	The name of the parameter.
<code>type</code>	The TypeCode of the parameter.
<code>type_def</code>	Identifies the definition of the type for the parameter.
<code>mode</code>	Specifies whether the parameter is an in input, output, or input and output parameter.

See Also CORBA::ParDescriptionSeq

CORBA::ParameterMode Enumeration

```
enum ParameterMode {PARAM_IN, PARAM_OUT, PARAM_INOUT};
```

```
typedef ParameterMode& ParameterMode_out;
```

The mode of an IDL operation's parameter in the interface repository.

<code>PARAM_IN</code>	The parameter is passed as input only.
<code>PARAM_OUT</code>	The parameter is passed as output only.
<code>PARAM_INOUT</code>	The parameter is passed as both input and output.

CORBA::ParDescriptionSeq Sequence

```
// C++
```

```
class ParDescriptionSeq {
    ...
};
```

A sequence of ParameterDescription structures in the interface repository.

See Also CORBA::ParameterDescription

```
CORBA::OperationDef
CORBA::OperationDescription
CORBA::InterfaceDef
CORBA::ValueDef
```

About Sequences

CORBA::PolicyError Exception

// IDL

```
exception PolicyError {
    PolicyErrorCode reason;
};
```

The `PolicyError` exception is thrown to indicate problems with parameter values passed to `ORB::create_policy()`. Possible reasons are described in the `PolicyErrorCode`.

See Also CORBA::ORB::create_policy()

```
CORBA::PolicyErrorCode
```

CORBA::PolicyErrorCode Type

```
typedef short PolicyErrorCode;
```

// C++

```
typedef Short PolicyErrorCode;
```

A value representing an error when creating a new Policy. The following constants are defined to represent the reasons a request to create a Policy might be invalid:

Table 4: PolicyErrorCode Constants

Constant	Explanation
BAD_POLICY	The requested Policy is not understood by the ORB.
UNSUPPORTED_POLICY	The requested Policy is understood to be valid by the ORB, but is not currently supported.
BAD_POLICY_TYPE	The type of the value requested for the Policy is not valid for that PolicyType.
BAD_POLICY_VALUE	The value requested for the Policy is of a valid type but is not within the valid range for that type.
UNSUPPORTED_POLICY_VALUE	The value requested for the Policy is of a valid type and within the valid range for that type, but this valid value is not currently supported.

See Also CORBA::ORB::create_policy()

CORBA::PolicyList Sequence

// C++

```
class PolicyList {
    ...
};
```

A list of Policy objects. Policies affect an ORB's behavior.

See Also CORBA::Policy

```
CORBA::Object::set_policy_overrides()
PortableServer::POA::POA_create_POA()
```

About Sequences

CORBA::PolicyType Type

// C++

```
typedef ULong PolicyType;
```

Defines the type of Policy object.

The CORBA module defines the following constant `PolicyType`:

```
// IDL
const PolicyType SecConstruction = 11;
// C++
static const PolicyType SecConstruction = 11;
```

Other valid constant values for a `PolicyType` are described with the definition of the corresponding Policy object. There are standard OMG values and Orbix-specific values.

See Also `CORBA::Policy`

```
CORBA::PolicyTypeSeq
CORBA::ORB::create_policy()
CORBA::Object::_get_policy()
CORBA::DomainManager::get_domain_policy()
```

`CORBA::PolicyTypeSeq` Sequence

```
// IDL
typedef sequence<PolicyType> PolicyTypeSeq;
```

// C++

```
class PolicyTypeSeq {
    ...
};
```

A sequence of `PolicyType` data types.

See Also `CORBA::Object::get_policy_overrides()`

```
CORBA::PolicyManager::get_policy_overrides()
```

CORBA::PrimitiveKind Enumeration

// IDL

```
enum PrimitiveKind {
    pk_null, pk_void, pk_short, pk_long, pk_ushort, pk_ulong,
    pk_float, pk_double, pk_boolean, pk_char, pk_octet,
    pk_any, pk_TypeCode, pk_Principal, pk_string, pk_objref,
    pk_longlong, pk_ulonglong, pk_longdouble,
    pk_wchar, pk_wstring, pk_value_base
};
typedef PrimitiveKind& PrimitiveKind_out;
```

Indicates the kind of primitive type a PrimitiveDef object represents in the interface repository.

Most kinds are self explanatory with the exception of the following:

- There are no PrimitiveDef objects with the kind `pk_null`.
- The kind `pk_string` represents an unbounded string.
- The kind `pk_objref` represents the IDL type Object.
- The kind `pk_value_base` represents the IDL type ValueBase.

See Also CORBA::PrimitiveDef

```
CORBA::Repository
```

CORBA::RepositoryId Type

// C++

```
typedef char* RepositoryId;
```

A string that uniquely identifies, in the interface repository, an IDL module, interface, constant, typedef, exception, attribute, value type, value member, value box, native type, or operation.

The format of `RepositoryId` types is a short format name followed by a colon followed by characters, as follows:

```
format_name:string
```

The most common format encountered is the OMG IDL format. For example:

```
IDL:Pre/B/C:5.3
```

This format contains three components separated by colons:

IDL	The first component is the format name, IDL .
Pre/B/C	The second component is a list of identifiers separated by '/' characters that uniquely identify a repository item and its scope. These identifiers can contain other characters including underscores (_), hyphens (-), and dots (.).
5.3	The third component contains major and minor version numbers separated by a dot (.).

See Also CORBA::Repository::lookup_id()

CORBA::RepositoryIdSeq Sequence

// C++

```
class RepositoryIdSeq {
    ...
};
```

A sequence of RepositoryId strings in the interface repository.

See Also CORBA::RepositoryId

[About Sequences](#)

CORBA::ScopedName Type

// C++

```
typedef char* ScopedName;
```

A string that specifies an IDL item's name relative to a scope in the interface repository. A

ScopedName correspond to an OMG IDL scoped name.

Examples A ScopedName that begins with "::" is an absolute scoped name; one that uniquely identifies an item within a repository. For example:

```
::Account::makeWithdrawal
```

A `ScopedName` that does not begin with “`::`” is a relative scoped name; one that identifies an item relative to some other item. For example:

```
makeWithdrawal
```

This example would be within the absolute scoped name of `::Account`.

See Also `CORBA::Contained::absolute_name`

```
CORBA::Container::lookup()
```

`CORBA::ServiceDetail` Structure

// IDL

```
struct ServiceDetail {
    ServiceDetailType service_detail_type;
    sequence <Octet> service_detail;
};
```

Detailed information about a single service or facility available to an ORB. Structure members consist of:

<code>service_detail_type</code>
<code>service_detail</code>

See Also `CORBA::ServiceInformation`

`CORBA::ServiceDetailType` Type

// C++

```
typedef ULong ServiceDetailType;
```

The type of service.

See Also `CORBA::ServiceDetail`

`CORBA::ServiceInformation` Structure


```
//IDL
```

```
struct ServiceInformation {
    sequence <ServiceOption> service_options;
    sequence <ServiceDetail> service_details;
};
```

Information about CORBA facilities and services that are supported by an ORB. Structure members consist of:

service_options
service_details

See Also CORBA::ORB::get_service_information()

CORBA::ServiceOption Type

```
// C++
typedef ULong ServiceOption;
```

An option for a service.

See Also CORBA::ServiceInformation

CORBA::ServiceType Type

```
typedef UShort ServiceType;
```

Used as a parameter in get_service_information() to obtain information about CORBA facilities and services that are supported by an ORB. A possible value consists of:

```
Security = 1
```

CORBA::SetOverrideType Enumeration

```
// IDL
```

```
enum SetOverrideType {SET_OVERRIDE, ADD_OVERRIDE};
```

The type of override to use in the **set_policy_overrides()** method when setting new policies for an object reference. Possible types consist of:

<code>SET_OVERRIDE</code>	Indicates that new policies are to be associated with an object reference.
<code>ADD_OVERRIDE</code>	Indicates that new policies are to be added to the existing set of policies and overrides for an object reference.

See Also `CORBA::Object::_set_policy_overrides()`

`CORBA::ShortSeq` Sequence

// C++

```
class ShortSeq {
    ...
};
```

A sequence of Short values used in marshalling custom value types.

See Also `CORBA::DataOutputStream`

`CORBA::DataInputStream`

[About Sequences](#)

`CORBA::StringValue` Value Box

// C++

```

class StringValue : public DefaultValueRefCountBase {
public:
    // constructors
    StringValue();
    StringValue(const StringValue& val);
    StringValue(char* str);
    StringValue(const char* str);
    StringValue(const String_var& var);
    // assignment operators
    StringValue& operator=(char* str);
    StringValue& operator=(const char* str);
    StringValue& operator=(const String_var& var);
    // accessor
    const char* _value() const;
    // modifiers
    void _value(char* str);
    void _value(const char* str);
    void _value(const String_var& var);
    // explicit argument passing conversions for underlying string
    const char* _boxed_in() const;
    char*& _boxed_inout();
    char*& _boxed_out();
    // ...other String_var methods such as overloaded
    // subscript operators, etc....
    static StringValue* _downcast(ValueBase* base);
protected:
    ~StringValue();
    ...
};

```

`StringValue` is a value box class that provides a reference-counted version of a string.

See Also

[About Sequences](#)

CORBA::StructMember Structure

// C++

```
struct StructMember {
    Identifier name;
    TypeCode type;
    IDLType type_def;
};
```

This describes an IDL structure member in the interface repository. The structure members consist of the following:

name	The name of the member.
type	The TypeCode for the member.
type_def	Identifies the definition of the type for the member.

See Also CORBA::StructMemberSeq

CORBA::StructMemberSeq Sequence

// C++

```
class StructMemberSeq {
    ...
};
```

A sequence of StructMember objects in the interface repository.

See Also CORBA::StructMember

```
CORBA::ORB::create_struct_tc()
CORBA::ORB::create_exception_tc()
CORBA::Container::create_struct()
CORBA::Container::create_exception()
CORBA::StructDef::members
CORBA::ExceptionDef::members
CORBA::Initializer
```

[About Sequences](#)

CORBA::TCKind Enumeration

// IDL

```
enum TCKind {
    tk_null, tk_void,
    tk_short, tk_long, tk_ushort, tk_ulong,
    tk_float, tk_double, tk_boolean, tk_char,
    tk_octet, tk_any, tk_TypeCode, tk_Principal, tk_objref,
    tk_struct, tk_union, tk_enum, tk_string,
    tk_sequence, tk_array, tk_alias, tk_except,
    tk_longlong, tk_ulonglong, tk_longdouble,
    tk_wchar, tk_wstring, tk_fixed,
    tk_value, tk_value_box,
    tk_native,
    tk_abstract_interface
};
```

A `TCKind` value indicates the kind of data type for a `TypeCode`. A `TypeCode` is a value that represent an invocation argument type or attribute type, such as that found in the interface repository or with a dynamic `any` type.

See Also `CORBA::TypeCode::kind()`

```
DynamicAny::DynStruct::current_member_kind()
DynamicAny::DynUnion::discriminator_kind()
DynamicAny::DynUnion::member_kind()
DynamicAny::DynValue::current_member_kind()
```

CORBA::TypeDescription Structure

```
// IDL
struct TypeDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
};
```

```
// C++
```

```
struct TypeDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
};
```

This structure describes an IDL data type in the interface repository. The structure members consist of the following:

<code>name</code>	The name of the data type.
<code>id</code>	The identifier for the data type.
<code>defined_in</code>	The identifier of where the data type is defined.
<code>version</code>	The version of the data type.
<code>type</code>	The TypeCode of the data type.

CORBA::ULongLongSeq Sequence

// C++

```
class ULongLongSeq {
    ...
};
```

A sequence of ULongLong values used in marshalling custom value types.

See Also CORBA::DataOutputStream

CORBA::DataInputStream

[About Sequences](#)

CORBA::ULongSeq Sequence

// C++

```
class ULongSeq {
    ...
};
```

A sequence of ULong values used in marshalling custom value types.

See Also CORBA::DataOutputStream

CORBA::DataInputStream

About Sequences

CORBA::UnionMember Structure

```
// IDL
struct UnionMember {
    Identifier name;
    any label;
    TypeCode type;
    IDLType type_def;
};
```

// C++

```
struct UnionMember {
    Identifier name;
    any label;
    TypeCode type;
    IDLType type_def;
};
```

This structure describes an IDL union member in the interface repository. The structure members consist of the following:

<code>name</code>	The name of the union member.
<code>label</code>	The label of the union member.
<code>type</code>	The TypeCode of the union member.

<code>type_def</code>	The IDL data type of the union member.

See Also CORBA::UnionMemberSeq

CORBA::UnionMemberSeq Sequence

// C++

```
class UnionMemberSeq {
    ...
};
```

A sequence of UnionMember structures in the interface repository.

See Also CORBA::UnionMember

```
CORBA::ORB::create_union_tc()
CORBA::Container::create_union()
CORBA::UnionDef::members
```

[About Sequences](#)

CORBA::UShortSeq Sequence

// C++

```
class UShortSeq {
    ...
};
```

A sequence of UShort values used in marshalling custom value types.

See Also CORBA::DataOutputStream

CORBA::DataInputStream

[About Sequences](#)

CORBA::ValueDefSeq Sequence

// C++


```
class ValueDefSeq {
    ...
};
```

A sequence of ValueDef objects in the interface repository.

See Also CORBA::ValueDef

```
CORBA::Container::create_value()
```

[About Sequences](#)

CORBA::ValueDescription Structure

```
// IDL
struct ValueDescription {
    Identifier name;
    RepositoryId id;
    boolean is_abstract;
    boolean is_custom;
    RepositoryId defined_in;
    VersionSpec version;
    RepositoryIdSeq supported_interfaces;
    RepositoryIdSeq abstract_base_values;
    boolean is_truncatable;
    RepositoryId base_value;
};
```

```
struct ValueDescription {
```

```

    Identifier name;
    RepositoryId id;
    Boolean is_abstract;
    Boolean is_custom;
    RepositoryId defined_in;
    VersionSpec version;
    RepositoryIdSeq supported_interfaces;
    RepositoryIdSeq abstract_base_values;
    Boolean is_truncatable;
    RepositoryId base_value;
};

```

The description of an IDL value type in the interface repository. Value types enable the passing of objects by value rather than just passing by reference. The structure members consist of the following:

<code>name</code>	The name of the value type.
<code>id</code>	The identifier of the value type.
<code>is_abstract</code>	True if the value type is abstract. False if the value type is not abstract.
<code>is_custom</code>	True if the value type is custom. False if the value type is not custom.
<code>defined_in</code>	The identifier of where the value type is defined.
<code>version</code>	The version of the value type.
<code>supported_interfaces</code>	
<code>abstract_base_values</code>	
<code>is_truncatable</code>	
<code>base_value</code>	

See Also `CORBA::ValueDef::describe()`

`CORBA::ValueMember` Structure

```
// IDL
struct ValueMember {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
    IDLType type_def;
    Visibility access;
};
```

```
// C++
```

```
struct ValueMember {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    TypeCode type;
    IDLType type_def;
    Visibility access;
};
```

This structure describes an IDL value type member in the interface repository. The structure members consist of the following:

<code>name</code>	The name of the value type member.
<code>id</code>	The identifier of the value type member.
<code>defined_in</code>	The identifier of where the value type member is defined.
<code>version</code>	The version of the value type member.
<code>type</code>	The TypeCode of the value type member.
<code>type_def</code>	The type definition of the value type member.
<code>access</code>	The accessibility of the value type member (public or private).

See Also CORBA::ValueMemberSeq

CORBA::ValueMemberSeq Sequence

```
// C++
```

```
class ValueMemberSeq {
    ...
};
```

A sequence of `ValueMember` structures in the interface repository.

See Also `CORBA::ValueMember`

```
CORBA::ORB::create_value_tc()
```

About Sequences

`CORBA::ValueModifier` Type

```
typedef Short ValueModifier;
```

A modifier for an IDL value type in the interface repository. Possible values consist of:

<code>VM_NONE</code>	The IDL value type has no modifiers.
<code>VM_CUSTOM</code>	The IDL value type has the <code>custom</code> modifier. This specifies that the value type uses custom marshalling.
<code>VM_ABSTRACT</code>	The IDL value type has the <code>abstract</code> modifier. Value types that are abstract can not be instantiated. Essentially they are a bundle of IDL operation signatures with a purely local implementation.
<code>VM_TRUNCATABLE</code>	The IDL value type has the <code>truncatable</code> modifier. A value with a state that derives from another value with a state can be specified as truncatable. A truncatable type means the object can be truncated to the base type.

See Also `CORBA::ORB::create_value_tc()`

```
CORBA::TypeCode::type_modifier()
```

`CORBA::VersionSpec` Type

```
// C++
```

```
typedef char* VersionSpec;
```

A string that describes a version of an IDL item in the interface repository. Version information can be associated with many IDL data types including modules, constants, types, exceptions, attributes, and operations.

See Also CORBA::Contained::version

```
CORBA::Contained::move()
CORBA::Container
```

CORBA::Visibility Type

```
typedef Short Visibility;
```

Indicates the visibility of a state member of an IDL value type in the interface repository. Possible values consist of:

```
PRIVATE_MEMBER
PUBLIC_MEMBER
```

IDL value types can have state members that are either public or private. Private members are not visible to clients but are only visible to implementation code and the marshalling routines.

See Also CORBA::ValueMember

```
CORBA::ValueMemberDef::access
CORBA::ValueDef::create_value_member()
CORBA::TypeCode::member_visibility()
```

CORBA::WCharSeq Sequence

```
// C++
```

```
class WCharSeq {
    ...
};
```

A sequence of WChar values used in marshalling custom value types.

See Also CORBA::DataOutputStream

CORBA::DataInputStream

[About Sequences](#)

CORBA::WStringValue Value Box

// C++

```

class WStringValue : public DefaultValueRefCountBase {
public:
    // constructors
    WStringValue();
    WStringValue(const WStringValue& val);
    WStringValue(char* str);
    WStringValue(const char* str);
    WStringValue(const String_var& var);
    // assignment operators
    WStringValue& operator=(char* str);
    WStringValue& operator=(const char* str);
    WStringValue& operator=(const String_var& var);
    // accessor
    const char* _value() const;
    // modifiers
    void _value(char* str);
    void _value(const char* str);
    void _value(const String_var& var);
    // explicit argument passing conversions for underlying string
    const char* _boxed_in() const;
    char*& _boxed_inout();
    char*& _boxed_out();
    // ...other String_var methods such as overloaded
    // subscript operators, etc....
    static WStringValue* _downcast(ValueBase* base);
protected:
    ~WStringValue();
    ...
};

```

`WStringValue` is a value box class that provides a reference-counted version of a wide string.

See Also[About Value Boxes](#)

CORBA::AliasDef Interface

The `AliasDef` interface describes an IDL typedef that aliases another definition in the interface repository. It is used to represent an IDL `typedef`.

```
// IDL in module CORBA.
interface AliasDef : TypedefDef {
    attribute IDLType original_type_def;
};
```

The following items are described for this interface:

- The `describe()` IDL operation
- The `original_type_def` attribute

See Also `CORBA::Contained`

```
CORBA::Container::create_alias()
```

```
AliasDef::describe()
```

```
// IDL
```

```
Description describe();
```

Inherited from `Contained` (which is inherited by `TypedefDef`), the `describe()` operation returns a structure of type `Contained::Description`. The `DefinitionKind` for the `kind` member is `dk_Alias`. The `value` member is an `any` whose `TypeCode` is `_tc_AliasDescription` and whose value is a structure of type `TypeDescription`.

See Also `CORBA::TypedefDef::describe()`

`AliasDef::original_type_def` Attribute

```
// IDL
```

```
attribute IDLType original_type_def;
```

Identifies the type being aliased. Modifying the `original_type_def` attribute will automatically update the `type` attribute (the `type` attribute is inherited from `TypedefDef` which in turn inherits it from `IDLType`). Both attributes contain the same information.

See Also CORBA :: IDLType::type

CORBA::Any Class

The class `Any` implements the IDL basic type `any`, which allows the specification of values that can express an arbitrary IDL type. This allows a program to handle values whose types are not known at compile time. The IDL type `any` is most often used in code that uses the interface repository or the dynamic invocation interface (DII) or with CORBA services in general.

Consider the following interface:

```
// IDL
interface Example {
    void op(in any value);
};
```

A client can construct an `any` to contain an arbitrary type of value and then pass this in a call to `op()`. A process receiving an `any` must determine what type of value it stores and then extract the value (using the `TypeCode`). Refer to the *CORBA Programmer's Guide* for more details.

Methods and structures are as follows:

<code>Any()</code>	<code>operator=()</code>
<code>~Any()</code>	<code>replace()</code>
<code>from_boolean structure</code>	<code>to_boolean structure</code>
<code>from_char structure</code>	<code>to_char structure</code>
<code>from_fixed structure</code>	<code>to_fixed structure</code>
<code>from_octet structure</code>	<code>to_object structure</code>
<code>from_string structure</code>	<code>to_octet structure</code>
<code>from_wchar structure</code>	<code>to_string structure</code>
<code>from_wstring structure</code>	<code>to_wchar structure</code>
<code>it_get_streamable()</code>	<code>to_wstring structure</code>
<code>it_set_streamable()</code>	<code>type()</code>
<code>it_take_streamable()</code>	

```

// C++
class IT_ART_API Any : public ITCxxMemBase
{
public:
    Any();
    Any(
        const Any& any
    );
    Any(
        TypeCode_ptr tc,
        void*         value,
        Boolean       release = 0
    );
    Any(
        IT_Streamable* strm,
        IT_Streamable::MemPolicy policy
    );
    ~Any();
    Any& operator=(
        const Any&
    );
    //
    // type-unsafe operations
    //
    void replace(
        TypeCode_ptr tc,
        void*         value,
        Boolean       release = 0
    );
    TypeCode_ptr type() const;
    void type(
        TypeCode_ptr new_type
    );
    const void* value() const;
    struct from_boolean {
        from_boolean(
            Boolean b
        );
        Boolean m_val;
    };
    struct from_octet {
        from_octet(
            Octet octet
        );
        Octet m_val;
    };
};

```

```

struct from_char {
    from_char(
        Char c
    );
    Char m_val;
};
struct from_wchar {
    from_wchar(
        WChar c
    );
    WChar m_val;
};
struct from_string {
    from_string(
        char* s,
        ULong b,
        Boolean nocopy = 0
    );
    from_string(
        const char* s,
        ULong b
    );
    char* m_val;
    ULong m_bound;
    Boolean m_nocopy;
};
struct from_wstring {
    from_wstring(
        WChar* s,
        ULong b,
        Boolean nocopy = 0
    );
    from_wstring(
        const WChar* s,
        ULong b
    );
    WChar* m_val;
    ULong m_bound;
    Boolean m_nocopy;
};
struct from_fixed {
    from_fixed(
        const Fixed& f,
        UShort digits,
        Short scale
    );
    const Fixed& m_val;
};

```

```

        UShort m_digits;
        Short m_scale;
};
struct to_boolean {
    to_boolean(
        Boolean& b
    );
    Boolean& m_ref;
};
struct to_char {
    to_char(
        Char& c
    );
    Char& m_ref;
};
struct to_wchar {
    to_wchar(
        WChar& c
    );
    WChar& m_ref;
};
struct to_octet {
    to_octet(
        Octet& o
    );
    Octet& m_ref;
};
struct to_object {
    to_object(
        Object_ptr& obj
    );
    Object_ptr& m_ref;
};
struct to_string {
    to_string(
        char*& s,
        ULong b
    );
    char*& m_ref;
    ULong m_bound;
};
struct to_wstring {
    to_wstring(
        WChar*& s,
        ULong b
    );
    WChar*& m_ref;
};

```

```

        ULong m_bound;
    };
    struct to_fixed {
        to_fixed(
            Fixed& f,
            UShort digits,
            Short scale
        );
        Fixed& m_ref;
        UShort m_digits;
        Short m_scale;
    };
    IT_Streamable* it_get_streamable(
        Boolean make_copy = 0
    ) const;
    Boolean it_take_streamable(
        IT_Streamable* &strm
    );
    void it_set_streamable(
        IT_Streamable* strm,
        IT_Streamable::MemPolicy policy
    );
private:
    ...
}

```

Any::Any() Constructors

Any();

The default constructor creates an Any with a TypeCode of type tk_null and with a zero value.

Any(

```

    const Any& any
);

```

This copy constructor duplicates the TypeCode_ptr of any and copies the value.

Any(

```

    TypeCode_ptr tc,
    void*         value,
    Boolean       release = 0
);

```

Constructs an `Any` with a specific `TypeCode` and `value`. This constructor is needed for cases where it is not possible to use the default constructor and `operator<=<()`. For example, since all strings are mapped to `char*`, it is not possible to create an `Any` with a specific `TypeCode` for a bounded string.

This constructor is not type-safe; you must ensure consistency between the `TypeCode` and the actual type of the argument `value`.

`Any(`

```

    IT_Streamable*      strm,
    IT_Streamable::MemPolicy policy
);

```

Constructs an `Any` from a stream.

Parameters

<code>type</code>	A reference to a <code>CORBA::TypeCode</code> . The constructor duplicates this object reference.
<code>val</code>	The value pointer. A conforming program should make no assumptions about the lifetime of the value passed in this parameter once it has been passed to this constructor with <code>release=1</code> .
<code>release</code>	A boolean variable to decide ownership of the storage pointed to by <code>value</code> . If set to 1, the <code>Any</code> object assumes ownership of the storage. If the <code>release</code> parameter is set to 0 (the default), the calling program is responsible for managing the memory pointed to by <code>value</code> .
<code>IT_Streamable*</code>	

```
IT_Streamab
le::MemPoli
cy
```

Examples The easiest and the type-safe way to construct an `Any` is to use the default constructor and then use `operator<=<=()` to insert a value into the `Any`. For example:

```
// C++
CORBA::Short s = 10;
CORBA::Any a;
a <=<= s;
```

See Also `CORBA::Any::operator<=<=()`

`Any::~Any()` Destructor

```
~Any();
```

Destructor for an `Any`. Depending on the value of the Boolean release parameter to the complex constructor, it frees the value contained in the `Any` based on the `TypeCode` of the `Any`. It then frees the `TypeCode`.

See Also `CORBA::Any::Any()`

`Any::from_type` Structure

`struct from_boolean` {

```
    from_boolean(
        Boolean b
    );
    Boolean m_val;
};
```

`struct from_char` {


```

    from_char(
        Char c
    );
    Char m_val;
};

```

struct from_fixed {

```

    from_fixed(
        const Fixed& f,
        UShort digits,
        Short scale
    );
    const Fixed& m_val;
    UShort m_digits;
    Short m_scale;
};

```

struct from_octet {

```

    from_octet(
        Octet octet
    );
    Octet m_val;
};

```

struct from_string {

```

    from_string(
        char* s,
        ULong b,
        Boolean nocopy = 0
    );
    from_string(
        const char* s,
        ULong b
    );
    char* m_val;
    ULong m_bound;
    Boolean m_nocopy;
};

```

struct from_wchar {

```

    from_wchar(
        WChar c
    );
    WChar m_val;
};

```

struct from_wstring {

```

    from_wstring(
        WChar* s,
        ULong b,
        Boolean nocopy = 0
    );
    from_wstring(
        const WChar* s,
        ULong b
    );
    WChar* m_val;
    ULong m_bound;
    Boolean m_nocopy;
};

```

Inserts the specific IDL type into the `any`. These helper structures are nested in the `any` class interface to distinguish these IDL data types from each other. Because these IDL types are not required to map to distinct C++ types, another means of distinguishing them from each other is necessary so that they can be used with the type-safe `any` interface.

See Also CORBA::Any::to_type

Any::it_get_streamable()

IT_Streamable* it_get_streamable(

```
    Boolean make_copy = 0
) const;
```

Enhancement IONA-specific enhancement.

Any::it_set_streamable()

void it_set_streamable(

```
    IT_Streamable*      strm,
    IT_Streamable::MemPolicy policy
);
```

Enhancement IONA-specific enhancement.

Any::it_take_streamable()

Boolean it_take_streamable(

```
    IT_Streamable* &strm
);
```

Enhancement IONA-specific enhancement.

Any::operator=()

Any& operator=(

```
    const Any& a
);
```

The assignment operator releases its `TypeCode` and frees the value if necessary.

Parameters

`a`

The value to duplicate. The method duplicates the `TypeCode` of `a` and deep copies the parameter's value.

```
void replace(
    TypeCode_ptr tc,
    void*        value,
    Boolean      release = 0
);
```

This method is needed for cases where it is not possible to use `operator<=<()` to insert into an existing `Any`. For example, because all strings are mapped to `char*`, it is not possible to create an `Any` with a specific `TypeCode` for a bounded string.

Parameters

<code>tc</code>	A reference to a <code>CORBA::TypeCode</code> . The method duplicates this object reference.
<code>value</code>	The value pointer. A conforming program should make no assumptions about the lifetime of the value passed in this parameter if it has been passed to <code>Any::replace()</code> with <code>release=1</code> .
<code>release</code>	A boolean variable to decide ownership of the storage pointed to by <code>value</code> . If set to 1, the <code>Any</code> object assumes ownership of the storage. If the release parameter is set to 0 (the default), the calling program is responsible for managing the memory pointed to by <code>value</code> .

This function is not type-safe; you must ensure consistency between the `TypeCode` and the actual type of the argument `value`.

`Any::to_type` Structure

```
struct to_boolean {
```

```

        to_boolean(
            Boolean& b
        );
        Boolean& m_ref;
};
struct to_char {
    to_char(
        Char& c
    );
    Char& m_ref;
};
struct to_fixed {
    to_fixed(
        Fixed& f,
        UShort digits,
        Short scale
    );
    Fixed& m_ref;
    UShort m_digits;
    Short m_scale;
};
struct to_object {
    to_object(
        Object_ptr& obj
    );
    Object_ptr& m_ref;
};
struct to_octet {
    to_octet(
        Octet& o
    );
    Octet& m_ref;
};
struct to_string {
    to_string(
        char*& s,
        ULong b
    );
    char*& m_ref;
    ULong m_bound;
};
struct to_wchar {
    to_wchar(
        WChar& c
    );
    WChar& m_ref;
};

```

```
};
struct to_wstring {
    to_wstring(
        WChar*& s,
        ULong b
    );
    WChar*& m_ref;
    ULong m_bound;
};
```

Extracts the specific IDL type from the `any`. These helper structures are nested in the `any` class interface to distinguish these IDL data types from each other. Because these IDL types are not required to map to distinct C++ types, another means of distinguishing them from each other is necessary so that they can be used with the type-safe `any` interface.

See Also `CORBA::Any::from_type`

`Any::type()`

```
TypeCode_ptr type() const;
```

Returns the `Typecode` of the `Object` encapsulated within the `Any`.

```
void type(TypeCode_ptr t);
```

Sets the `Typecode` of the `Object` encapsulated within the `Any`.

Parameters

`t`

The `TypeCode` of the object.

CORBA::ArrayDef Interface

The `ArrayDef` interface represents a one-dimensional array in an interface repository. A multi-dimensional array is represented by an `ArrayDef` with an element type that is another array definition. The final element type represents the type of element contained in the array. An instance of interface `ArrayDef` can be created using `create_array()`.

```
// IDL in module CORBA.
interface ArrayDef : IDLType {
    attribute unsigned long [length](#corbaarraydef-interface);
    readonly attribute TypeCode [element_type](#corbaarraydef-interface);
    attribute IDLType [element_type_def](#corbaarraydef-interface);
};
```

See Also `CORBA::IDLType`

```
CORBA::ArrayDef::element_type_def
CORBA::Repository::create_array()
```

`ArrayDef::element_type` Attribute

// IDL

```
readonly attribute TypeCode element_type;
```

Identifies the type of the element contained in the array. This contains the same information as in the `element_type_def` attribute.

See Also `CORBA::ArrayDef::element_type_def`

`ArrayDef::element_type_def` Attribute

// IDL

```
attribute IDLType element_type_def;
```

Describes the type of the element contained within the array. This contains the same information as in the attribute `element_type` attribute.

The type of elements contained in the array can be changed by changing this attribute. Changing this attribute also changes the `element_type` attribute.

See Also CORBA :: ArrayDef::element_type

ArrayDef::length Attribute

// IDL

```
attribute unsigned long length;
```

Returns the number of elements in the array.

Specifies the number of elements in the array.

CORBA::AttributeDef Interface

The `AttributeDef` interface describes an attribute of an interface in the interface repository.

```
// IDL in module CORBA.
interface AttributeDef : Contained {
    readonly attribute TypeCode [type](#corbaattributedef-interface);
    attribute IDLType [type_def](#corbaattributedef-interface);
    attribute AttributeMode [mode](#corbaattributedef-interface);
};
```

The inherited `describe()` method is also described.

See Also `CORBA::Contained`

```
CORBA::InterfaceDef::create_attribute()
```

`AttributeDef::describe()`

// IDL

```
Description describe();
```

Inherited from `Contained`, the `describe()` method returns a structure of type `Contained::Description`. The `DefinitionKind` for the `kind` member of this structure is `dk_Attribute`. The `value` member is an `any` whose `TypeCode` is `_tc_AttributeDescription`. The value is a structure of type `AttributeDescription`.

See Also `CORBA::Contained::describe()`

`AttributeDef::mode` `Attribute`

// IDL

```
attribute AttributeMode mode;
```

// C++

```
virtual AttributeMode mode() = 0;
```

Returns the mode of the attribute.

// C++

```
virtual void mode(
    AttributeMode _itvar_mode
) = 0;
```

Specifies whether the attribute is read and write (ATTR_NORMAL) or read-only (ATTR_READONLY).

AttributeDef::type Attribute

// IDL

```
readonly attribute TypeCode type;
```

// C++

```
virtual TypeCode_ptr type() = 0;
```

Returns the type of this attribute. The same information is contained in the `type_def` attribute.

See Also CORBA::TypeCode

```
CORBA::AttributeDef::type_def
```

AttributeDef::type_def Attribute

// IDL

```
attribute IDLType type_def;
```

// C++

```
virtual IDLType_ptr type_def() = 0;
```

Returns the type of this attribute.

// C++

```
virtual void type_def(  
    IDLType_ptr _itvar_type_def  
) = 0;
```

Describes the type for this attribute. The same information is contained in the `type` attribute. Changing the `type_def` attribute automatically changes the `type` attribute.

See Also CORBA::IDLType

```
CORBA::AttributeDef::type
```

CORBA::ConstantDef Interface

Interface `ConstantDef` describes an IDL constant in the interface repository. The name of the constant is inherited from `Contained`.

```
// IDL
// in module CORBA.
interface ConstantDef : Contained {
    readonly attribute TypeCode [type](#corbaattributedef-interface);
    attribute IDLType [type_def](#corbaattributedef-interface);
    attribute any [value](#corbaconstantdef-interface);
};
```

The inherited operation `describe()` is also described.

See Also `CORBA::Contained`

```
CORBA::Container::create_constant()
```

`ConstantDef::describe()`

```
// IDL
```

```
Description describe();
```

Inherited from `Contained`, `describe()` returns a structure of type `Contained::Description`.

The `kind` member is `dk_Constant`.

The `value` member is an `any` whose `TypeCode` is `_tc_ConstantDescription` and whose value is a structure of type `ConstantDescription`.

See Also `CORBA::Contained::describe()`

`ConstantDef::type` Attribute

```
// IDL
```

```
readonly attribute TypeCode type;
```

Identifies the type of this constant. The type must be a TypeCode for one of the simple types (such as `long`, `short`, `float`, `char`, `string`, `double`, `boolean`, `unsigned long`, and `unsigned short`). The same information is contained in the `type_def` attribute.

See Also CORBA::ConstantDef::type_def

ConstantDef::type_def Attribute

// IDL

```
attribute IDLType type_def;
```

Returns the type of this constant.

Identifies the type of the constant. The same information is contained in the `type` attribute.

The type of a constant can be changed by changing its `type_def` attribute. This also changes its `type` attribute.

See Also CORBA::ConstantDef::type

ConstantDef::value Attribute

// IDL

```
attribute any value;
```

Returns the value of this attribute.

Contains the value for this constant. When changing the `value` attribute, the TypeCode of the `any` must be the same as the `type` attribute.

See Also CORBA::TypeCode

CORBA::ConstructionPolicy Interface

When new object references are created, the `ConstructionPolicy` object allows the caller to specify that the instance should be automatically assigned membership in a newly created policy domain. When a policy domain is created, it also has a DomainManager object associated with it. The `ConstructionPolicy` object provides a single operation that makes the DomainManager object.

```
// IDL in CORBA Module
interface ConstructionPolicy: Policy {
    void [make_domain_manager](#corbaconstructionpolicy-interface)(
        in CORBA::InterfaceDef object_type,
        in boolean constr_policy
    );
};
```

`ConstructionPolicy::make_domain_manager()`

// IDL

```
void make_domain_manager(
    in CORBA::InterfaceDef object_type,
    in boolean constr_policy
);
```

This operation sets the construction policy that is to be in effect in the policy domain for which this `ConstructionPolicy` object is associated.

Parameters

<code>object_type</code>	The type of the objects for which domain managers will be created. If this is nil, the policy applies to all objects in the policy domain.

<code>constr_policy</code>	A value of true indicates to the ORB that new object references of the specified <code>object_type</code> are to be associated with their own separate policy domains (and associated domain manager). Once such a construction policy is set, it can be reversed by invoking <code>make_domain_manager()</code> again with the value of false. A value of false indicates the construction policy is set to associate the newly created object with the policy domain of the creator or a default policy domain.

You can obtain a reference to the newly created domain manager by calling `_get_domain_managers()` on the newly created object reference.

See Also CORBA::DomainManager

```
CORBA::Object::_get_domain_managers()
```

CORBA::Contained Interface

Interface `Contained` is an abstract interface that describes interface repository objects that can be contained in a module, interface, or repository. It is a base interface for the following interfaces:

```
ModuleDef  
InterfaceDef  
ConstantDef  
TypedefDef  
ExceptionDef  
AttributeDef  
OperationDef  
StructDef  
EnumDef  
UnionDef  
AliasDef  
ValueDef
```

The complete interface is shown here:


```
// IDL
// In module CORBA.
interface Contained : IRObject {
    // read/write interface
    attribute RepositoryId ;
    attribute Identifier [name](#portableinterceptorinterface);
    attribute VersionSpec [version](#corbacontained-interface);
    // read interface
    readonly attribute Container [defined_in](#corbacontained-interface);
    readonly attribute ScopedName [absolute_name](#corbacontained-interface);
    readonly attribute Repository [containing_repository](#corbacontained-
interface);
    struct [Description](#corbacontainer-interface) {
        DefinitionKind kind;
        any value;
    };
    Description [describe](#corbaattributedef-interface)();
    // write interface
    void [move](#corbacontained-interface)(
        in Container new_container,
        in Identifier new_name,
        in VersionSpec new_version
    );
};
```

See Also CORBA::Container

CORBA::IRObject

Contained::absolute_name Attribute

//IDL

```
readonly attribute ScopedName absolute_name;
```

Gives the absolute scoped name of an object.

See Also CORBA::ScopedName

Contained::containing_repository Attribute

// IDL

```
readonly attribute Repository containing_repository;
```

Gives the Repository within which the object is contained.

Contained::defined_in Attribute

// IDL

```
attribute Container defined_in;
```

Specifies the Container for the interface repository object in which the object is contained.

An IFR object is said to be contained by the IFR object in which it is defined. For example, an InterfaceDef object is contained by the ModuleDef in which it is defined.

A second notion of contained applies to objects of type AttributeDef or OperationDef. These objects may also be said to be contained in an InterfaceDef object if they are inherited into that interface. Note that inheritance of operations and attributes across the boundaries of different modules is also allowed.

See Also CORBA::Container::contents()

Contained::describe()

// IDL

```
Description describe();
```

Returns a structure of type Contained::Description.

The `kind` field of the `Description` structure contains the same value as the `def_kind` attribute that Contained inherits from IRObjct.

See Also CORBA::Container::describe_contents()

```
CORBA::DefinitionKind
```

Contained::Description Structure

// IDL

```
struct Description {
    DefinitionKind kind;
    any value;
};
```

This is a generic form of description which is used as a wrapper for another structure stored in the `value` field.

Depending on the type of the `Contained` object, the `value` field will contain a corresponding description structure:

```
ConstantDescription
ExceptionDescription
AttributeDescription
OperationDescription
ModuleDescription
InterfaceDescription
TypeDescription
```

The last of these, `TypeDescription` is used for objects of type `StructDef`, `UnionDef`, `EnumDef`, and `AliasDef` (it is associated with interface `TypedefDef` from which these four listed interfaces inherit).

`Contained::id` Attribute

// IDL

```
attribute RepositoryId id;
```

A `RepositoryId` provides an alternative method of naming an object which is independent of the `ScopedName`.

In order to be CORBA compliant the naming conventions specified for CORBA `RepositoryIds` should be followed. Changing the `id` attribute changes the global identity of the contained object. It is an error to change the `id` to a value that currently exists in the contained object's Repository.

`Contained::move()`

// IDL

```
void move(
    in Container new_container,
    in Identifier new_name,
    in VersionSpec new_version
);
```

Removes this object from its container, and adds it to the container specified by `new_container`. The new container must:

- Be in the same repository.
- Be capable of containing an object of this type.
- Not contain an object of the same name (unless multiple versions are supported).

The `name` attribute of the object being moved is changed to that specified by the `new_name` parameter. The `version` attribute is changed to that specified by the `new_version` parameter.

See Also CORBA :: Container

Contained::name Attribute

// IDL

```
attribute Identifier name;
```

Return or set the name of the object within its scope. For example, in the following definition:

```
// IDL
interface Example {
void op();
};
```

the names are `Example` and `op`. A `name` must be unique within its scope but is not necessarily unique within an interface repository. The `name` attribute can be changed but it is an error to change it to a value that is currently in use within the object's Container.

See Also CORBA :: Contained :: id

Contained::version Attribute

// IDL

```
attribute VersionSpec version;
```

Return or set the version number for this object. Each interface object is identified by a version which distinguishes it from other versioned objects of the same name.

CORBA::Container Interface

Interface `Container` describes objects that can contain other objects in the interface repository. A `Container` can contain any number of objects derived from the `Contained` interface. Such objects include:

```
AttributeDef  
ConstantDef  
ExceptionDef  
InterfaceDef  
ModuleDef  
OperationDef  
TypedefDef  
ValueDef  
ValueMemberDef
```

The interface is shown here:

```

//IDL
// In CORBA Module
interface Container : IRObject {
    // read interface
    Contained [lookup](#corbacontainer-interface)(
        in ScopedName search_name);
    ContainedSeq [contents](#corbacontainer-interface)(
        in DefinitionKind limit_type,
        in boolean exclude_inherited
    );
    ContainedSeq [lookup_name](#corbacontainer-interface)(
        in Identifier search_name,
        in long levels_to_search,
        in DefinitionKind limit_type,
        in boolean exclude_inherited
    );
    struct [Description](#corbacontainer-interface) {
        Contained contained_object;
        DefinitionKind kind;
        any value;
    };
    typedef sequence<Description> [DescriptionSeq](#corbacontainer-
interface);
    DescriptionSeq [describe_contents](#corbacontainer-interface)(
        in DefinitionKind limit_type,
        in boolean exclude_inherited,
        in long max_returned_objs
    );
    // write interface
    ModuleDef [create_module](#corbacontainer-interface)(
        in RepositoryId id,
        in Identifier name,
        in VersionSpec version
    );
    ConstantDef [create_constant](#corbacontainer-interface)(
        in RepositoryId id,
        in Identifier name,
        in VersionSpec version,
        in IDLType type,
        in any value
    );
    StructDef [create_struct](#corbacontainer-interface)(
        in RepositoryId id,
        in Identifier name,
        in VersionSpec version,
        in StructMemberSeq members

```

```

);
UnionDef [create_union](#corbacontainer-interface)(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in IDLType discriminator_type,
    in UnionMemberSeq members
);
EnumDef [create_enum](#corbacontainer-interface)(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in EnumMemberSeq members
);
AliasDef [create_alias](#corbacontainer-interface)(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in IDLType original_type
);
InterfaceDef [create_interface](#corbacontainer-interface)(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in InterfaceDefSeq base_interfaces
    in boolean is_abstract
);
ValueDef [create_value](#corbacontainer-interface)(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in boolean is_custom,
    in boolean is_abstract,
    in ValueDef base_value,
    in boolean is_truncatable,
    in ValueDefSeq abstract_base_values,
    in InterfaceDef supported_interface,
    in InitializerSeq initializers
);
ValueBoxDef [create_value_box](#corbacontainer-interface)(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in IDLType original_type_def
);
ExceptionDef [create_exception](#corbacontainer-interface)(
    in RepositoryId id,

```



```

        in Identifier name,
        in VersionSpec version,
        in StructMemberSeq members
    );
NativeDef [create_native](#corbacontainer-interface)(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
);
}; // End Interface Container

```

See Also **CORBA** :: IObject

Container::contents()

// IDL

```

ContainedSeq contents(
    in DefinitionKind limit_type,
    in boolean exclude_inherited
);

```

Returns a sequence of Contained objects that are directly contained in (defined in or inherited into) the target object. This operation can be used to navigate through the hierarchy of definitions—starting, for example, at a Repository.

Parameters

limit_type	If set to dk_all , all of the contained interface repository objects are returned. If set to the DefinitionKind for a specific interface type, it returns only interfaces of that type. For example, if set to, dk_Operation , then it returns contained operations only.
exclude_inherited	Applies only to interfaces. If true, no inherited objects are returned. If false, objects are returned even if they are inherited.

See Also **CORBA** :: Container::describe_contents()

CORBA :: DefinitionKind

Container::create_alias()

// IDL

```
AliasDef create_alias(  
    in RepositoryId id,  
    in Identifier name,  
    in VersionSpec version,  
    in IDLType original_type  
);
```

Creates a new AliasDef object within the target `Container`. The defined_in attribute is set to the target `Container`. The containing_repository attribute is set to the Repository in which the new AliasDef object is defined.

Parameters

id	The repository ID for the new AliasDef object. An exception is raised if an interface repository object with the same ID already exists within the object's repository.
name	The name for the new AliasDef object. It is an error to specify a name that already exists within the object's Container when multiple versions are not supported.
version	A version for the new AliasDef.
original_type	The original type that is being aliased.

Exceptions

BAD_PARAM, minor code 2	An object with the specified id already exists in the repository.
BAD_PARAM, minor code 3	The specified name already exists within this Container and multiple versions are not supported.
BAD_PARAM, minor code 4	The created object is not allowed by the Container. Certain interfaces derived from Container may restrict the types of definitions that they may contain.

See AlsoCORBA :: AliasDef

Container::create_constant()

// IDL

```
ConstantDef create_constant(  
    in RepositoryId id,  
    in Identifier name,  
    in VersionSpec version,  
    in IDLType type,  
    in any value  
);
```

Creates a ConstantDef object within the target `Container`. The `defined_in` attribute is set to the target `Container`. The `containing_repository` attribute is set to the Repository in which the new ConstantDef object is defined.

Parameters

<code>id</code>	The repository ID of the new ConstantDef object. It is an error to specify an ID that already exists within the object's repository.
<code>name</code>	The name of the new ConstantDef object. It is an error to specify a name that already exists within the object's <code>Container</code> when multiple versions are not supported.
<code>version</code>	The version number of the new ConstantDef object.
<code>type</code>	The type of the defined constant. This must be one of the simple types (<code>long</code> , <code>short</code> , <code>ulong</code> , <code>ushort</code> , <code>float</code> , <code>double</code> , <code>char</code> , <code>string</code> , <code>boolean</code>).
<code>value</code>	The value of the defined constant.

Exceptions

<code>BAD_PARAM,</code> <code>minor code 2</code>	An object with the specified <code>id</code> already exists in the repository.
<code>BAD_PARAM,</code> <code>minor code 3</code>	The specified <code>name</code> already exists within this <code>Container</code> and multiple versions are not supported.

<code>BAD_PARAM,</code> <code>minor code 4</code>	The created object is not allowed by the <code>Container</code> . Certain interfaces derived from <code>Container</code> may restrict the types of definitions that they may contain.

See Also `CORBA::ConstantDef`

`Container::create_enum()`

// IDL

```
EnumDef create_enum(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in EnumMemberSeq members
);
```

Creates a new EnumDef object within the target `Container`. The `defined_in` attribute is set to `Container`. The `containing_repository` attribute is set to the Repository in which the new EnumDef object is defined.

Parameters

<code>id</code>	The repository ID of the new EnumDef object. It is an error to specify an ID that already exists within the Repository.
<code>name</code>	The name of the EnumDef object. It is an error to specify a name that already exists within the object's <code>Container</code> when multiple versions are not supported.
<code>version</code>	The version number of the new EnumDef object.
<code>members</code>	A sequence of structures that describes the members of the new EnumDef object.

Exceptions

<code>BAD_PARAM,</code> <code>minor code 2</code>	An object with the specified <code>id</code> already exists in the repository.
<code>BAD_PARAM,</code> <code>minor code 3</code>	The specified <code>name</code> already exists within this <code>Container</code> and multiple versions are not supported.

<code>BAD_PARAM,</code> <code>minor code 4</code>	The created object is not allowed by the <code>Container</code> . Certain interfaces derived from <code>Container</code> may restrict the types of definitions that they may contain.

See Also `CORBA::EnumDef`

`Container::create_exception()`

// IDL

```
ExceptionDef create_exception(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in StructMemberSeq members
);
```

Creates a new `ExceptionDef` object within the target `Container`. The `defined_in` attribute is set to `Container`. The `containing_repository` attribute is set to the Repository in which new `ExceptionDef` object is defined. The `type` attribute of the `StructMember` structures is ignored and should be set to `_tc_void`.

Parameters

<code>id</code>	The repository ID of the new <code>ExceptionDef</code> object. It is an error to specify an ID that already exists within the object's repository.
<code>name</code>	The name of the new <code>ExceptionDef</code> object. It is an error to specify a name that already exists within the object's <code>Container</code> when multiple versions are not supported.
<code>version</code>	A version number for the new <code>ExceptionDef</code> object.
<code>members</code>	A sequence of <code>StructMember</code> structures that describes the members of the new <code>ExceptionDef</code> object.

Exceptions

<code>BAD_PARAM,</code> <code>minor code 2</code>	An object with the specified <code>id</code> already exists in the repository.

<code>BAD_PARAM,</code> minor code 3	The specified <code>name</code> already exists within this <code>Container</code> and multiple versions are not supported.
<code>BAD_PARAM,</code> minor code 4	The created object is not allowed by the <code>Container</code> . Certain interfaces derived from <code>Container</code> may restrict the types of definitions that they may contain.

See Also `CORBA::ExceptionDef`

`Container::create_interface()`

// IDL

```
InterfaceDef create_interface(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in InterfaceDefSeq base_interfaces
    in boolean is_abstract
);
```

Creates a new empty `InterfaceDef` object within the target `Container`. The `defined_in` attribute is set to `Container`. The `containing_repository` attribute is set to the `Repository` in which the new `InterfaceDef` object is defined.

Parameters

<code>id</code>	The repository ID of the new <code>InterfaceDef</code> object. It is an error to specify an ID that already exists within the object's repository.
<code>name</code>	The name of the new <code>InterfaceDef</code> object. It is an error to specify a name that already exists within the object's <code>Container</code> when multiple versions are not supported.
<code>version</code>	A version for the new <code>InterfaceDef</code> object.
<code>base_interfaces</code>	A sequence of <code>InterfaceDef</code> objects from which the new interface inherits.
<code>is_abstract</code>	If true the interface is abstract.

Exceptions

<code>BAD_PARAM,</code> <code>minor code 2</code>	An object with the specified <code>id</code> already exists in the repository.
<code>BAD_PARAM,</code> <code>minor code 3</code>	The specified <code>name</code> already exists within this <code>Container</code> and multiple versions are not supported.
<code>BAD_PARAM,</code> <code>minor code 4</code>	The created object is not allowed by the <code>Container</code> . Certain interfaces derived from <code>Container</code> may restrict the types of definitions that they may contain.

See Also `CORBA::InterfaceDef`

`Container::create_module()`

// IDL

```
ModuleDef create_module (
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version
);
```

Creates an empty `ModuleDef` object within the target `Container`. The `defined_in` attribute is set to `Container`. The `containing_repository` attribute is set to the repository in which the newly created `ModuleDef` object is defined.

Parameters

<code>id</code>	The repository ID of the new <code>ModuleDef</code> object. It is an error to specify an ID that already exists within the object's repository.
<code>name</code>	The name of the new <code>ModuleDef</code> object. It is an error to specify a name that already exists within the object's <code>Container</code> when multiple versions are not supported.
<code>version</code>	A version for the <code>ModuleDef</code> object to be created.

Exceptions

<code>BAD_PARAM,</code> <code>minor code 2</code>	An object with the specified <code>id</code> already exists in the repository.
<code>BAD_PARAM,</code> <code>minor code 3</code>	The specified <code>name</code> already exists within this <code>Container</code> and multiple versions are not supported.
<code>BAD_PARAM,</code> <code>minor code 4</code>	The created object is not allowed by the <code>Container</code> . Certain interfaces derived from <code>Container</code> may restrict the types of definitions that they may contain.

`Container::create_native()`

// IDL

```
NativeDef create_native(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
);
```

Creates a `NativeDef` object within the target `Container`. The `defined_in` attribute is set to `Container`. The `containing_repository` attribute is set to the repository in which the newly created `NativeDef` object is defined.

Parameters

<code>id</code>	The repository ID of the new <code>NativeDef</code> object. It is an error to specify an ID that already exists within the object's repository.
<code>name</code>	The name of the new <code>NativeDef</code> object. It is an error to specify a name that already exists within the object's <code>Container</code> when multiple versions are not supported.
<code>version</code>	A version for the <code>NativeDef</code> object to be created.

Exceptions

<code>BAD_PARAM,</code> <code>minor code 2</code>	An object with the specified <code>id</code> already exists in the repository.

<code>BAD_PARAM,</code> minor code 3	The specified <code>name</code> already exists within this <code>Container</code> and multiple versions are not supported.
<code>BAD_PARAM,</code> minor code 4	The created object is not allowed by the <code>Container</code> . Certain interfaces derived from <code>Container</code> may restrict the types of definitions that they may contain.

`Container::create_struct()`

// IDL

```
StructDef create_struct(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in StructMemberSeq members
);
```

Creates a new StructDef object within the target `Container`. The `defined_in` attribute is set to `Container`. The `containing_repository` attribute is set to the repository in which the new StructDef object is defined. The `type` attribute of the StructMember structures is ignored and should be set to `_tc_void`.

Parameters

<code>id</code>	The repository ID of the new StructDef object. It is an error to specify an ID that already exists within the object's repository.
<code>name</code>	The name of the new StructDef object. It is an error to specify a name that already exists within the object's <code>Container</code> when multiple versions are not supported.
<code>version</code>	A version for the new StructDef object.
<code>members</code>	A sequence of StructMember structures that describes the members of the new StructDef object.

Exceptions

<code>BAD_PARAM,</code> minor code 2	An object with the specified <code>id</code> already exists in the repository.

<code>BAD_PARAM,</code> minor code 3	The specified <code>name</code> already exists within this <code>Container</code> and multiple versions are not supported.
<code>BAD_PARAM,</code> minor code 4	The created object is not allowed by the <code>Container</code> . Certain interfaces derived from <code>Container</code> may restrict the types of definitions that they may contain.

See Also `CORBA::StructDef`

`Container::create_union()`

// IDL

```
UnionDef create_union(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in IDLType discriminator_type,
    in UnionMemberSeq members
);
```

Creates a new `UnionDef` object within the target `Container`. The `defined_in` attribute is set to the target `Container`. The `containing_repository` attribute is set to the repository in which the new `UnionDef` object is defined. The `type` attribute of the `UnionMember` structures is ignored and should be set to `_tc_void`.

Parameters

<code>id</code>	The repository ID of the new <code>UnionDef</code> object. It is an error to specify an ID that already exists within the object's repository.
<code>name</code>	The name of the new <code>UnionDef</code> object. It is an error to specify a name that already exists within the object's <code>Container</code> when multiple versions are not supported.
<code>version</code>	A version for the new <code>UnionDef</code> object.
<code>discriminator_type</code>	The type of the union discriminator.

members	A sequence of UnionMember structures that describes the members of the new UnionDef object.

Exceptions

BAD_PARAM, minor code 2	An object with the specified <code>id</code> already exists in the repository.
BAD_PARAM, minor code 3	The specified <code>name</code> already exists within this <code>Container</code> and multiple versions are not supported.
BAD_PARAM, minor code 4	The created object is not allowed by the <code>Container</code> . Certain interfaces derived from <code>Container</code> may restrict the types of definitions that they may contain.

See Also CORBA :: UnionDef

Container::create_value()

```
// IDL
ValueDef create_value(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in boolean is_custom,
    in boolean is_abstract,
    in ValueDef base_value,
    in boolean is_truncatable,
    in ValueDefSeq abstract_base_values,
    in InterfaceDef supported_interfaces,
    in InitializerSeq initializers
);
```

Creates a new empty ValueDef object within the target `Container`. The `defined_in` attribute is set to `Container`. The `containing_repository` attribute is set to the repository in which the new ValueDef object is defined.

Parameters

<code>id</code>	The repository ID of the new ValueDef object. It is an error to specify an ID that already exists within the object's repository.
<code>name</code>	The name of the new ValueDef object. It is an error to specify a name that already exists within the object's <code>Container</code> when multiple versions are not supported.
<code>version</code>	A version for the new ValueDef object.
<code>is_custom</code>	If true the value type is custom.
<code>is_abstract</code>	If true the value type is abstract.
<code>base_value</code>	The base value for this value type.
<code>is_truncatable</code>	if true the value type is truncatable.
<code>abstract_base_values</code>	A sequence of ValueDef structures that describes the base values of the new ValueDef object.
<code>supported_interfaces</code>	The interface the value type supports.
<code>initializers</code>	A sequence of initializers for the new ValueDef object.

Exceptions

<code>BAD_PARAM,</code> <code>minor code 2</code>	An object with the specified <code>id</code> already exists in the repository.
<code>BAD_PARAM,</code> <code>minor code 3</code>	The specified <code>name</code> already exists within this <code>Container</code> and multiple versions are not supported.
<code>BAD_PARAM,</code> <code>minor code 4</code>	The created object is not allowed by the <code>Container</code> . Certain interfaces derived from <code>Container</code> may restrict the types of definitions that they may contain.

Container::create_value_box()

// IDL

```
ValueBoxDef create_value_box(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in IDLType original_type_def
);
```

Creates a new empty ValueBoxDef object within the target `Container`. The `defined_in` attribute is set to `Container`. The `containing_repository` attribute is set to the repository in which the new ValueBoxDef object is defined.

Parameters

<code>id</code>	The repository ID of the new ValueBoxDef object. It is an error to specify an ID that already exists within the object's repository.
<code>name</code>	The name of the new ValueBoxDef object. It is an error to specify a name that already exists within the object's <code>Container</code> when multiple versions are not supported.
<code>version</code>	A version for the new ValueBoxDef object.
<code>original_type_def</code>	The IDL data type of the value box.

Exceptions

<code>BAD_PARAM,</code> <code>minor code 2</code>	An object with the specified <code>id</code> already exists in the repository.
<code>BAD_PARAM,</code> <code>minor code 3</code>	The specified <code>name</code> already exists within this <code>Container</code> and multiple versions are not supported.
<code>BAD_PARAM,</code> <code>minor code 4</code>	The created object is not allowed by the <code>Container</code> . Certain interfaces derived from <code>Container</code> may restrict the types of definitions that they may contain.

Container::describe_contents()

// IDL

```

DescriptionSeq describe_contents(
    in DefinitionKind limit_type,
    in boolean exclude_inherited,
    in long max_returned_objs
);

```

Returns a sequence of structures of type `Container::Description`. `describe_contents()` is a combination of operations `Contained::describe()` and `Container::contents()`.

Parameters

<code>limit_type</code>	If this is set to <code>dk_all</code> , then all of the contained interface repository objects are returned. If set to the <code>DefinitionKind</code> for a particular interface repository kind, it returns only objects of that kind. For example, if set to <code>dk_Operation</code> , then it returns contained operations only.
<code>exclude_inherited</code>	Applies only to interfaces. If true, no inherited objects are returned. If false, objects are returned even if they are inherited.
<code>max_returned_objs</code>	The number of objects that can be returned in the call. Setting a value of <code>-1</code> means return all contained objects.

See Also `CORBA::Container::contents()`

```
CORBA::Contained::describe()
```

Container::Description Structure

// IDL

```

struct Description {
    Contained contained_object;
    DefinitionKind kind;
    any value;
};

```

This structure gives the object reference of a contained object, together with its `kind` and `value`.

Each structure has the following members:

<code>contained_object</code>	The object reference, of type <code>Contained</code> , of the contained top level object. The <code>describe()</code> function can be called on an object reference, of type <code>Contained</code> , to get further information on a top level object in the repository.
<code>kind</code>	The kind of the object being described.
<code>value</code>	An <code>any</code> type that may contain one of the following structures: <code>ModuleDescription</code> <code>ConstantDescription</code> <code>TypeDescription</code> <code>ExceptionDescription</code> <code>AttributeDescription</code> <code>ParameterDescription</code> <code>OperationDescription</code> <code>InterfaceDescription</code>

See Also `CORBA::Container::describe_contents()`

```
CORBA::Contained::describe()
```

`Container::DescriptionSeq` Sequence

// IDL

```
typedef sequence<Description> DescriptionSeq;
```

A sequence of `Container::Description` structures in the interface repository.

See Also `CORBA::Container::Description`

`Container::lookup()`

// IDL

```
Contained lookup(
    in ScopedName search_name
);
```

Locates an object name within the target container. The objects can be directly or indirectly defined in or inherited into the target container.

Parameters

`search_name`

The `name` of the object to search for relative to the target container. If a relative name is given, the object is looked up relative to the target container. If `search_name` is an absolute scoped name (prefixed by '::<'), the object is located relative to the containing Repository.

See Also CORBA::Container::lookup_name()

CORBA::ScopedName

Container::lookup_name()

// IDL

```
ContainedSeq lookup_name (
    in Identifier search_name,
    in long levels_to_search,
    in DefinitionKind limit_type,
    in boolean exclude_inherited
);
```

Locates an object or objects by name within the target container and returns a sequence of contained objects. The named objects can be directly or indirectly defined in or inherited into the target container. (More than one object, having the same simple name can exist within a nested scope structure.)

Parameters

<code>search_name</code>	The simple name of the object to search for.
<code>me</code>	

<code>levels_to_search</code>	Defines whether the search is confined to the current object or should include all interface repository objects contained by the object. If set to <code>-1</code> , the current object and all contained interface repository objects are searched. If set to <code>1</code> , only the current object is searched.
<code>limit_type</code>	If this is set to <code>dk_all</code> , then all of the contained interface repository objects are returned. If set to the DefinitionKind for a particular interface repository kind, it returns only objects of that kind. For example, if set to <code>dk_Operation</code> , then it returns contained operations only.
<code>exclude_inherited</code>	Applies only to interfaces. If true, no inherited objects are returned. If false, objects are returned even if they are inherited.

See Also `CORBA::DefinitionKind`

CORBA::Context Class

Class `CORBA::Context` implements the OMG pseudo-interface `Context`. A context is intended to represent information about the client that is inconvenient to pass via parameters. An IDL operation can specify that it is to be provided with the client's mapping for particular identifiers (properties). It does this by listing these identifiers following the operation declaration in a context clause.

An IDL operation that specifies a context clause is mapped to a C++ member method that takes an extra input parameter of type `Context_ptr`, just before the `Environment` parameter. A client can optionally maintain one or more CORBA `Context` objects, that provide a mapping from identifiers (string names) to string values. A `Context` object contains a list of properties; each property consists of a name and a string value associated with that name and can be passed to a method that takes a `Context` parameter.

You can arrange `Context` objects in a hierarchy by specifying parent-child relationships among them. Then, a child passed to an operation also includes the identifiers of its parent(s). The called method can decide whether to use just the context actually passed, or the hierarchy above it.

The `Context` class is as follows:

```
// IDL
pseudo interface Context {
    readonly attribute Identifier context_name;
    readonly attribute Context parent;
    Context create_child(in Identifier child_ctx_name);
    void set_one_value(in Identifier propname, in any propvalue);
    void set_values(in NVList values);
    void delete_values(in Identifier propname);
    NVList get_values(in Identifier start_scope,
        in Flags op_flags,
        in Identifier pattern);
};

class Context {
public:
    const char *[context_name](#corbacontext-class)() const;
    Context_ptr [parent](#corbacontext-class)() const;
    void [create_child](#corbacontext-class)(
        const char *,
        Context_out
    );
    void [set_one_value](#corbacontext-class)(
        const char *,
        const Any &
    );
    void [set_values](#corbacontext-class)(
        NVList_ptr
    );
    void [delete_values](#corbacontext-class)(
        const char *
    );
    void [get_values](#corbacontext-class)(
        const char*,
        Flags,
        const char*,
        NVList_out
    );
};
};
```

****Context::context_name()

const char *context_name() const;

Returns the name of the `Context` object. Ownership of the returned value is maintained by the `Context` and must not be freed by the caller.

See Also CORBA::Context::create_child()

Context::create_child()

void create_child(

```
    const char *ctx_name,
    Context_out child_ctx
);
```

Creates a child context of the current context. When a child context is passed as a parameter to an operation, any searches (using CORBA::Context::get_values()) look in parent contexts if necessary to find matching property names.

Parameters

<code>ctx_name</code>	The name of the child context. Context object names follow the rules for IDL identifiers.
<code>child_ctx</code>	The newly created context.
<code>child_ctx_name</code>	The newly created context.

See Also CORBA::Context::get_values()

Context::delete_values()

void delete_values(

```
    const char *prop_name
);
```

Deletes the specified property value(s) from the context. The search scope is limited to the Context object on which the invocation is made.

Parameters

`prop_name`

The property name to be deleted. If `prop_name` has a trailing asterisk (*), all matching properties are deleted.

Exceptions An exception is raised if no matching property is found.

Context::get_values()

void get_values(

```
    const char* start_scope,
    Flags op_flags,
    const char* prop_name,
    NVList_out values
);
```

Retrieves the specified context property values.

Parameters

<code>start_scope</code>	The context in which the search for the values requested should be started. The name of a direct or indirect parent context may be specified to this parameter. If 0 is passed in, the search begins in the context which is the target of the call.
<code>op_flags</code>	By default, searching of identifiers propagates upwards to parent contexts; if the value <code>CORBA::CTX_RESTRICT_SCOPE</code> is specified, then searching is limited to the specified search scope or context object.
<code>prop_name</code>	If <code>prop_name</code> has a trailing asterisk (*), all matching properties and their values are returned.
<code>values</code>	An NVList to contain the returned property values.

Context::parent()

Context_ptr parent() const;

Returns the parent of the `Context` object. Ownership of the return value is maintained by the `Context` and must not be freed by the caller.

See Also CORBA::Context::create_child()

Context::set_one_value()

void set_one_value(

```
const char * prop_name,
const Any &value
);
```

Adds a property name and value to the `Context`. Although the value member is of type `Any`, the type of the `Any` must be a string.

Parameters

<code>prop_name</code>	The name of the property to add.
<code>value</code>	The value of the property to add.

See Also `CORBA::Context::set_values()`

`Context::set_values()`

`void set_values(`

```
NVList_ptr values
);
```

Sets one or more property values in the `Context`. The previous value of a property, if any, is discarded.

Parameters

`values`

An `NVList` containing the `property_name:values` to add or change. In the `NVList`, the `flags` field must be set to zero, and the

See Also `CORBA::Context::set_one_value()`

CORBA::ContextList Class

A `ContextList` allows an application to provide a list of Context strings that must be supplied when a dynamic invocation Request is invoked.

The Context is where the actual values are obtained by the ORB. The `ContextList` supplies only the context strings whose values are to be looked up and sent with the request invocation. The serverless `ContextList` object allows the application to specify context information in a way that avoids potentially expensive interface repository lookups for the information by the ORB during a request.

```
// IDL
pseudo interface ContextList {
    readonly attribute unsigned long count;
    void add(in string ctx);
    string item(in unsigned long index) raises (CORBA::Bounds);
    void remove(in unsigned long index) raises (CORBA::Bounds);
};

// C++
class ContextList {
public:
    ULong [count](#corbaexceptionlist-class)();
    void [add](#corbaexceptionlist-class)(
        const char* ctx
    );
    void [add_consume](#corbaexceptionlist-class)(
        char* ctx
    );
    const char* [item](#corbaexceptionlist-class)(
        ULong index
    );
    void [remove](#corbaexceptionlist-class)(
        ULong index
    );
};
```

See Also `CORBA::Object::_create_request()`

```
CORBA::Request::contexts
CORBA::ORB::create_context_list()
```

ContextList::add()

void add(

```
    const char* ctxt
);
```

Adds a context string to the context list.

Parameters

```
ctxt
```

A string representing context information.

See Also CORBA::ContextList::add_consume()

ContextList::add_consume()

void add_consume(

```
    char* ctxt
);
```

Adds a context string to the context list. The memory of the `ctxt` parameter is managed by the method. The caller cannot access the memory of `ctxt` after it has been passed in because this method could copy and free the original immediately.

Parameters

```
ctxt
```

A string representing context information.

See Also CORBA::ContextList::add()

ContextList::count()


```
ULong count();
```

Returns the number of context strings in the context list.

```
ContextList::item()
```

```
const char* item(
```

```
    ULong index  
);
```

Returns the context item at the indexed location of the list. This return value must not be released by the caller because ownership of the return value is maintained by the `ContextList`.

Parameters

```
index
```

The indexed location of the desired context item.

```
ContextList::remove()
```

```
void remove(
```

```
    ULong index  
);
```

Removes from the context list the context item at the indexed location.

CORBA::CustomMarshal Value Type

Custom value types can override the default marshaling/unmarshaling mechanism and provide their own way to encode/decode their state. If an application's value type is marked as custom, you use custom marshaling to facilitate integration of such mechanisms as existing class libraries and other legacy systems. Custom marshaling is not to be used as the standard marshaling mechanism.

`CustomMarshal` is an abstract value type that is meant to be implemented by the application programmer and used by the ORB. For example, if an application's value type needs to use custom marshaling, the IDL declares it explicitly as follows:

```
// Application-specific IDL
custom valuetype type {
    // optional state definition
    ...
};
```

When implementing a custom value type such as this, you must provide a concrete implementation of the `CustomMarshal` operations so that the ORB is able to marshal and unmarshal the value type. Each custom marshaled value type needs its own implementation.

You can use the skeletons generated by the IDL compiler as the basis for your implementation. These operations provide the streams for marshaling. Your implemented `CustomMarshal` code encapsulates the application code that can marshal and unmarshal instances of the value type over a stream using the CDR encoding. It is the responsibility of your implementation to marshal the value type's state of all of its base types (if it has any).

The implementation requirements of the streaming mechanism require that the implementations must be local because local memory addresses such as those for the marshal buffers have to be manipulated by the ORB.

Semantically, `CustomMarshal` is treated as a custom value type's implicit base class, although the custom value type does not actually inherit it in IDL. While nothing prevents you from writing IDL that inherits from `CustomMarshal`, doing so will not in itself make the type custom, nor will it cause the ORB to treat it as a custom value type. You must implement these `CustomMarshal` operations.

Implement the following IDL operations for a custom value type:

```
// IDL in module CORBA
abstract valuetype CustomMarshal {
    void [marshal](#corbacustommarshal-value-type)(
        in DataOutputStream os
    );
    void [unmarshal](#corbacustommarshal-value-type)(
        in DataInputStream is
    );
};
```

CustomMarshal::marshal()

The operation you implement so that the ORB can marshal a custom value type.

Parameters

os

A handle to the output stream the ORB uses to marshal the custom value type.

Use the operations of the `DataOutputStream` in your implementation to write the custom value type's data to the stream as appropriate.

See Also `CORBA::DataOutputStream`

CustomMarshal::unmarshal()

The operation you implement so that the ORB can unmarshal a custom value type.

Parameters

is

A handle to the input stream the ORB uses to unmarshal the custom value type.

Use the operations of the `DataInputStream` in your implementation to read the custom value type's data from the stream as appropriate.

See Also `CORBA::DataInputStream`

CORBA::DataInputStream Value Type

The `DataInputStream` value type is a stream used by `unmarshal()` for unmarshaling an application's custom value type. You use the `DataInputStream` operations in your implementation of `unmarshal()` to read specific types of data from the stream, as defined in the custom value type. The stream takes care of breaking the data into chunks if necessary. The IDL code is as follows:

```

// IDL in module CORBA
abstract valuetype DataInputStream {
    any [read_any](#corbadatainputstream-value-type)();
    boolean [read_boolean](#corbadatainputstream-value-type)();
    char [read_char](#corbadatainputstream-value-type)();
    wchar [read_wchar](#corbadatainputstream-value-type)();
    octet [read_octet](#corbadatainputstream-value-type)();
    short [read_short](#corbadatainputstream-value-type)();
    unsigned short [read_ushort](#corbadatainputstream-value-type)();
    long [read_long](#corbadatainputstream-value-type)();
    unsigned long [read_ulong](#corbadatainputstream-value-type)();
    unsigned long long [read_ulonglong](#corbadatainputstream-value-type)();
    float [read_float](#corbadatainputstream-value-type)();
    double [read_double](#corbadatainputstream-value-type)();
    long double [read_longdouble](#corbadatainputstream-value-type)();
    string [read_string](#corbadatainputstream-value-type)();
    wstring [read_wstring](#corbadatainputstream-value-type)();
    Object [read_Object](#corbadatainputstream-value-type)();
    AbstractBase [read_Abstract](#corbadatainputstream-value-type)();
    ValueBase [read_Value](#corbadatainputstream-value-type)();
    TypeCode [read_TypeCode](#corbadatainputstream-value-type)();
    void [read_any_array](#corbadatainputstream-value-type)(
        inout AnySeq seq,
        in unsigned long offset,
        in unsigned long length
    );
    void [read_boolean_array](#corbadatainputstream-value-type)(
        inout BooleanSeq seq,
        in unsigned long offset,
        in unsigned long length
    );
    void [read_char_array](#corbadatainputstream-value-type)(
        inout CharSeq seq,
        in unsigned long offset,
        in unsigned long length
    );
    void [read_wchar_array](#corbadatainputstream-value-type)(
        inout WcharSeq seq,
        in unsigned long offset,
        in unsigned long length
    );
    void [read_octet_array](#corbadatainputstream-value-type)(
        inout OctetSeq seq,
        in unsigned long offset,
        in unsigned long length
    );
};

```

```

void [read_short_array](#corbadatainputstream-value-type)(
    inout ShortSeq seq,
    in unsigned long offset,
    in unsigned long length
);
void [read_ushort_array](#corbadatainputstream-value-type)(
    inout UShortSeq seq,
    in unsigned long offset,
    in unsigned long length
);
void [read_long_array](#corbadatainputstream-value-type)(
    inout LongSeq seq,
    in unsigned long offset,
    in unsigned long length
);
void [read_ulong_array](#corbadatainputstream-value-type)(
    inout ULongSeq seq,
    in unsigned long offset,
    in unsigned long length
);
void [read_ulonglong_array](#corbadatainputstream-value-type)(
    inout ULongLongSeq seq,
    in unsigned long offset,
    in unsigned long length
);
void [read_longlong_array](#corbadatainputstream-value-type)(
    inout LongLongSeq seq,
    in unsigned long offset,
    in unsigned long length
);
void [read_float_array](#corbadatainputstream-value-type)(
    inout FloatSeq seq,
    in unsigned long offset,
    in unsigned long length
);
void [read_double_array](#corbadatainputstream-value-type)(
    inout DoubleSeq seq,
    in unsigned long offset,
    in unsigned long length
);
};

```

Exceptions

MARSHAL

An inconsistency is detected for any operations.

See Also CORBA::CustomMarshal

CORBA::DataOutputStream

DataInputStreamread_Abstract()

// IDL

```
AbstractBase read_Abstract();
```

Returns an abstract data type from the stream.

DataInputStream::read_any()

// IDL

```
any read_any();
```

Returns an `any` data type from the stream.

DataInputStream::read_any_array()

// IDL

```
void read_any_array(
    inout AnySeq seq,
    in unsigned long offset,
    in unsigned long length
);
```

Reads an array of `any` data from the stream.

Parameters

seq	The sequence into which the data is placed.

offset	The starting index from which to read from the sequence.
length	The number of items to read from the array.

DataInputStream::read_boolean()

// IDL

```
boolean read_boolean();
```

Returns a `boolean` data type from the stream.

DataInputStream::read_boolean_array()

// IDL

```
void read_boolean_array(
    inout BooleanSeq seq,
    in unsigned long offset,
    in unsigned long length
);
```

Reads an array of `boolean` data from the stream.

Parameters

seq	The sequence into which the data is placed.
offset	The starting index from which to read from the sequence.
length	The number of items to read from the array.

DataInputStream::read_char()

// IDL

```
char read_char();
```

Returns a `char` data type from the stream.

DataInputStream::read_char_array()

// IDL

```
void read_char_array(  
    inout CharSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Reads an array of `char` data from the stream.

Parameters

<code>seq</code>	The sequence into which the data is placed.
<code>offset</code>	The starting index from which to read from the sequence.
<code>length</code>	The number of items to read from the array.

DataInputStream::read_double()

// IDL

```
double read_double();
```

Returns a `double` data type from the stream.

DataInputStream::read_double_array()

// IDL

```
void read_double_array(  
    inout DoubleSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Reads an array of `double` data from the stream.

Parameters

<code>seq</code>	The sequence into which the data is placed.
<code>offset</code>	The starting index from which to read from the sequence.
<code>length</code>	The number of items to read from the array.

`DataInputStream::read_float()`

// IDL

```
float read_float();
```

Returns a `float` data type from the stream.

`DataInputStream::read_float_array()`

// IDL

```
void read_float_array(
    inout FloatSeq seq,
    in unsigned long offset,
    in unsigned long length
);
```

Reads an array of `float` data from the stream.

Parameters

<code>seq</code>	The sequence into which the data is placed.
<code>offset</code>	The starting index from which to read from the sequence.
<code>length</code>	The number of items to read from the array.

`DataInputStream::read_long()`

// IDL

```
long read_long();
```

Returns a `long` data type from the stream.

`DataInputStream::read_long_array()`

// IDL

```
void read_long_array(
    inout LongSeq seq,
    in unsigned long offset,
    in unsigned long length
);
```

Reads an array of `long` data from the stream.

Parameters

<code>seq</code>	The sequence into which the data is placed.
<code>offset</code>	The starting index from which to read from the sequence.
<code>length</code>	The number of items to read from the array.

`DataInputStream::read_longdouble()`

// IDL

```
long double read_longdouble();
```

Unsupported.

`DataInputStream::read_longlong_array()`

// IDL

```
void read_longlong_array(  
    inout LongLongSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Reads an array of `long long` data from the stream.

Parameters

<code>seq</code>	The sequence into which the data is placed.
<code>offset</code>	The starting index from which to read from the sequence.
<code>length</code>	The number of items to read from the array.

`DataInputStream::read_Object()`

// IDL

```
Object read_Object();
```

Returns an Object (object reference) data type from the stream.

`DataInputStream::read_octet()`

// IDL

```
octet read_octet();
```

Returns an `octet` data type from the stream.

`DataInputStream::read_octet_array()`

// IDL

```
void read_octet_array(  
    inout OctetSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Reads an array of `octet` data from the stream.

Parameters

<code>seq</code>	The sequence into which the data is placed.
<code>offset</code>	The starting index from which to read from the sequence.
<code>length</code>	The number of items to read from the array.

DataInputStream::read_short()

// IDL

```
short read_short();
```

Returns a `short` data type from the stream.

DataInputStream::read_short_array()

// IDL

```
void read_short_array(  
    inout ShortSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Reads an array of `short` data from the stream.

Parameters

<code>seq</code>	The sequence into which the data is placed.

<code>offset</code>	The starting index from which to read from the sequence.
<code>length</code>	The number of items to read from the array.

`DataInputStream::read_string()`

// IDL

```
string read_string();
```

Returns a `string` data type from the stream.

`DataInputStream::read_TypeCode()`

// IDL

```
TypeCode read_TypeCode();
```

Returns a `TypeCode` data type from the stream.

`DataInputStream::read_ulong()`

// IDL

```
unsigned long read_ulong();
```

Returns an `unsigned long` data type from the stream.

`DataInputStream::read_ulong_array()`

// IDL

```
void read_ulong_array(
    inout ULongSeq seq,
    in unsigned long offset,
    in unsigned long length
);
```

Reads an array of `unsigned long` data from the stream.

Parameters

<code>seq</code>	The sequence into which the data is placed.
<code>offset</code>	The starting index from which to read from the sequence.
<code>length</code>	The number of items to read from the array.

`DataInputStream::read_ulonglong()`

// IDL

```
unsigned long long read_ulonglong();
```

Returns an `unsigned long long` data type from the stream.

`DataInputStream::read_ulonglong_array()`

// IDL

```
void read_ulonglong_array(
    inout ULongLongSeq seq,
    in unsigned long offset,
    in unsigned long length
);
```

Reads an array of `unsigned long long` data from the stream.

Parameters

<code>seq</code>	The sequence into which the data is placed.
<code>offset</code>	The starting index from which to read from the sequence.
<code>length</code>	The number of items to read from the array.

`DataInputStream::read_ushort()`

// IDL

```
unsigned short read_ushort();
```

Returns an unsigned `short` data type from the stream.

`DataInputStream::read_ushort_array()`

// IDL

```
void read_ushort_array(
    inout UShortSeq seq,
    in unsigned long offset,
    in unsigned long length
);
```

Reads an array of `unsigned short` data from the stream.

Parameters

<code>seq</code>	The sequence into which the data is placed.
<code>offset</code>	The starting index from which to read from the sequence.
<code>length</code>	The number of items to read from the array.

`DataInputStream::read_Value()`

// IDL

```
ValueBase read_Value();
```

Returns a value type from the stream.

`DataInputStream::read_wchar()`

// IDL

```
wchar read_wchar();
```

Returns a `wchar` data type from the stream.

DataInputStream::read_wchar_array()

// IDL

```
void read_wchar_array(  
    inout WCharSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Reads an array of `wchar` data from the stream.

Parameters

<code>seq</code>	The sequence into which the data is placed.
<code>offset</code>	The starting index from which to read from the sequence.
<code>length</code>	The number of items to read from the array.

DataInputStream::read_wstring()

// IDL

```
wstring read_wstring();
```

Returns a `wstring` data type from the stream.

CORBA::DataOutputStream Value Type

The `DataOutputStream` value type is a stream used by `marshal()` for marshaling an application's custom value type. You use the `DataOutputStream` operations in your implementation of `marshal()` to write specific types of data to the stream, as defined in the custom value type. The stream takes care of breaking the data into chunks if necessary. The IDL code is as follows:

```

//IDL in module CORBA
abstract valuetype DataOutputStream {
    void [write_any](#corbadataoutputstream-value-type)( in any value );
    void [write_boolean](#corbadataoutputstream-value-type)( in boolean
value );
    void [write_char](#corbadataoutputstream-value-type)( in char value );
    void [write_wchar](#corbadataoutputstream-value-type)( in wchar value );
    void [write_octet](#corbadataoutputstream-value-type)( in octet value );
    void [write_short](#corbadataoutputstream-value-type)( in short value );
    void [write_ushort](#corbadataoutputstream-value-type)( in unsigned short
value );
    void [write_long](#corbadataoutputstream-value-type)( in long value );
    void [write_ulong](#corbadataoutputstream-value-type)( in unsigned long
value );
    void [write_longlong](#corbadataoutputstream-value-type)( in long long
value );
    void [write_ulonglong](#corbadataoutputstream-value-type)( in unsigned
long long value );
    void [write_float](#corbadataoutputstream-value-type)( in float value );
    void [write_double](#corbadataoutputstream-value-type)( in double
value );
    void [write_longdouble](#corbadataoutputstream-value-type)( in long
double value );
    void [write_string](#corbadataoutputstream-value-type)( in string
value );
    void [write_wstring](#corbadataoutputstream-value-type)( in wstring
value );
    void [write_Object](#corbadataoutputstream-value-type)( in Object
value );
    void [write_Abstract](#corbadataoutputstream-value-type)( in AbstractBase
value );
    void [write_Value](#corbadataoutputstream-value-type)( in ValueBase
value );
    void [write_TypeCode](#corbadataoutputstream-value-type)( in TypeCode
value );
    void [write_any_array](#corbadataoutputstream-value-type)(
        in AnySeq seq,
        in unsigned long offset,
        in unsigned long length );
    void [write_boolean_array](#corbadataoutputstream-value-type)(
        in BooleanSeq seq,
        in unsigned long offset,
        in unsigned long length );
    void [write_char_array](#corbadataoutputstream-value-type)(
        in CharSeq seq,
        in unsigned long offset,

```

```

        in unsigned long length );
void [write_wchar_array](#corbadataoutputstream-value-type)(
    in WcharSeq seq,
    in unsigned long offset,
    in unsigned long length );
void [write_octet_array](#corbadataoutputstream-value-type)(
    in OctetSeq seq,
    in unsigned long offset,
    in unsigned long length );
void [write_short_array](#corbadataoutputstream-value-type)(
    in ShortSeq seq,
    in unsigned long offset,
    in unsigned long length );
void [write_ushort_array](#corbadataoutputstream-value-type)(
    in UShortSeq seq,
    in unsigned long offset,
    in unsigned long length );
void [write_long_array](#corbadataoutputstream-value-type)(
    in LongSeq seq,
    in unsigned long offset,
    in unsigned long length );
void [write_ulong_array](#corbadataoutputstream-value-type)(
    in ULongSeq seq,
    in unsigned long offset,
    in unsigned long length );
void [write_ulonglong_array](#corbadataoutputstream-value-type)(
    in ULongLongSeq seq,
    in unsigned long offset,
    in unsigned long length );
void [write_longlong_array](#corbadataoutputstream-value-type)(
    in LongLongSeq seq,
    in unsigned long offset,
    in unsigned long length );
void [write_float_array](#corbadataoutputstream-value-type)(
    in FloatSeq seq,
    in unsigned long offset,
    in unsigned long length );
void [write_double_array](#corbadataoutputstream-value-type)(
    in DoubleSeq seq,
    in unsigned long offset,
    in unsigned long length );
};

```

Exceptions

MARSHAL

An inconsistency is detected for any operations.

See Also CORBA::CustomMarshal

CORBA::DataInputStream

DataOutputStream::write_Abstract()

// IDL

```
void write_Abstract(
    in AbstractBase value
);
```

Writes an `abstract` data type to the stream.

Parameters

value

The value written to the stream.

DataOutputStream::write_any()

// IDL

```
void write_any(
    in any value
);
```

Writes an `any` data type to the stream.

Parameters

value

The value written to the stream.

DataOutputStream::write_any_array()

// IDL

```
void write_any_array(  
    in AnySeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Writes an array of `any` data to the stream.

Parameters

<code>seq</code>	The sequence of data to write to the stream.
<code>offset</code>	The offset in <code>seq</code> from which to start writing data.
<code>length</code>	The number of data items to write.

DataOutputStream::write_boolean()

// IDL

```
void write_boolean(  
    in boolean value  
);
```

Writes a `boolean` data type to the stream.

Parameters

value

The value written to the stream.

DataOutputStream::write_boolean_array()

// IDL

```
void write_boolean_array(
    in BooleanSeq seq,
    in unsigned long offset,
    in unsigned long length
);
```

Writes an array of `boolean` data to the stream.

Parameters

<code>seq</code>	The sequence of data to write to the stream.
<code>offset</code>	The offset in <code>seq</code> from which to start writing data.
<code>length</code>	The number of data items to write.

DataOutputStream::write_char()

// IDL

```
void write_char(
    in char value
);
```

Writes a `char` data type to the stream.

Parameters

<code>value</code>

The value written to the stream.

DataOutputStream::write_char_array()

// IDL

```
void write_char_array(  
    in CharSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Writes an array of `char` data to the stream.

Parameters

<code>seq</code>	The sequence of data to write to the stream.
<code>offset</code>	The offset in <code>seq</code> from which to start writing data.
<code>length</code>	The number of data items to write.

`DataOutputStream::write_double()`

// IDL

```
void write_double(  
    in double value  
);
```

Writes a `double` data type to the stream.

Parameters

`value`

The value written to the stream.

`DataOutputStream::write_double_array()`

// IDL


```
void write_double_array(  
    in DoubleSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Writes an array of `double` data to the stream.

Parameters

<code>seq</code>	The sequence of data to write to the stream.
<code>offset</code>	The offset in <code>seq</code> from which to start writing data.
<code>length</code>	The number of data items to write.

`DataOutputStream::write_float()`

// IDL

```
void write_float(  
    in float value  
);
```

Writes a `float` data type to the stream.

Parameters

`value`

The value written to the stream.

`DataOutputStream::write_float_array()`

// IDL

```
void write_float_array(  
    in FloatSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Writes an array of `float` data to the stream.

Parameters

<code>seq</code>	The sequence of data to write to the stream.
<code>offset</code>	The offset in <code>seq</code> from which to start writing data.
<code>length</code>	The number of data items to write.

`DataOutputStream::write_long()`

// IDL

```
void write_long(  
    in long value  
);
```

Writes a `long` data type to the stream.

Parameters

<code>value</code>

The value written to the stream.

`DataOutputStream::write_long_array()`

// IDL

```
void write_long_array(  
    in LongSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Writes an array of `long` data to the stream.

Parameters

<code>seq</code>	The sequence of data to write to the stream.
<code>offset</code>	The offset in <code>seq</code> from which to start writing data.
<code>length</code>	The number of data items to write.

`DataOutputStream::write_longdouble()`

// IDL

```
void write_longdouble(  
    in long double value  
);
```

Writes a `long double` data type to the stream.

Parameters

<code>value</code>

The value written to the stream.

`DataOutputStream::write_longlong()`

// IDL

```
void write_longlong(  
    in long long value  
);
```

Writes a `long long` data type to the stream.

Parameters

```
value
```

The value written to the stream.

`DataOutputStream::write_longlong_array()`

// IDL

```
void write_longlong_array(  
    in LongLongSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Writes an array of `long long` data to the stream.

Parameters

<code>seq</code>	The sequence of data to write to the stream.
<code>offset</code>	The offset in <code>seq</code> from which to start writing data.
<code>length</code>	The number of data items to write.

`DataOutputStream::write_Object()`

// IDL

```
void write_Object(  
    in Object value  
);
```

Writes an Object data type (object reference) to the stream.

Parameters

value

The value written to the stream.

DataOutputStream::write_octet()

// IDL

```
void write_octet(  
    in octet value  
);
```

Writes an `octet` data type to the stream.

Parameters

value

The value written to the stream.

DataOutputStream::write_octet_array()

// IDL

```
void write_octet_array(  
    in OctetSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Writes an array of `octet` data to the stream.

Parameters

<code>seq</code>	The sequence of data to write to the stream.
<code>offset</code>	The offset in <code>seq</code> from which to start writing data.
<code>length</code>	The number of data items to write.

`DataOutputStream::write_short()`

// IDL

```
void write_short(
    in short value
);
```

Writes a `short` data type to the stream.

Parameters

`value`

The value written to the stream.

`DataOutputStream::write_short_array()`

// IDL

```
void write_short_array(
    in ShortSeq seq,
    in unsigned long offset,
    in unsigned long length
);
```

Writes an array of `short` data to the stream.

Parameters

<code>seq</code>	The sequence of data to write to the stream.
<code>offset</code>	The offset in <code>seq</code> from which to start writing data.

length	The number of data items to write.

DataOutputStream::write_string()

// IDL

```
void write_string(
    in string value
);
```

Writes a `string` data type to the stream.

Parameters

value

The value written to the stream.

DataOutputStream::write_TypeCode()

// IDL

```
void write_TypeCode(
    in TypeCode value
);
```

Writes a `TypeCode` data type to the stream.

Parameters

value

The value written to the stream.

DataOutputStream::write_ulong()

// IDL

```
void write_ulong(  
    in unsigned long value  
);
```

Writes an `unsigned long` data type to the stream.

Parameters

`value`

The value written to the stream.

`DataOutputStream::write_ulong_array()`

// IDL

```
void write_ulong_array(  
    in ULongSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Writes an array of `unsigned long` data to the stream.

Parameters

<code>seq</code>	The sequence of data to write to the stream.
<code>offset</code>	The offset in <code>seq</code> from which to start writing data.
<code>length</code>	The number of data items to write.

`DataOutputStream::write_ulonglong()`

// IDL


```
void write_ulonglong(  
    in unsigned long long value  
);
```

Writes an `unsigned long long` data type to the stream.

Parameters

```
value
```

The value written to the stream.

`DataOutputStream::write_ulonglong_array()`

// IDL

```
void write_ulonglong_array(  
    in ULongLongSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Writes an array of `unsigned long long` data to the stream.

Parameters

<code>seq</code>	The sequence of data to write to the stream.
<code>offset</code>	The offset in <code>seq</code> from which to start writing data.
<code>length</code>	The number of data items to write.

`DataOutputStream::write_ushort()`

// IDL

```
void write_ushort(  
    in unsigned short value  
);
```

Writes an `unsigned short` data type to the stream.

Parameters

```
value
```

The value written to the stream.

`DataOutputStream::write_ushort_array()`

// IDL

```
void write_ushort_array(  
    in UShortSeq seq,  
    in unsigned long offset,  
    in unsigned long length  
);
```

Writes an array of `unsigned short` data to the stream.

Parameters

<code>seq</code>	The sequence of data to write to the stream.
<code>offset</code>	The offset in <code>seq</code> from which to start writing data.
<code>length</code>	The number of data items to write.

`DataOutputStream::write_Value()`

// IDL

```
void write_Value(
    in ValueBase value
);
```

Writes a value type to the stream.

Parameters

value

The value written to the stream.

DataOutputStream::write_wchar()

// IDL

```
void write_wchar(
    in wchar value
);
```

Writes a `wchar` data type to the stream.

Parameters

value

The value written to the stream.

DataOutputStream::write_wchar_array()

// IDL

```
void write_wchar_array(
    in WCharSeq seq,
    in unsigned long offset,
    in unsigned long length
);
```

Writes an array of `wchar` data to the stream.

Parameters

seq	The sequence of data to write to the stream.
offset	The offset in seq from which to start writing data.
length	The number of data items to write.

DataOutputStream::write_wstring()

// IDL

```
void write_wstring(  
    in wstring value  
);
```

Writes a wstring data type to the stream.

Parameters

```
value
```

The value written to the stream.

CORBA::DomainManager Interface

The `DomainManager` interface provides an operation to find the Policy objects associated with a policy domain. Each policy domain includes one policy domain manager object (`DomainManager`). The `DomainManager` has associated with it the policy objects for that domain and it records the membership of the domain.

```
// IDL in CORBA Module
interface DomainManager {
    Policy [get_domain_policy](#corbadomainmanager-interface)(
        in PolicyType policy_type
    );
};
```

A *policy domain* is a set of objects with an associated set of policies. These objects are the *policy domain members*. The policies represent the rules and criteria that constrain activities of the objects of the policy domain. Policy domains provide a higher granularity for policy management than an individual object instance provides.

When a new object reference is created, the ORB implicitly associates the object reference (and hence the object that it is associated with) with one or more policy domains, thus defining all the policies to which the object is subject. If an object is simultaneously a member of more than one policy domain, it is governed by all policies of all of its domains.

Each `DomainManager` has a `ConstructionPolicy` object associated with it which has the `make_domain_manager()` operation. This operation controls whether a new `DomainManager` is created or an existing one is used when the new object reference is created.

The `DomainManager` does not include operations to manage domain membership, structure of domains, or to manage which policies are associated with domains. However, because a `DomainManager` is a CORBA object, it has access to the `CORBA::Object` interface, which is available to all CORBA objects. The `Object` interface includes the following related operations:

`_get_domain_managers()` allows your applications to retrieve the domain managers and hence the security and other policies applicable to individual objects that are members of the policy domain.

You can also obtain an object's policy using `_get_policy()`.

`DomainManager::get_domain_policy()`

`Policy get_domain_policy (`

```
    in PolicyType policy_type
);
```

Returns a reference to the policy object of the specified policy type for objects in this policy domain.

Parameters

policy_type

The type of policy for objects in the domain which the application wants to administer.

There may be several policies associated with a domain, with a policy object for each. There is at most one policy of each type associated with a policy domain. The policy objects are thus shared between objects in the domain, rather than being associated with individual objects. Consequently, if an object needs to have an individual policy, then it must be a singleton member of a policy domain.

Exceptions

INV_POLICY

The value of policy type is not valid either because the specified type is not supported by this ORB or because a policy object of that type is not associated with this object.

See Also

CORBA::Policy

```
CORBA::Object::_get_domain_managers()
CORBA::ConstructionPolicy::make_domain_manager()
CORBA::Object::_get_policy()
```

CORBA::EnumDef Interface

Interface `EnumDef` describes an IDL enumeration definition in the interface repository.

```
// IDL in module CORBA.
interface EnumDef : TypedefDef {
    attribute EnumMemberSeq [members](#it_loadbalancingobjectgroup-
interface);
};
```

The inherited operation `describe()` is also described.

`EnumDef::describe()`

// IDL

```
Description describe();
```

Inherited from `Contained` (which `TypedefDef` inherits), `describe()` returns a structure of type `Contained::Description`. The `DefinitionKind` for the description's `kind` member is `dk_Enum`. The value member is an `any` whose `TypeCode` is `_tc_TypeDescription` and whose value is a structure of type `TypeDescription`. The `type` field of the `struct` gives the `TypeCode` of the defined enumeration.

See Also `CORBA::TypedefDef::describe()`

`EnumDef::members` Attribute

// IDL

```
attribute EnumMemberSeq members;
```

Returns or changes the enumeration's list of identifiers (its set of enumerated constants).

See Also `CORBA::Identifier`

CORBA::Environment Class

The `Environment` class provides a way to handle exceptions in situations where true exception-handling mechanisms are unavailable or undesirable.

For example, in the DII you can use the `Environment` class to pass information between a client and a server where the C++ host compiler does not support C++ exception handling.

```
// IDL
pseudo interface Environment {
    attribute exception exception;
    void clear();
};
// C++
class Environment {
public:
    void [exception](#corbaenvironment-class)(Exception* e);
    Exception *[exception](#corbaenvironment-class)() const;
    void [clear](#corbaenvironment-class)();
    [_duplicate](#corbapolicycurrent-class)(Environment_ptr obj);
    [_nil](#corbapolicycurrent-class)();
};
```

See Also `CORBA::ORB::create_environment()`

`Environment::clear()`

//C++

```
void clear();
```

Deletes the Exception, if any, contained in the `Environment`. This is equivalent to passing zero to `exception()`. It is not an error to call `clear()` on an `Environment` that holds no exception.

See Also `CORBA::Environment::exception()`

`Environment::_duplicate()`

// C++


```
static Environment_ptr _duplicate(
    Environment_ptr obj
);
```

Returns a reference to `obj` and increments the reference count of `obj`.

See Also `CORBA::release()`

`Environment::exception()`

Extracts the exception contained in the `Environment` object.

// C++

```
Exception* exception() const;
```

Returns the exception, if any, raised by a preceding remote request. The returned pointer refers to memory owned by the `Environment` and must not be freed by the caller. Once the `Environment` is destroyed, the pointer is no longer valid.

// C++

```
void exception(
    Exception* e
);
```

Assigns the `Exception` denoted by the parameter `e` into the `Environment`.

Parameters

`e`

The `Exception` assigned to the `Environment`. The `Environment` does not copy the parameter but it assumes ownership of it. The `Exception` must be dynamically allocated.

Examples Following is an example of usage:

```
// C++
CORBA::Environment env;
A_var obj = ...
obj->op(env);
if(CORBA::Exception* ex = env.exception()) {
    ...
}
```

You can make a number of remote requests using the same `Environment` variable. Each attempt at a request immediately aborts if the `Exception` referenced by the `Environment` is not 0, and thus any failure causes subsequent requests not to be attempted, until the exception pointer is reset to 0. Any failed call may also generate one or more null proxies, so that any attempts to use these proxies prior to the end of a `TRY` macro (for non-exception handling compilers) are null operations.

The `Environment` retains ownership of the `Exception` returned. Thus, once the `Environment` is destroyed, or its `Exception` cleared, the reference is no longer valid.

See Also `CORBA::Environment::clear()`

`Environment::_nil()`

// C++

```
static Environment_ptr _nil();
```

Returns a nil object reference for an `Environment` object.

See Also `CORBA::is_nil()`

CORBA::Exception Class

Details of this class can be found in the CORBA specification. The C++ Language Mapping document provides the following explanation of the `CORBA::Exception` class:

```
// C++
class Exception
{
    public:
    virtual ~Exception();
    virtual void _raise() const = 0;
    virtual const char * _name() const;
    virtual const char * _rep_id() const;
};
```

The `Exception` base class is abstract and may not be instantiated except as part of an instance of a derived class. It supplies one pure virtual function to the exception hierarchy: the `_raise()` function. This function can be used to tell an exception instance to throw itself so that a catch clause can catch it by a more derived type.

Each class derived from `Exception` implements `_raise()` as follows:

```
// C++
void SomeDerivedException::_raise() const
{
    throw *this;
}
```

For environments that do not support exception handling, please refer to Section 1.42.2, "Without Exception Handling," on page 1-169 of the CORBA specification for information about the `_raise()` function.

The `_name()` function returns the unqualified (unscoped) name of the exception. The `_rep_id()` function returns the repository ID of the exception.

CORBA::ExceptionDef Interface

Interface `ExceptionDef` describes an IDL exception in the interface repository. It inherits from interface `Contained` and `Container`.

```
// IDL in module CORBA.
interface ExceptionDef : Contained, Container {
    readonly attribute TypeCode [type](#corbaattributedef-interface);
    attribute StructMemberSeq [members](#it_loadbalancingobjectgroup-
interface);
};
```

The inherited operation `describe()` is also described.

See Also `CORBA::Contained`

`CORBA::Container`

`ExceptionDef::describe()`

// IDL

Description `describe();`

Inherited from `Contained`, `describe()` returns a structure of type `Contained::Description`.

The `DefinitionKind` for the `kind` member of this structure is `dk_Exception`. The `value` member is an `any` whose `TypeCode` is `_tc_ExceptionDescription` and whose value is a structure of type `ExceptionDescription`.

The `type` field of the `ExceptionDescription` structure gives the `TypeCode` of the defined exception.

See Also `CORBA::Contained::describe()`

`CORBA::TypeCode`

`ExceptionDef::members` Attribute

```
// IDL
```

```
attribute StructMemberSeq members;
```

In a sequence of StructMember structures, the `members` attribute describes the exception's members.

The `members` attribute can be modified to change the structure's members. Only the `name` and `type_def` fields of each StructMember should be set. The `type` field should be set to `_tc_void`, and it will be set automatically to the TypeCode of the `type_def` field.

See Also CORBA :: StructDef

```
CORBA::ExceptionDef::type
```

ExceptionDef::type Attribute

```
// IDL
```

```
readonly attribute TypeCode type;
```

The type of the exception (from which the definition of the exception can be understood). The TypeCode kind for an exception is `tk_except`.

See Also CORBA :: TypeCode

```
CORBA::ExceptionDef::members
```

CORBA::ExceptionList Class

An `ExceptionList` object allows an application to provide a list of `TypeCodes` for all application-specific (user-defined) exceptions that may result when a dynamic invocation Request is invoked. This server-less `ExceptionList` object allows the ORB to avoid potentially expensive interface repository lookups for the exception information during a request.

```
// PIDL
pseudo interface ExceptionList {
    readonly attribute unsigned long count;
    void add(in TypeCode exc);
    TypeCode item(in unsigned long index) raises(Bounds);
    void remove(in unsigned long index) raises(Bounds);
};

// C++
class ExceptionList {
public:
    ULong [count](#corbaexceptionlist-class)();
    void [add](#corbaexceptionlist-class)(TypeCode_ptr tc);
    void [add_consume](#corbaexceptionlist-class)(TypeCode_ptr tc);
    TypeCode_ptr [item](#corbaexceptionlist-class)(ULong index);
    void [remove](#corbaexceptionlist-class)(ULong index);
};
```

See Also `CORBA::Object::_create_request()`

```
CORBA::Request::exceptions
CORBA::ORB::create_exception_list()
```

`ExceptionList::add()`

// C++

```
void add(
    TypeCode_ptr tc
);
```

Adds a `TypeCode` to the exception list.

Parameters

<code>tc</code>	A TypeCode representing exception information.
<code>exc</code>	The <code>TypeCode</code> to be added to the list. Should be a TypeCode for an exception.

See Also CORBA::ExceptionList::add_consume()

ExceptionList::add_consume()

// C++

```
void add_consume(
    TypeCode_ptr tc
);
```

Adds an item to the exception list. The memory of the `tc` parameter is managed by the function. The caller cannot access the memory of `tc` after it has been passed in because this function could copy and free the original immediately.

Parameters

`tc`

A TypeCode representing exception information.

See Also CORBA::ExceptionList::add()

ExceptionList::count()

// C++

```
ULong count();
```

Returns the number of items in the exception list.

ExceptionList::item()

// C++

```
TypeCode_ptr item(  
    ULong index  
);
```

Returns the exception item at the indexed location of the list. This return value must not be released by the caller because ownership of the return value is maintained by the `ExceptionList`.

Parameters

index

The indexed location of the desired item.

ExceptionList::remove()

// C++

```
void remove(  
    ULong index  
);
```

Removes from the exception list the item at the indexed location.

Parameters

index

The indexed location of the desired item.

CORBA::FixedDef Interface

The FixedDef interface describes an IDL fixed-point type in the interface repository. A fixed-point decimal literal consists of an integer part, a decimal point, a fraction part, and a `d` or `D`.

```
// IDL in module CORBA.
interface FixedDef : IDLType {
    attribute unsigned short [digits](#corbafixeddef-interface);
    attribute short [scale](#corbafixeddef-interface);
```

}; The inherited IDLType attribute is a `tk_fixed` TypeCode, which describes a fixed-point decimal number.

See Also CORBA::Repository::create_fixed()

FixedDef::digits Attribute

// IDL

```
attribute unsigned short digits;
```

The `digits` attribute specifies the total number of decimal digits in the fixed-point number, and must be in the range of 1 to 31, inclusive.

FixedDef::scale Attribute

// IDL

```
attribute short scale;
```

The `scale` attribute specifies the position of the decimal point.

CORBA.InterfaceDefPackage.FullInterfaceDescription Class

InterfaceDefPackage.FullInterfaceDescription.FullInterfaceDescription()

// IDL

```
struct FullInterfaceDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    OpDescriptionSeq operations;
    AttrDescriptionSeq attributes;
    RepositoryIdSeq base_interfaces;
    TypeCode type;
    boolean is_abstract;
};
```

Describes an interface including its operations and attributes.

name	The name of the interface.
id	An identifier of the interface.
defined_in	The identifier where the interface is defined.
version	The version of the interface.
operations	A sequence of interface operations.
attributes	A sequence of interface attributes.
base_interfaces	A sequence of base interfaces from which this interface is derived.
type	The type of the interface.
is_abstract	True if the interface is an abstract one, false otherwise.

See Also CORBA::InterfaceDef::describe_interface()

CORBA::IDLType Interface

The abstract base interface `IDLType` describes interface repository objects that represent IDL types. These types include interfaces, type definitions, structures, unions, enumerations, and others. Thus, the `IDLType` is a base interface for the following interfaces:

```
ArrayDef
AliasDef
EnumDef
FixedDef
InterfaceDef
NativeDef
PrimitiveDef
SequenceDef
StringDef
StructDef
TypedefDef
UnionDef
ValueBoxDef
ValueDef
WstringDef
```

The `IDLType` provides access to the `TypeCode` describing the type, and is used in defining other interfaces wherever definitions of IDL types must be referenced.

```
// IDL in module CORBA.
interface IDLType : IObject {
    readonly attribute TypeCode [type](#corbaattributedef-interface);
};
```

See Also `CORBA::IObject`

```
CORBA::TypeCode
CORBA::TypedefDef
```

`IDLType::type` Attribute

//IDL

```
readonly attribute TypeCode type;
```

Encodes the type information of an interface repository object. Most type information can also be extracted using operations and attributes defined for derived types of the IDLType.

See Also CORBA :: TypeCode

CORBA::InterfaceDef Interface

`InterfaceDef` describes an IDL interface definition in the interface repository. It may contain lists of constants, typedefs, exceptions, operations, and attributes. It inherits from the interfaces `Container`, `Contained`, and `IDLType`.

Calling `_get_interface()` on a reference to an object (`interface_ptr` or `interface_var`) returns a reference to the `InterfaceDef` object that defines the CORBA object's interface.

```

// IDL in module CORBA.
interface InterfaceDef : Container, Contained, IDLType {
    // read/write interface
    attribute InterfaceDefSeq [base_interfaces](#corbainterfacedef-
interface);
    // read interface
    boolean [is_a](#corbainterfacedef-interface)(
        in RepositoryId interface_id
    );
    struct [FullInterfaceDescription](#corbainterfacedef-interface) {
        Identifier name;
        RepositoryId id;
        RepositoryId defined_in;
        VersionSpec version;
        OpDescriptionSeq operations;
        AttrDescriptionSeq attributes;
        RepositoryIdSeq base_interfaces;
        TypeCode type;
    };
    FullInterfaceDescription [describe_interface](#corbainterfacedef-
interface)();
    // write interface
    AttributeDef [create_attribute](#corbainterfacedef-interface)(
        in RepositoryId id,
        in Identifier name,
        in VersionSpec version,
        in IDLType type,
        in AttributeMode mode
    );
    OperationDef [create_operation](#corbainterfacedef-interface)(
        in RepositoryId id,
        in Identifier name,
        in VersionSpec version,
        in IDLType result,
        in OperationMode mode,
        in ParDescriptionSeq params,
        in ExceptionDefSeq exceptions,
        in ContextIdSeq contexts
    );
}; // End interface InterfaceDef

```

The inherited operation [describe\(\)](#) is also described.

See Also CORBA :: Contained

```
CORBA::Container
CORBA::Object::_get_interface()
```

InterfaceDef::base_interfaces Attribute

// IDL

```
attribute InterfaceDefSeq base_interfaces;
```

The `base_interfaces` attribute lists in a sequence of `InterfaceDef` objects the interfaces from which this interface inherits.

The inheritance specification of an `InterfaceDef` object can be changed by changing its `base_interfaces` attribute.

Exceptions

`BAD_PARAM`, minor code 5

The `name` of any definition contained in the interface conflicts with the `name` of a definition in any of the base interfaces.

See Also `CORBA::Object::_get_interface()`

InterfaceDef::create_attribute()

// IDL

```
AttributeDef create_attribute(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in IDLType type,
    in AttributeMode mode
);
```

Creates a new `AttributeDef` within the target `InterfaceDef`. The `defined_in` attribute of the new `AttributeDef` is set to the target `InterfaceDef`.

Parameters

<code>id</code>	The identifier of the new attribute. It is an error to specify an <code>id</code> that already exists within the target object's repository.
<code>name</code>	The name of the attribute. It is an error to specify a <code>name</code> that already exists within this <code>InterfaceDef</code> .
<code>version</code>	A version for this attribute.
<code>type</code>	The IDLType for this attribute.
<code>mode</code>	Specifies whether the attribute is read only (ATTR_READONLY) or read/write (ATTR_NORMAL).

Exceptions

<code>BAD_PARAM</code> , minor code <code>2</code>	An object with the specified <code>id</code> already exists in the repository.
<code>BAD_PARAM</code> , minor code <code>3</code>	An object with the same <code>name</code> already exists in this <code>Interface Def</code> .

See Also `CORBA::AttributeDef`

`InterfaceDef::create_operation()`

// IDL

```
OperationDef create_operation(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in IDLType result,
    in OperationMode mode,
    in ParDescriptionSeq params,
    in ExceptionDefSeq exceptions,
    in ContextIdSeq contexts
);
```

Creates a new `OperationDef` within the target `InterfaceDef`. The `defined_in` attribute of the new `OperationDef` is set to the target `InterfaceDef`.

Parameters

<code>id</code>	The identifier of the new attribute. It is an error to specify an <code>id</code> that already exists within the target object's repository.
<code>name</code>	The name of the attribute. It is an error to specify a <code>name</code> that already exists within this <code>InterfaceDef</code> .
<code>version</code>	A version number for this operation.
<code>result</code>	The return type for this operation.
<code>mode</code>	Specifies whether this operation is normal (OP_NORMAL) or oneway (OP_ONeway).
<code>params</code>	A sequence of ParameterDescription structures that describes the parameters to this operation.
<code>exceptions</code>	A sequence of ExceptionDef objects that describes the exceptions this operation can raise.
<code>contexts</code>	A sequence of context identifiers for this operation.

See Also CORBA::OperationDef

CORBA::ExceptionDef

InterfaceDef::describe()

// IDL

```
Description describe();
```

Inherited from Contained, `describe()` returns a structure of type Contained::Description. The DefinitionKind for the `kind` member is `dk_Interface`. The value member is an `any` whose TypeCode is `_tc_InterfaceDescription` and whose value is a structure of type InterfaceDescription.

See Also CORBA::Contained::describe()

InterfaceDef::describe_interface()

// IDL

```
FullInterfaceDescription describe_interface();
```

Returns a description of the interface, including its operations, attributes, and base interfaces in a FullInterfaceDescription.

Details of exceptions and contexts can be determined via the returned sequence of OperationDescription structures.

See Also CORBA::OperationDef::describe()

```
CORBA::AttributeDef::describe()
```

InterfaceDef::FullInterfaceDescription Structure

// IDL

```
struct FullInterfaceDescription {
    Identifier name;
    RepositoryId id;
    RepositoryId defined_in;
    VersionSpec version;
    OpDescriptionSeq operations;
    AttrDescriptionSeq attributes;
    RepositoryIdSeq base_interfaces;
    TypeCode type;
};
```

Describes an interface including its operations and attributes.

name	The name of the interface.
id	An identifier of the interface.
defined_in	The identifier where the interface is defined.
version	The version of the interface.
operations	A sequence of interface operations.
attributes	A sequence of interface attributes.
base_interfaces	A sequence of base interfaces from which this interface is derived.

<code>type</code>	The type of the interface.

See Also CORBA::InterfaceDef::describe_interface()

InterfaceDef::is_a()

// IDL

```
boolean is_a(  
    in RepositoryId interface_id  
);
```

Returns `TRUE` if the interface is either identical to or inherits (directly or indirectly) from the interface represented by `interface_id`. Otherwise the operation returns `FALSE`.

Parameters

`interface_id`

The repository ID of another `InterfaceDef` object.

CORBA::IObject Interface

The interface `IObject` is the base interface from which all interface repository interfaces are derived.

```
// IDL in module CORBA.
interface IObject {
    readonly attribute DefinitionKind [def_kind](#corbaiobject-interface);
    void [destroy](#cosnamingbindingiterator-interface)();
};
```

`IObject::def_kind` Attribute

// IDL

```
readonly attribute DefinitionKind def_kind;
```

Identifies the kind of an IFR object. For example, an `OperationDef` object, describing an IDL operation, has the kind `dk_Operation`.

See Also `CORBA::DefinitionKind`

`IObject::destroy()`

// IDL

```
void destroy();
```

Deletes an IFR object. This also deletes any objects contained within the target object.

Exceptions `BAD_INV_ORDER` with a minor value of:

2	<code>destroy()</code> is invoked on a Repository or on a PrimitiveDef object.
1	An attempt is made to destroy an object that would leave the repository in an incoherent state.

CORBA::ModuleDef Interface

The interface `ModuleDef` describes an IDL module in the interface repository. It inherits from the interfaces `Container` and `Contained`.

```
// IDL in module CORBA.  
interface ModuleDef : Container, Contained { };
```

The inherited operation `describe()` is also described.

`ModuleDef::describe()`

// IDL

```
Description describe();
```

Inherited from `Contained`, `describe()` returns a structure of type `Contained::Description`.

The `kind` member is `dk_Module`. The value member is an `any` whose TypeCode is `_tc_ModuleDescription` and whose value is a structure of type `ModuleDescription`.

See Also `CORBA::Contained::describe()`

CORBA::NamedValue Class

A `NamedValue` object describes an argument to a request or a return value, especially in the DII, and is used as an element of an `NVList` object. A `NamedValue` object maintains an `any` value, parameter-passing mode flags, and an (optional) name.

```
// IDL
pseudo interface NamedValue {
    readonly attribute Identifier name;
    readonly attribute any value;
    readonly attribute Flags flags;
};

// C++
class NamedValue {
public:
    const char *[name](#corbanamedvalue-class)() const;
    Any *[value](#it_portableserverobjectdeactivationpolicy-class)() const;
    Flags [flags](#corbanamedvalue-class)() const;
    static NamedValue_ptr [_duplicate](#corbapolicycurrent-class)
(NamedValue_ptr nv);
    static NamedValue_ptr [_nil](#corbapolicycurrent-class)();
};
```

See Also `CORBA::NVList`

```
CORBA::ORB::create_named_value()
CORBA::Request::result()
CORBA::Object::_create_request()
```

`NamedValue::_duplicate()`

`static NamedValue_ptr _duplicate(NamedValue_ptr nv);`

Returns a new reference to the `NamedValue` object input and increments its reference count.

Parameters

nv

The `NamedValue` object reference to be duplicated.

See Also `CORBA::release()`

`NamedValue::flags()`

Flags `flags() const;`

Returns the flags associated with the `NamedValue`. Flags identify the parameter passing mode for arguments of an `NVList`.

See Also `CORBA::Flags`

`NamedValue::name()`

`const char *name() const;`

Returns a pointer to the optional name associated with the `NamedValue`. This is the name of a parameter or argument of a request. The return value is a pointer to the internal memory of the `NamedValue` object and must not be freed by the caller.

`NamedValue::_nil()`

`static NamedValue_ptr _nil();`

Returns a nil object reference for a `NamedValue`.

See Also `CORBA::is_nil()`

`NamedValue::value()`

`Any *value() const;`

Returns a pointer to `Any` value contained in the `NamedValue`.

The return value is a pointer to the internal memory of the `NamedValue` object and must not be freed by the caller. However, the value in a `NamedValue` may be manipulated via standard operations on `any` values.

CORBA::NativeDef Interface

The interface `NativeDef` describes an IDL native type in the interface repository. It inherits from the interface `TypedefDef`. The inherited type attribute is a `tk_native` `TypeCode` that describes the native type.

```
// IDL in module CORBA
interface NativeDef : TypedefDef {};
```

See Also `CORBA::Container::create_native()`

CORBA::NVList Class

An `NVList` is a pseudo-object used for constructing parameter lists. It is a list of `NamedValue` elements where each `NamedValue` describes an argument to a request.

The `NamedValue` and `NVList` types are used mostly in the DII in the request operations to describe arguments and return values. They are also used in the context object routines to pass lists of property names and values. The `NVList` is also used in the DSI operation `ServerRequest::arguments()`.

The `NVList` class is partially opaque and may only be created by using `ORB::create_list()`. The `NVList` class is as follows:

```
// IDL
pseudo interface NVList {
    readonly attribute unsigned long count;
    NamedValue add(in Flags flags);
    NamedValue add_item(in Identifier item_name, in Flags flags);
    NamedValue add_value( in Identifier item_name,
        in any val, in Flags flags );
    NamedValue item(in unsigned long index) raises(Bounds);
    void remove(in unsigned long index) raises(Bounds);
};

// C++
class NVList {
public:
    ULong count() const;
    NamedValue_ptr [add](#corbaexceptionlist-class)(Flags);
    NamedValue_ptr [add_item](#corbanvlist-class)(const char*, Flags);
    NamedValue_ptr [add_value](#corbanvlist-class)(const char*, const Any&,
Flags);
    NamedValue_ptr [add_item_consume](#corbanvlist-class)(char*, Flags);
    NamedValue_ptr [add_value_consume](#corbanvlist-class)(char*, Any*,
Flags);
    NamedValue_ptr [item](#corbaexceptionlist-class)(ULong);
    void [remove](#corbaexceptionlist-class)(ULong);
    static NVList_ptr [_duplicate](#corbapolicycurrent-class)(NVList_ptr nv);
    static NVList_ptr [_nil](#corbapolicycurrent-class)();
};
```

See Also `CORBA::NamedValue`

```
CORBA::ORB:create_list()
CORBA::Object::_create_request()
```

NVList::count()

```
ULong count() const;
```

Returns the number of elements in the list.

NVList::add()

NamedValue_ptr add(

```
    Flags flags
);
```

Creates an unnamed value, initializes only the flags, and adds it to the list. The new NamedValue is returned.

Parameters

flags

Possible values include:

```
ARG_IN
ARG_OUT
ARG_INOUT
IN_COPY_VALUE
DEPENDENT_LIST
```

The reference count of the returned NamedValue pseudo object is not incremented. Therefore, the caller should not release the returned reference when no longer needed, nor assign it to a `type_var` variable.

See Also CORBA::NVList::add_item()

```

CORBA::NVList::add_value()
CORBA::NVList::add_item_consume()
CORBA::NVList::add_value_consume()

```

NVList::add_item()

NamedValue_ptr add_item(

```

    const char* item_name,
    Flags flags
);

```

Creates and returns a NamedValue with name and flags initialized, and adds it to the list.

Parameters

item_name	Name of item.
flags	Possible values include: - ARG_IN - ARG_OUT - ARG_INOUT - IN_COPY_VALUE - DEPENDENT_LIST

The reference count of the returned NamedValue pseudo object is not incremented. Therefore, the caller should not release the returned reference when no longer needed, nor assign it to a `type_var` variable.

See Also CORBA::NVList::add()

```

CORBA::NVList::add_value()
CORBA::NVList::add_item_consume()
CORBA::NVList::add_value_consume()

```

NVList::add_item_consume()

NamedValue_ptr add_item_consume(

```

    char* item_name,
    Flags flags
);

```

Creates and returns a NamedValue with name and flags initialised, and adds it to the list. The `NVList` takes over memory management responsibilities for the `item_name` parameter.

Parameters

<code>item_name</code>	Name of item. This parameter is consumed by the <code>NVList</code> . The caller may not access this data after it has been passed to this function.
<code>flags</code>	Possible values include: <code>ARG_IN</code> <code>ARG_OUT</code> <code>ARG_INOUT</code> <code>IN_COPY_VALUE</code> <code>DEPENDENT_LIST</code>

The reference count of the returned NamedValue pseudo object is not incremented. Therefore, the caller should not release the returned reference when no longer needed, nor assign it to a `type_var` variable.

See Also `CORBA::NVList::add()`

```

CORBA::NVList::add_item()
CORBA::NVList::add_value()
CORBA::NVList::add_value_consume()

```

`NVList::add_value()`

NamedValue_ptr add_value(

```

    const char* item_name,
    const Any& value,
    Flags flags
);

```

Creates and returns a NamedValue with name, value, and flags initialized and adds it to the list.

Parameters

<code>item_name</code>	Name of item.
<code>value</code>	Value of item.
<code>flags</code>	Possible values include: <code>ARG_IN</code> <code>ARG_OUT</code> <code>ARG_INOUT</code> <code>IN_COPY_VALUE</code> <code>DEPENDENT_LIST</code>

The reference count of the returned NamedValue pseudo object is not incremented. Therefore, the caller should not release the returned reference when no longer needed, nor assign it to a `type_var` variable.

See Also CORBA::NVList::add()

```
CORBA::NVList::add_item()
CORBA::NVList::add_item_consume()
CORBA::NVList::add_value_consume()
```

NVList::add_value_consume()

NamedValue_ptr add_value_consume(

```
    char* item_name,
    Any* value,
    Flags flags
);
```

Creates and returns a NamedValue with name, value, and flags initialised, and adds it to the list. The `NVList` takes over memory management responsibilities for both the name and value parameters.

Parameters

<code>item_name</code>	Name of item. This parameter is consumed by the <code>NVList</code> . The caller may not access this data after it has been passed to this function.

<code>value</code>	Value of item. This parameter is consumed by the <code>NVList</code> . The caller may not access this data after it has been passed to this function.
<code>flags</code>	Possible values include: <code>ARG_IN</code> <code>ARG_OUT</code> <code>ARG_INOUT</code> <code>IN_COPY_VALUE</code> <code>DEPENDENT_LIST</code>

The caller should use `NamedValue::value()` to modify the value attribute of the underlying `NamedValue`, if needed.

The reference count of the returned `NamedValue` pseudo object is not incremented. Therefore, the caller should not release the returned reference when no longer needed, nor assign it to a `type_var` variable.

See Also `CORBA::NamedValue::value()`

```

CORBA::NVList::add()
CORBA::NVList::add_item()
CORBA::NVList::add_item_consume()
CORBA::NVList::add_value()

```

`NVList::count()`

`ULong count() const;`

Returns the number of `NamedValue` elements in the `NVList`.

`NVList::_duplicate()`

`static NVList_ptr _duplicate(`

```

    NVList_ptr nv
);

```

Returns a new reference to the `NVList` and increments the reference count of the `nv` object.

Parameters

```
nv
```

The NamedValue for which to get a duplicate reference.

See Also CORBA::release()

NVList::item()

NamedValue_ptr item(

```
    ULong index
);
```

Returns the NamedValue list item at the given index. The first item is at index 0. This method can be used to access existing elements in the list.

Parameters

```
index
```

Index of item.

Exceptions

```
Bounds
```

The index is out of range.

NVList::_nil()

static NVList_ptr _nil();

Returns a nil object reference for an `NVList` object.

See Also CORBA::is_nil()

NVList::remove()

void remove(

```
        ULong index  
    );
```

Removes the item at the given index. The first item is at index 0. The method calls CORBA::release() on the item.

Parameters

index

Index of item

Exceptions

Bounds

The index is out of range.

See Also CORBA::release()

CORBA::Object Class

The `Object` class is the base class for all normal CORBA objects. This class has some common methods that operate on any CORBA object. These operations are implemented directly by the ORB, not passed on to your object's implementation.

On the client side, the methods of this class are called on a proxy (unless collocation is set). On the server side, they are called on the real object.

Table 5 shows the methods provided by the `CORBA::Object` class:

Table 5: Methods of the Object Class

Manage Object References	Create Requests for the DII
<code>_release()</code>	Access Information in the IFR
	<code>_get_interface()</code>
Manage Policies and Domains	Enhancements
<code>_validate_connection()</code>	<code>_it_get_type_id()</code>

The CORBA namespace provides the `is_nil()` and `release()` operations that are defined in the `Object` interface's IDL. All other IDL operations for the `Object` interface map to C++ functions with leading underscores.

```

// IDL
interface Object {
    boolean is_nil();
    Object duplicate();
    void release();
    ImplementationDef get_implementation();
    InterfaceDef get_interface();
    boolean is_a(in string logical_type_id);
    boolean non_existent();
    boolean is_equivalent(in Object other_object);
    unsigned long hash(in unsigned long maximum);
    void create_request(
        in Context ctx,
        in Identifier operation,
        in NVList arg_list,
        in NamedValue result,
        out Request request,
        in Flags req_flags
    );
    void create_request2(
        in Context ctx,
        in Identifier operation,
        in NVList arg_list,
        in NamedValue result,
        in ExceptionList exclist,
        in ContextList ctxtlist,
        out Request request,
        in Flags req_flags
    );
    Policy_ptr get_policy(in PolicyType policy_type);
    DomainManagerList get_domain_managers();
    Object set_policy_overrides(
        in PolicyList policies,
        in SetOverrideType set_or_add
    );
};

// IDL Additions from CORBA Messaging
Policy get_policy(
    in PolicyType type
);
Policy get_client_policy(
    in PolicyType type
);
Object set_policy_overrides(
    in PolicyList policies,
    in SetOverrideType set_add
)

```

```

        raises (InvalidPolicies);
PolicyList get_policy_overrides(
    in PolicyTypeSeq types
);
boolean validate_connection(
    out PolicyList inconsistent_policies
);
};
class Object {
public:
    static Object_ptr [_duplicate](#corbapolicycurrent-class)(Object_ptr
obj);
    static Object_ptr [_nil](#corbapolicycurrent-class)();
    InterfaceDef_ptr [_get_interface](#corbaobject-class)();
    Boolean [_is_a](#corbaobject-class)(const char* logical_type_id);
    Boolean [_non_existent](#corbaobject-class)();
    Boolean [_is_equivalent](#corbaobject-class)(Object_ptr other_object);
    ULong [_hash](#corbaobject-class)(ULong maximum);
    void [_create_request](#corbaobject-class)(
        Context_ptr ctx,
        const char      *operation,
        NVList_ptr      arg_list,
        NamedValue_ptr  result,
        Request_out     request,
        Flags           req_flags
    );
    void [_create_request](#corbaobject-class)(
        Context_ptr      ctx,
        const char        *operation,
        NVList_ptr        arg_list,
        NamedValue_ptr    result,
        ExceptionList_ptr ,
        ContextList_ptr   ,
        Request_out       request,
        Flags             req_flags
    );
    Request_ptr [_request](#corbaobject-class)(const char* operation);
    Policy_ptr [_get_policy](#corbaobject-class)(PolicyType policy_type);
    DomainManagerList* [_get_domain_managers](#corbaobject-class)();
    Object_ptr [_set_policy_overrides](#corbaobject-class)(
        const PolicyList &policies,
        SetOverrideType set_add
    );
    virtual Policy_ptr [_get_client_policy](#corbaobject-class)(
        PolicyType type
    ) = 0;
    virtual PolicyList * [_get_policy_overrides](#corbaobject-class)(

```

```

        const PolicyTypeSeq & types
    ) = 0;
    virtual Boolean [_validate_connection](#corbaobject-class)(
        PolicyList &inconsistent_policies
    ) = 0;
    //
    // Non-CORBA pseudo-operations.
    //
    virtual ORB_ptr [_it_get_orb()](#corbaobject-class) = 0;
    virtual Object_ptr [_it_proxy_for()](#corbaobject-class) = 0;
    virtual void [_it_marshall](#corbaobject-class)(
        IT_OutputStream_ptr os,
        ORB_ptr orb
    ) = 0;
    virtual char* [_it_get_type_id()](#corbaobject-class) = 0;
};

```

****Object::_create_request()

void _create_request(

```

    Context_ptr ctx,
    const char *operation,
    NVList_ptr arg_list,
    NamedValue_ptr result,
    Request_out request,
    Flags req_flags
);

```

void _create_request(

```

    Context_ptr ctx,
    const char *operation,
    NVList_ptr arg_list,
    NamedValue_ptr result,
    ExceptionList_ptr exceptions,
    ContextList_ptr contexts,
    Request_out request,
    Flags req_flags
);

```

These construct a CORBA::Request object. These methods are part of the DII and create an ORB request on an object by constructing one of the object's operations.

See `_request()` for a simpler alternative way to create a Request.

Parameters

<code>ctx</code>	Context object, if any, to be sent in the <code>request</code> . If the <code>ctx</code> argument to <code>_create_request()</code> is a nil Context object reference, then you can add the <code>Context</code> later by calling the <code>Request::ctx()</code> function on the Request object.
<code>operation</code>	The name of the request operation. The operation name is the same operation identifier that is specified in the IDL definition for this operation.
<code>arg_list</code>	The parameters, for the operation, each of type <code>NamedValue</code> . If this value is zero, you can add the arguments later by calling the <code>Request::arguments()</code> function. You can also add each argument one at a time by calling the appropriate helper function such as <code>add_in_arg()</code> on the Request object.
<code>result</code>	The result of the operation invocation is placed in this argument after the invocation completes. Use <code>ORB::create_named_value()</code> to create the <code>NamedValue</code> object to be used as this return value parameter.
<code>request</code>	Contains the newly created Request.
<code>req_flags</code>	If you specify flag values they are ignored because argument insertion or extraction is handled using the <code>Any</code> type.
<code>exceptions</code>	A reference to a list of <code>TypeCodes</code> for all application-specific (user-defined) exceptions that may result when the Request is invoked.
<code>contexts</code>	A reference to a list of context strings for the operation.

The only implicit object reference operations allowed with the `_create_request()` call include:

```
_non_existent()
_is_a()
_get_interface()
```

Exceptions

BAD_PARAM

The name of an implicit operation that is not allowed is passed to `_create_request()`—for example, `_is_equivalent` is passed to `_create_request()` as the `operation` parameter.

See Also `CORBA::Object::_request()`

```
CORBA::Request
CORBA::Request::arguments()
CORBA::Request::ctx()
CORBA::NVList
CORBA::NamedValue
```

`Object::_duplicate()`

`static Object_ptr _duplicate(`

```
    Object_ptr obj
);
```

Returns a new reference to `obj` and increments the reference count of the object. Because object references are opaque and ORB-dependent, it is not possible for your application to allocate storage for them. Therefore, if more than one copy of an object reference is needed, use this method to create a duplicate.

Parameters

`obj`

Pointer to the object to duplicate.

See Also `CORBA::release()`

`Object::_get_client_policy()`

`virtual Policy_ptr _get_client_policy(`

```
PolicyType type
) = 0;
```

Returns the effective overriding policy for the object reference. The effective override is obtained by first checking for an override of the given PolicyType at the Object scope, then at the Current scope, and finally at the ORB scope. If no override is present for the requested PolicyType, the system-dependent default value for that PolicyType is used.

Portable applications should set the desired defaults at the `ORB` scope since default policy values are not specified.

Parameters

```
type
```

The type of policy desired.

See Also `CORBA::Object::_get_policy()`

```
CORBA::Object::_set_policy_overrides()
CORBA::Object::_get_policy_overrides()
```

`Object::_get_domain_managers()`

`DomainManagersList* _get_domain_managers();`

Returns the list of immediately enclosing domain managers of this object. At least one domain manager is always returned in the list since by default each object is associated with at least one domain manager at creation.

The `_get_domain_managers()` method allows applications such as administration services to retrieve the domain managers and hence the security and other policies applicable to individual objects that are members of the domain.

See Also `CORBA::DomainManager`

`Object::_get_interface()`

`InterfaceDef_ptr _get_interface();`

Returns a reference to an object in the interface repository that describes this object's interface.

See Also `CORBA::InterfaceDef`

Object::_get_policy()

Policy_ptr _get_policy(

```
    PolicyType policy_type
);
```

Returns a reference to the Policy object of the type specified by the `policy_type` parameter.

Parameters

`policy_type`

The type of policy to get.

`_get_policy()` returns the effective policy which is the one that would be used if a request were made. Note that the effective policy may change from invocation to invocation due to transparent rebinding. Invoking `_non_existent()` on an object reference prior to `_get_policy()` ensures the accuracy of the returned effective policy.

Quality of Service (see [Quality of Service Framework](#)) is managed on a per-object reference basis with `_get_policy()`, `_set_policy_overrides()`, `_get_policy_overrides()`, and `_get_client_policy()`.

Exceptions

INV_POLICY

The value of `policy_type` is not valid either because the specified type is not supported by this ORB or because a policy object of that type is not associated with this object.

See Also CORBA::Object::_non_existent()

```
CORBA::Object::_set_policy_overrides()
CORBA::Object::_get_policy_overrides()
CORBA::Object::_get_client_policy()
CORBA::Object::_validate_connection()
```

Object::_get_policy_overrides()

virtual PolicyList * _get_policy_overrides(


```
const PolicyTypeSeq & types
) = 0;
```

Returns the list of policy overrides of the specified policy types set at the Object scope. If the specified sequence is empty, all policy overrides at this scope will be returned. If none of the requested policy types are overridden at the Object scope, an empty sequence is returned.

Parameters

types

A sequence of policy types for which the overrides are desired.

See Also CORBA::Object::_get_policy()

```
CORBA::Object::_set_policy_overrides()
CORBA::Object::_get_client_policy()
```

Object::_hash()

ULong _hash(

```
    ULong maximum
);
```

Returns a hashed value for the object reference in the range 0 ... maximum.

Parameters

maximum

The maximum value that is to be returned from the hash method.

Use `_hash()` to quickly guarantee that objects references refer to different objects. For example, if `_hash()` returns the same hash number for two object references, the objects might or might not be the same, however, if the method returns different numbers for object references, these object references are guaranteed to be for different objects.

In order to efficiently manage large numbers of object references, some applications need to support a notion of object reference identity. Object references are associated with internal identifiers that you can access indirectly by using `_hash()`. The value of this internal identifier does not change during the lifetime of the object reference.

You can use `_hash()` and `_is_equivalent()` to support efficient maintenance and search of tables keyed by object references. `_hash()` allows you to partition the space of object references into sub-spaces of potentially equivalent object references. For example, setting `maximum` to 7 partitions the object reference space into a maximum of 8 sub-spaces (0 - 7).

See Also `CORBA::Object::_is_equivalent()`

`Object::_is_a()`

Boolean `_is_a()`

```
const char* logical_type_id
);
```

Returns 1 (true) if the target object is either an instance of the type specified in `logical_type_id` or of a derived type of the type in `logical_type_id`. If the target object is neither, it returns 0 (false).

Parameters

`logical_type_id`

The fully scoped name of the IDL interface. This is a string denoting a shared type identifier (`RepositoryId`). Use an underscore ('_') rather than a scope operator (::) to delimit the scope.

The ORB maintains type-safety for object references over the scope of an ORB, but you can use this method to help maintaining type-safety when working in environments that do not have compile time type checking to explicitly maintain type safety.

Exceptions If `_is_a()` cannot make a reliable determination of type compatibility due to failure, it raises an exception in the calling application code. This enables the application to distinguish among the true, false, and indeterminate cases.

See Also `CORBA::Object::_non_existent()`

`Object::_is_equivalent()`

Boolean `_is_equivalent()`

```
Object_ptr other_object
);
```

Returns 1 (true) if the object references definitely refer to the same object. A return value of 0 (false) does not necessarily mean that the object references are not equivalent, only that the ORB cannot confirm that they reference the same object. Two objects are equivalent if they have the same object reference, or they both refer to the same object.

Parameters

```
other_object
```

An object reference of other object.

A typical application use of `_is_equivalent()` is to match object references in a hash table. Bridges could use the method to shorten the lengths of chains of proxy object references. Externalization services could use it to flatten graphs that represent cyclical relationships between objects.

See Also `CORBA::Object::_is_a()`

```
CORBA::Object::_hash()
```

```
Object::_it_get_orb()
```

```
virtual ORB_ptr _it_get_orb() = 0;
```

Returns the ORB.

Enhancement This is an Orbix enhancement.

```
Object::_it_get_type_id()
```

```
virtual char* _it_get_type_id() = 0;
```

Returns the repository ID string contained within the Interoperable Object Reference (IOR). If the IOR contains no type ID the return value is an empty string. This function follows the standard C++ mapping rules for string return values, which means the caller of this function must take responsibility for the returned string and ensure that it is freed via `CORBA::string_free()` when they are finished with it.

Enhancement This is an Orbix enhancement.

```
Object::_it_marshal()
```

virtual void _it_marshall(

```
    IT_OutputStream_ptr os,
    ORB_ptr orb
) = 0;
```

EnhancementThis is an Orbix enhancement.

Object::_it_proxy_for()

virtual Object_ptr _it_proxy_for() = 0;

Returns a proxy for this object.

EnhancementThis is an Orbix enhancement.

Object::_nil()

static Object_ptr _nil();

Returns a nil object reference.

See AlsoCORBA::is_nil()

Object::_non_existent()

Boolean _non_existent();

Returns 1 (true) if the object does not exist or returns 0 (false) otherwise.

Normally you might invoke this method on a proxy to determine whether the real object still exists. This method may be used to test whether an object has been destroyed because the method does not raise an exception if the object does not exist.

Applications that maintain state that includes object references, (such as bridges, event channels, and base relationship services) might use this method to sift through object tables for objects that no longer exist, deleting them as they go, as a form of garbage collection.

Object::_request()

Request_ptr _request(

```
    const char* operation
);
```

Returns a reference to a constructed Request on the target object. This is the simpler form of `_create_request()`.

Parameters

`operation`

The name of the operation.

You can add arguments and contexts after construction using `Request::arguments()` and `Request::ctx()`.

See Also `CORBA::Object::_create_request()`

```
CORBA::Request::arguments()
CORBA::Request::ctx()
```

`Object::_set_policy_overrides()`

`Object_ptr _set_policy_overrides(`

```
    const PolicyList& policies,
    SetOverrideType  set_add
);
```

Returns a new object reference with the overriding policies associated with it.

Parameters

<code>policies</code>	A sequence of Policy object references that are to be associated with the new copy of the object reference returned.
<code>set_add</code>	Indicates whether the policies are in addition to (ADD_OVERRIDE) or as replacement of (SET_OVERRIDE) any existing overrides already associated with the object reference.

Exceptions

NO_PERMISSION

An attempt is made to override any policy that cannot be overridden. Only certain policies that pertain to the invocation of an operation at the client end can be overridden using this operation.

See Also CORBA::Object::_get_policy()

```
CORBA::Object::_get_policy_overrides()
CORBA::Object::_get_client_policy()
```

Object::_validate_connection()

virtual Boolean _validate_connection(

```
    PolicyList &inconsistent_policies
) = 0;
```

Returns true if the current effective policies for the object will allow an invocation to be made. Returns false if the current effective policies would cause an invocation to raise the system exception `INV_POLICY`.

Parameters

`inconsistent_policies`

If the current effective policies are incompatible, This parameter contains those policies causing the incompatibility. This returned list of policies is not guaranteed to be exhaustive.

If the object reference is not yet bound, a binding will occur as part of this operation. If the object reference is already bound, but current policy overrides have changed or for any other reason the binding is no longer valid, a rebind will be attempted regardless of the setting of any `RebindPolicy` override. This method is the only way to force such a rebind when implicit rebinds are disallowed by the current effective `RebindPolicy`.

Exceptions The appropriate system exception is raised if the binding fails due to some reason unrelated to policy overrides.

CORBA::OperationDef Interface

Interface `OperationDef` describes an IDL operation that is defined in an IDL interface stored in the interface repository.

One way you can use the `OperationDef` is to construct an NVList for a specific operation for use in the Dynamic Invocation Interface. For details see `ORB::create_operation_list()`.

```
// IDL in module CORBA.
interface OperationDef : Contained {
    readonly attribute TypeCode [result](#portableinterceptorrequestinfo-
interface);
    attribute IDLType [result_def](#corbaoperationdef-interface);
    attribute ParDescriptionSeq [params](#corbaoperationdef-interface);
    attribute OperationMode [mode](#corbaattributedef-interface);
    attribute ContextIdSeq [contexts](#portableinterceptorrequestinfo-
interface);
    attribute ExceptionDefSeq [exceptions](#portableinterceptorrequestinfo-
interface);
};
```

The inherited operation `describe()` is also described.

See Also `CORBA::Contained`

```
CORBA::ORB::create_operation_list()
CORBA::ExceptionDef
```

`OperationDef::contexts` Attribute

// IDL

```
attribute ContextIdSeq contexts;
```

The list of context identifiers specified in the context clause of the operation.

`OperationDef::exceptions` Attribute

// IDL

```
attribute ExceptionDefSeq exceptions;
```

The list of exceptions that the operation can raise.

See Also CORBA::ExceptionDef

OperationDef::describe()

// IDL

```
Description describe();
```

Inherited from Contained, `describe()` returns a structure of type Contained::Description.

The DefinitionKind for the `kind` member of this structure is `dk_Operation`. The value member is an `any` whose TypeCode is `_tc_OperationDescription` and whose value is a structure of type OperationDescription.

See Also CORBA::Contained::describe()

```
CORBA::ExceptionDef
```

OperationDef::mode Attribute

// IDL

```
attribute OperationMode mode;
```

Specifies whether the operation is normal (OP_NORMAL) or oneway (OP_ONeway). The `mode` attribute can only be set to OP_ONeway if the `result` is `_tc_void` and all parameters have a `mode` of PARAM_IN.

OperationDef::params Attribute

// IDL

```
attribute ParDescriptionSeq params;
```

Specifies the parameters for this operation. It is a sequence of structures of type ParameterDescription.

The `name` member of the `ParameterDescription` structure provides the name for the parameter. The `type` member identifies the `TypeCode` for the parameter. The `type_def` member identifies the definition of the type for the parameter. The `mode` specifies whether the parameter is an `in` (`PARAM_IN`), an `out` (`PARAM_OUT`) or an `inout` (`PARAM_INOUT`) parameter. The order of the `ParameterDescription`s is significant.

See Also `CORBA::TypeCode`

```
CORBA::IDLType
```

`OperationDef::result` Attribute

// IDL

```
readonly attribute TypeCode result;
```

The return type of this operation. The attribute `result_def` contains the same information.

See Also `CORBA::TypeCode`

```
CORBA::OperationDef::result_def
```

`OperationDef::result_def` Attribute

// IDL

```
attribute IDLType result_def;
```

Describes the return type for this operation. The attribute `result` contains the same information.

Setting the `result_def` attribute also updates the `result` attribute.

See Also `CORBA::IDLType`

```
CORBA::OperationDef::result
```

CORBA::ORB Class

The `ORB` class provides a set of methods and data types that control the ORB from both the client and the server. See [Table 6](#):

Table 6: Methods and Types of the ORB Class

Object Reference Manipulation	ORB Operation and Threads
<code>_duplicate()</code> <code>list_initial_services()</code> <code>type sequence</code> <code>object_to_string()</code> <code>resolve_initial_references()</code> <code>string_to_object()</code>	<code>destroy()</code> <code>perform_work()</code> <code>run()</code> <code>shutdown()</code> <code>work_pending()</code>
	ORB Policies and Services
	<code>create_policy()</code> <code>get_service_information()</code>
Dynamic Invocation Interface (DII)	TypeCode Creation Methods
<code>create_exception_list()</code> <code>create_list()</code> <code>create_named_value()</code> <code>create_operation_list()</code> <code>get_next_response()</code> <code>poll_next_response()</code> <code>sequence</code> <code>send_multiple_requests_deferred()</code> <code>send_multiple_requests_oneway()</code>	<code>create_abstract_interface_tc()</code> <code>create_alias_tc()</code> <code>create_array_tc()</code> <code>create_enum_tc()</code> <code>create_exception_tc()</code> <code>create_fixed_tc()</code> <code>create_interface_tc()</code> <code>create_native_tc()</code> <code>create_recursive_tc()</code> <code>create_sequence_tc()</code> <code>create_string_tc()</code> <code>create_struct_tc()</code> <code>create_union_tc()</code> <code>create_value_box_tc()</code> <code>create_value_tc()</code> <code>create_wstring_tc()</code>
Value Type Factory Methods	
<code>lookup_value_factory()</code> <code>register_value_factory()</code> <code>unregister_value_factory()</code>	

You initialize the ORB using `ORB_init()`.

The `ORB` class is defined as follows:

```

// IDL
pseudo interface ORB {
    typedef sequence<Request> RequestSeq;
    string object_to_string(in Object obj);
    Object string_to_object(in string str);
    void create_list(in long count, out NVList new_list);
    void create_operation_list(
        in OperationDef oper,
        out NVList
        new_list
    );
    void create_named_value(out NamedValue nmval);
    void create_exception_list(out ExceptionList exclist);
    void create_context_list(out ContextList ctxtlist);
    void [get_default_context](#corbaorb-class)(out Context ctx);
    void create_environment(out Environment new_env);
    void send_multiple_requests_oneway(in RequestSeq req);
    void send_multiple_requests_deferred(in RequestSeq req);
    boolean poll_next_response();
    void get_next_response(out Request req);
    Boolean work_pending();
    void perform_work();
    void shutdown(in Boolean wait_for_completion);
    void run();
    void destroy();
    Boolean get_service_information (
        in ServiceType service_type,
        out ServiceInformation service_information
    );
    typedef string ObjectId;
    typedef sequence<ObjectId> ObjectIdList;
    Object resolve_initial_references(
        in ObjectId id
    ) raises(InvalidName);
    ObjectIdList list_initial_services();
    Policy create_policy(in PolicyType type, in any val)
    raises(PolicyError);
};

// C++
class ORB {
public:
    class [RequestSeq](#corbaorb-class) {...};
    char *[object_to_string](#corbaorb-class)(Object_var);
    Object_var [string_to_object](#corbaorb-class)(const char *);
    void [create_list](#corbaorb-class)(Long, NVList_out);
    void [create_operation_list](#corbaorb-class)(OperationDef_ptr,

```

```

NVList_out);
    void [create_named_value](#corbaorb-class)(NamedValue_out);
    void [create_exception_list](#corbaorb-class)(ExceptionList_out);
    void [create_context_list](#corbaorb-class)(ContextList_out);
    void [get_default_context](#corbaorb-class)(Context_out);
    void [create_environment](#corbaorb-class)(Environment_out);
    void [send_multiple_requests_oneway](#corbaorb-class)(const RequestSeq
&);
    void [send_multiple_requests_deferred](#corbaorb-class)(const RequestSeq
&);
    Boolean [poll_next_response](#corbaorb-class)();
    void [get_next_response](#corbaorb-class)(Request_out);
    Boolean [work_pending](#corbaorb-class)();
    void [perform_work](#corbaorb-class)();
    void [shutdown](#it_configconfiguration-interface)(Boolean
wait_for_completion);
    void [run](#corbaorb-class)();
    Boolean [get_service_information](#corbaorb-class)(
        ServiceType svc_type,
        ServiceInformation_out svc_info
    );
    void [destroy](#cosnamingbindingiterator-interface)();
    typedef char* [ObjectId](#portableinterceptororbinitinfo-interface);
    class [ObjectIdList](#corbaorb-class) { ... };
    Object_ptr [resolve_initial_references](#portableinterceptororbinitinfo-
interface)(const char* id);
    ObjectIdList* [list_initial_services](#corbaorb-class)();
    Policy_ptr [create_policy](#portableinterceptorpolicyfactory-interface)
(PolicyType type, const Any& val);
    static ORB_ptr [_duplicate](#corbapolicycurrent-class)(ORB_ptr orb);
    static ORB_ptr [_nil](#corbapolicycurrent-class)();
    virtual TypeCode_ptr
[create_struct_tc](#corbaorb-class)(
    const char* id,
    const char* name,
    const StructMemberSeq & members
) = 0;
    virtual TypeCode_ptr
[create_union_tc](#corbaorb-class)(
    const char* id,
    const char* name,
    TypeCode_ptr discriminator_type,
    const UnionMemberSeq & members
) = 0;
    virtual TypeCode_ptr
[create_enum_tc](#corbaorb-class)(
    const char* id,

```

```

        const char* name,
        const EnumMemberSeq & members
    ) = 0;
virtual TypeCode_ptr
[create_alias_tc](#corbaorb-class)(
    const char* id,
    const char* name,
    TypeCode_ptr original_type
) = 0;
virtual TypeCode_ptr
[create_exception_tc](#corbaorb-class)(
    const char* id,
    const char* name,
    const StructMemberSeq & members
) = 0;
virtual TypeCode_ptr
[create_interface_tc](#corbaorb-class)(
    const char* id,
    const char* name
) = 0;
virtual TypeCode_ptr
[create_string_tc](#corbaorb-class)(
    CORBA::ULong bound
) = 0;
virtual TypeCode_ptr
[create_wstring_tc](#corbaorb-class)(
    CORBA::ULong bound
) = 0;
virtual TypeCode_ptr
[create_fixed_tc](#corbaorb-class)(
    CORBA::UShort digits,
    CORBA::Short scale
) = 0;
virtual TypeCode_ptr
[create_sequence_tc](#corbaorb-class)(
    CORBA::ULong bound,
    TypeCode_ptr element_type
) = 0;
virtual TypeCode_ptr
[create_recursive_tc](#corbaorb-class)(
    const char* id
) = 0;
virtual TypeCode_ptr
[create_array_tc](#corbaorb-class)(
    CORBA::ULong length,
    TypeCode_ptr element_type
) = 0;

```

```

virtual TypeCode_ptr
[create_value_tc](#corbaorb-class)(
    const char* id,
    const char* name,
    ValueModifier type_modifier,
    TypeCode_ptr concrete_base,
    const ValueMemberSeq & members
) = 0;
virtual TypeCode_ptr
[create_value_box_tc](#corbaorb-class)(
    const char* id,
    const char* name,
    TypeCode_ptr original_type
) = 0;
virtual TypeCode_ptr
[create_native_tc](#corbaorb-class)(
    const char* id,
    const char* name
) = 0;
virtual TypeCode_ptr
[create_abstract_interface_tc](#corbaorb-class)(
    const char* id,
    const char* name
) = 0;
virtual ValueFactory
[register_value_factory](#corbaorb-class)(
    const char* id,
    ValueFactory factory
) = 0;
virtual void
[unregister_value_factory](#corbaorb-class)(
    const char* id
) = 0;
virtual ValueFactory
[lookup_value_factory](#corbaorb-class)(
    const char* id
) = 0;
};

```

ORB::create_abstract_interface_tc()

virtual TypeCode_ptr create_abstract_interface_tc(

```

    const char* id,
    const char* name
) = 0;

```

Returns a pointer to a new TypeCode of kind `tk_abstract_interface` representing an IDL abstract interface.

Parameters

<code>id</code>	The repository ID that globally identifies the TypeCode object.
<code>name</code>	The simple name identifying the TypeCode object within its enclosing scope.

See Also CORBA::TypeCode

```
CORBA**::**TCKind
```

ORB::create_alias_tc()

virtual TypeCode_ptr create_alias_tc(

```

    const char* id,
    const char* name,
    TypeCode_ptr original_type
) = 0;

```

Returns a pointer to a new TypeCode of kind `tk_alias` representing an IDL alias.

Parameters

<code>id</code>	The repository ID that globally identifies the TypeCode object.
<code>name</code>	The simple name identifying the TypeCode object within its enclosing scope.
<code>original_type</code>	A pointer to the actual TypeCode object this alias represents.

See Also CORBA::TypeCode

```
CORBA**::**TCKind
```

```
ORB::create_array_tc()
```

```
virtual TypeCode_ptr create_array_tc(
```

```
    CORBA::ULong length,
    TypeCode_ptr element_type
) = 0;
```

Returns a pointer to a new TypeCode of kind `tk_array` representing an IDL array.

Parameters

<code>length</code>	The length of the array.
<code>element_type</code>	The data type for the elements of the array.

See Also CORBA::TypeCode

```
CORBA**::**TCKind
```

```
ORB::create_context_list()
```

```
void create_context_list(ContextList_out list);
```

Creates an empty ContextList object for use with a DII request. You can add context strings to the list using ContextList::add() and then pass the list as a parameter to Object::_create_request().

Parameters

```
list
```

A reference to the new ContextList.

See Also CORBA::ContextList


```
CORBA::Object::_create_request()
```

```
ORB::create_enum_tc()
```

```
virtual TypeCode_ptr create_enum_tc(
```

```
    const char* id,
    const char* name,
    const EnumMemberSeq & members
) = 0;
```

Returns a pointer to a new TypeCode of kind `tk_enum` representing an IDL enumeration.

Parameters

<code>id</code>	The repository ID that globally identifies the TypeCode object.
<code>name</code>	The simple name identifying the TypeCode object within its enclosing scope.
<code>members</code>	The sequence of enumeration members.

See Also CORBA::TypeCode

```
CORBA::TCKind
```

```
ORB::create_environment()
```

```
void create_environment(
```

```
    Environment_out environment
);
```

Gets a newly created Environment object.

Parameters

```
new_env
```

New environment created.

See Also CORBA::Environment

ORB::create_exception_list()

void create_exception_list(

```
    ExceptionList_out list
);
```

Creates an empty ExceptionList object for use with a DII request. You can add user-defined exceptions to the list using ExceptionList::add() and then pass the list as a parameter to Object::_create_request().

Parameters

```
list
```

A reference to the new ExceptionList.

See Also CORBA::ExceptionList

```
CORBA::Object::_create_request()
```

ORB::create_exception_tc()

virtual TypeCode_ptr create_exception_tc(

```
    const char* id,
    const char* name,
    const StructMemberSeq & members
) = 0;
```

Returns a pointer to a new TypeCode of kind `tk_except` representing an IDL exception.

Parameters

<code>id</code>	The repository ID that globally identifies the TypeCode object.
<code>name</code>	The simple name identifying the TypeCode object within its enclosing scope.
<code>members</code>	The sequence of members.

See Also CORBA::TypeCode

```
CORBA**::**TCKind
```

ORB::create_fixed_tc()

virtual TypeCode_ptr create_fixed_tc(

```
    CORBA::UShort digits,
    CORBA::Short scale
) = 0;
```

Returns a pointer to a new TypeCode of kind `tk_fixed` representing an IDL fixed point type.

Parameters

<code>digits</code>	The number of digits for the fixed point type.
<code>scale</code>	The scale of the fixed point type.

See Also CORBA::TypeCode

```
CORBA**::**TCKind
```

ORB::create_interface_tc()

virtual TypeCode_ptr create_interface_tc(

```

    const char* id,
    const char* name
) = 0;

```

Returns a pointer to a new TypeCode representing an IDL interface.

Parameters

<code>id</code>	The repository ID that globally identifies the TypeCode object.
<code>name</code>	The simple name identifying the TypeCode object within its enclosing scope.

See Also CORBA::TypeCode

```
CORBA**::**TCKind
```

ORB::create_list()

void create_list(

```

    Long count,
    NVList_out list
);

```

Allocates space for an empty NVList of the size specified by `count` to contain NamedValue objects. A list of NamedValue object can be used to describe arguments to a request when using the Dynamic Invocation Interface. You can add NamedValue items to list using the NVList::add_item() routine.

Parameters

<code>count</code>	Number of elements anticipated for the new NVList. This is a hint to help with storage allocation.
<code>list</code>	A pointer to the start of the list. The caller must release the reference when it is no longer needed, or assign it to an NVList_var variable for automatic management.

See Also CORBA::NVList

```

CORBA**::**NamedValue
CORBA**::**ORB**::**create_operation_list()
CORBA**::**Request()

```

ORB::create_named_value()

void create_named_value(

```

    NamedValue_out value
);

```

Creates NamedValue objects you can use as return value parameters in the Object::_create_request() method.

Parameters

value

A pointer to the NamedValue object created. You must release the reference when it is no longer needed, or assign it to a NamedValue_var variable for automatic management.

See Also CORBA::NVList

```

CORBA**::**NamedValue
CORBA**::**Any
CORBA**::**ORB**::**create_list()

```

ORB::create_native_tc()

virtual TypeCode_ptr create_native_tc(

```

    const char* id,
    const char* name
) = 0;

```

Returns a pointer to a new TypeCode of kind tk_native representing an IDL native type.

Parameters

<code>id</code>	The repository ID that globally identifies the TypeCode object.
<code>name</code>	The simple name identifying the TypeCode object within its enclosing scope.

See Also CORBA::TypeCode

```
CORBA**::**TCKind
```

ORB::create_operation_list()

void create_operation_list(

```
    OperationDef_ptr operation,
    NVList_out list
);
```

Creates an NVList and returns it in the `list` parameter, initialized with the argument descriptions for the operation specified in `operation`.

Parameters

<code>operation</code>	A pointer to the interface repository object describing the operation.
<code>list</code>	A pointer to the start of the list. The caller must release the reference when it is no longer needed, or assign it to a NVList <code>_var</code> variable for automatic management. The returned NVList is of the correct length with one element per argument, and each NamedValue element of the list has a valid name and valid flags (denoting the argument passing mode).

Each element in the list is of type NamedValue whose `value` member (of type CORBA::Any) has a valid type that denotes the type of the argument. The value of the argument is not filled in.

Use of this method requires that the relevant IDL file be compiled with the `-R` option.

See Also CORBA::NVList

```

CORBA**::**NamedValue
CORBA**::**Any
CORBA**::**ORB**::**create_list()

```

ORB::create_policy()

Policy_ptr create_policy(

```

    PolicyType type,
    const Any& value
);

```

Returns a reference to a newly created Policy object.

Parameters

type	The PolicyType of the Policy object to be created.
value	The value for the initial state of the Policy object created.

Exceptions

PolicyError

The requested policy type or initial state for the policy is not supported. The appropriate reason as described in the PolicyErrorCode.

See Also CORBA::Policy

```

CORBA::PolicyType
CORBA::PolicyErrorCode

```

ORB::create_recursive_tc()

virtual TypeCode_ptr create_recursive_tc(

```
    const char* id
) = 0;
```

Returns a pointer to a recursive `TypeCode`, which serves as a place holder for a concrete `TypeCode` during the process of creating type codes that contain recursion. After the recursive `TypeCode` has been properly embedded in the enclosing `TypeCode`, which corresponds to the specified repository `id`, it will act as a normal `TypeCode`.

Parameters

`id`

The repository ID of the enclosing type for which the recursive `TypeCode` is serving as a place holder.

Invoking operations on the recursive `TypeCode` before it has been embedded in the enclosing `TypeCode` will result in undefined behavior.

Examples The following IDL type declarations contains `TypeCode` recursion:

```
// IDL
struct foo {
    long value;
    sequence<foo> chain;
};
valuetype V {
    public V member;
};
```

To create a `TypeCode` for valuetype `V`, you invoke the `TypeCode` creation functions as follows:


```
// C++
TypeCode_var recursive_tc = orb->create_recursive_tc("IDL:V:1.0");
ValueMemberSeq v_seq;
v_seq.length(1);
v_seq[0].name = string_dup("member");
v_seq[0].type = recursive_tc;
v_seq[0].access = PUBLIC_MEMBER;
TypeCode_var v_val_tc = orb->create_value_tc(
    "IDL:V:1.0",
    "V",
    VM_NONE,
    TypeCode::_nil(),
    v_seq
);
```

See Also CORBA::TypeCode

ORB::create_sequence_tc()

virtual TypeCode_ptr create_sequence_tc(

```
    CORBA::ULong bound,
    TypeCode_ptr element_type
) = 0;
```

Returns a pointer to a new TypeCode of kind `tk_sequence` representing an IDL sequence.

Parameters

<code>bound</code>	The upper bound of the sequence.
<code>element_type</code>	The data type for the elements of the sequence.

See Also CORBA::TypeCode

```
CORBA**::**TCKind
```

ORB::create_string_tc()

virtual TypeCode_ptr create_string_tc(

```
CORBA::ULong bound
) = 0;
```

Returns a pointer to a new TypeCode of kind `tk_string` representing an IDL string.

Parameters

`bound`

The upper bound of the string.

See Also `CORBA::TypeCode`

```
CORBA**::**TCKind
```

`ORB::create_struct_tc()`

virtual `TypeCode_ptr` `create_struct_tc(`

```
const char* id,
const char* name,
const StructMemberSeq & members
) = 0;
```

Returns a pointer to a new TypeCode of kind `tk_struct` representing an IDL structure.

Parameters

<code>id</code>	The repository ID that globally identifies the TypeCode object.
<code>name</code>	The simple name identifying the TypeCode object within its enclosing scope.
<code>members</code>	The sequence of structure members.

See Also `CORBA::TypeCode`

```
CORBA**::**TCKind
```

```
ORB::create_union_tc()
```

```
virtual TypeCode_ptr create_union_tc(
```

```
    const char* id,
    const char* name,
    TypeCode_ptr discriminator_type,
    const UnionMemberSeq & members
) = 0;
```

Returns a pointer to a TypeCode of kind `tk_union` representing an IDL union.

Parameters

<code>id</code>	The repository ID that globally identifies the TypeCode object.
<code>name</code>	The simple name identifying the TypeCode object within its enclosing scope.
<code>discriminator_type</code>	The union discriminator type.
<code>members</code>	The sequence of union members.

See Also `CORBA::TypeCode`

```
CORBA**::**TCKind
```

```
ORB::create_value_box_tc()
```

```
virtual TypeCode_ptr create_value_box_tc(
```

```
    const char* id,
    const char* name,
    TypeCode_ptr original_type
) = 0;
```

Returns a pointer to a new TypeCode of kind `tk_value_box` representing an IDL boxed value.

Parameters

<code>id</code>	The repository ID that globally identifies the TypeCode object.
<code>name</code>	The simple name identifying the TypeCode object within its enclosing scope.
<code>original_type</code>	A pointer to the original TypeCode object this boxed value represents.

See Also

CORBA::TypeCode

CORBA::**::**TCKind

ORB::create_value_tc()

virtual TypeCode_ptr create_value_tc(

```

    const char* id,
    const char* name,
    ValueModifier type_modifier,
    TypeCode_ptr concrete_base,
    const ValueMemberSeq & members
) = 0;

```

Returns a pointer to a TypeCode of kind `tk_value` representing an IDL value type.

Parameters

<code>id</code>	The repository ID that globally identifies the TypeCode object.
<code>name</code>	The simple name identifying the TypeCode object within its enclosing scope.
<code>type_modifier</code>	A value type modifier.
<code>concrete_base</code>	A TypeCode for the immediate concrete value type base of the value type for which the TypeCode is being created. If the value type does not have a concrete base, use a nil TypeCode reference.

members	The sequence of value type members.

See Also CORBA::TypeCode

```
CORBA**::**TCKind
```

ORB::create_wstring_tc()

virtual TypeCode_ptr create_wstring_tc(

```
    CORBA::ULong bound
) = 0;
```

Returns a pointer to a new TypeCode of kind `tk_wstring` representing an IDL wide string.

Parameters

```
bound
```

The upper bound of the string.

See Also CORBA::TypeCode

```
CORBA::TCKind
```

ORB::destroy()

void destroy();

This thread operation destroys the ORB so that its resources can be reclaimed by the application.

If `destroy()` is called on an ORB that has not been shut down (see `shutdown()`) it will start the shut down process and block until the ORB has shut down before it destroys the ORB. For maximum portability and to avoid resource leaks, applications should always call `shutdown()` and `destroy()` on all ORB instances before exiting.

After an ORB is destroyed, another call to `ORB_init()` with the same ORB ID will return a reference to a newly constructed ORB.

Exceptions

<code>BAD_INV_ORDER</code> , minor code <code>3</code>	An application calls <code>destroy()</code> in a thread that is currently servicing an invocation because blocking would result in a deadlock.
<code>OBJECT_NOT_EXIST</code>	An operation is invoked on a destroyed ORB reference.

The exception is raised if

See Also `CORBA::ORB::run()`

```
CORBA::ORB::shutdown()
CORBA::ORB_init()
```

`ORB::_duplicate()`

static `ORB_ptr _duplicate()`

```
ORB_ptr obj
);
```

Returns a new reference to `obj` and increments the reference count of the object. Because object references are opaque and ORB-dependent, it is not possible for your application to allocate storage for them. Therefore, if more than one copy of an object reference is needed, use this method to create a duplicate.

Parameters

`obj`

Pointer to the object to duplicate.

See Also `CORBA::release()`

`ORB::get_default_context()`

void `get_default_context(Context_out context);`

Obtains a `CORBA::Context` object representing the default context of the process.

Parameters

```
context
```

The default context of the process.

See Also CORBA::Context

```
CORBA**::**NVList
```

```
ORB::get_next_response()
```

```
void get_next_response(
```

```
    Request_out request  
);
```

Gets the next response for a request that has been sent.

Parameters

```
request
```

A pointer to the Request whose completion is being reported.

You can call `get_next_response()` successively to determine the outcomes of the individual requests from `send_multiple_requests_deferred()` calls. The order in which responses are returned is not necessarily related to the order in which the requests are completed.

Exceptions

```
WrongTransaction
```

The thread invoking this method has a non-null transaction context that differs from that of the request *and* the request has an associated transaction context.

See Also CORBA::ORB::send_multiple_requests_deferred()

```

CORBA**::**Request**::**get_response()
CORBA**::**Request**::**send_deferred()
CORBA**::**ORB**::**poll_next_response()

```

ORB::get_service_information()

Boolean get_service_information(

```

    ServiceType svc_type,
    ServiceInformation_out svc_info
};

```

Gets the service information about CORBA facilities and services that this ORB supports. Returns 1 (true) if service information is available for the `svc_type` and returns 0 (false) otherwise.

Parameters

<code>svc_type</code>	The service type for which information is being requested.
<code>svc_info</code>	The service information available for <code>svc_type</code> , if that information is available.

See Also CORBA::ServiceInformation

ORB::list_initial_services()

ObjectIdList* list_initial_services();

Returns a sequence of ObjectId strings, each of which names a service provided by Orbix. This method allows your application to determine which objects have references available. Before you can use some services such as the naming service in your application you have to first obtain an object reference to the service.

The ObjectIdList may include the following names:


```

DynAnyFactory
IT_Configuration
InterfaceRepository
NameService
ORBPolicyManager
POACurrent
PSS
RootPOA
SecurityCurrent
TradingService
TransactionCurrent

```

See Also CORBA::ORB::resolve_initial_references()

ORB::lookup_value_factory()

virtual ValueFactory lookup_value_factory(

```

    const char* id
) = 0;

```

Returns a pointer to the factory method.

Parameters

id

A repository ID that identifies a value type factory method.

Your application assumes ownership of the returned reference to the factory. When you are done with the factory, invoke ValueFactoryBase::_remove_ref() once on that factory.

See Also CORBA::ValueFactory

```

CORBA::ORB::register_value_factory( )
CORBA::ORB::unregister_value_factory( )

```

Object::_nil()

static ORB_ptr _nil();

Returns a nil object reference.

See Also CORBA::is_nil()

ORB::ObjectId

typedef char* ObjectId;

The name that identifies an object for a service. `ObjectId` strings uniquely identify each service used by an ORB.

See Also CORBA::ORB::ObjectIdList

```
CORBA::ORB::list_initial_services()
```

ORB::ObjectIdList Sequence Class

```
class ObjectIdList {
```

```

public:
    // default constructor
    ObjectIdList();
    // initial maximum length constructor
    ObjectIdList(ULong max);
    // data constructor
    ObjectIdList(
        ULong max,
        ULong length,
        ObjectId *data,
        Boolean release = FALSE
    );
    // copy constructor
    ObjectIdList(const ObjectIdList&);
    // destructor
    ~ObjectIdList();
    // assignment operator
    ObjectIdList &operator=(const ObjectIdList&);
    ULong maximum() const;
    void length(ULong);
    ULong length() const;
    // subscript operators
    ObjectId &operator[](ULong index);
    const ObjectId &operator[](ULong index) const;
    Boolean release() const;
    void replace(
        ULong max,
        ULong length,
        ObjectId *data,
        Boolean release = FALSE
    );
    // buffer reference
    ObjectId* get_buffer(Boolean orphan = FALSE);
    // buffer access
    const ObjectId* get_buffer() const;
};

```

A sequence of ObjectId objects.

See Also CORBA::ORB::ObjectId

```
CORBA::ORB::list_initial_services()
```

ORB::object_to_string()

```
char *object_to_string(
```

```
    Object_var obj
);
```

Returns a string representation of an object reference. An object reference can be translated into a string by this method and the resulting value stored or communicated in whatever ways strings are manipulated.

Parameters

```
obj
```

Object reference to be translated to a string.

Use `string_to_object()` to translate the string back to the corresponding object reference.

A string representation of an object reference has the prefix `IOR:` followed by a series of hexadecimal octets. The hexadecimal strings are generated by first turning an object reference into an *interoperable object reference* (IOR), and then encapsulating the IOR using the encoding rules of *common data representation* (CDR). The content of the encapsulated IOR is then turned into hexadecimal digit pairs, starting with the first octet in the encapsulation and going until the end. The high four bits of each octet are encoded as a hexadecimal digit, then the low four bits are encoded.

Note

Because an object reference is opaque and may differ from ORB to ORB, the object reference itself is not a convenient value for storing references to objects in persistent storage or communicating references by means other than invocation.

See Also `CORBA::ORB::string_to_object()`

`ORB::perform_work()`

`void perform_work();`

A thread function that provides execution resources to your application if called by the main thread. This function does nothing if called by any other thread.

You can use `perform_work()` and `work_pending()` for a simple polling loop that multiplexes the main thread among the ORB and other activities. Such a loop would most likely be used in a single-threaded server. A multi-threaded server would need a polling loop only if there were both ORB and other code that required use of the main thread. Here is a simple example of such a polling loop:

```
// C++
for (;;) {
    if (orb->work_pending()) {
        orb->perform_work();
    };
    // do other things
    // sleep
};
```

Exceptions

`BAD_INV_ORDER`, minor code 4

The method is called after the ORB has shut down. You can catch this exception to determine when to terminate a polling loop.

See Also `CORBA::ORB::run()`

`CORBA::ORB::work_pending()`

`ORB::poll_next_response()`

Boolean `poll_next_response()`;

Returns 1 (true) if any request has completed or returns 0 (false) if none have completed. This method returns immediately, whether any request has completed or not.

You can call this method successively to determine whether the individual requests specified in a `send_multiple_requests_oneway()` or `send_multiple_requests_deferred()` call have completed successfully.

Alternatively you can call `Request::poll_response()` on the individual Request objects in the sequence of requests passed to `send_multiple_requests_oneway()` or `send_multiple_requests_deferred()`.

See Also `CORBA::ORB::get_next_response()`

```

CORBA::ORB::send_multiple_requests_oneway()
CORBA::ORB::send_multiple_requests_deferred()
CORBA::Request::poll_response()

```

ORB::register_value_factory()

virtual ValueFactory register_value_factory(

```

    const char* id,
    ValueFactory factory
) = 0;

```

Registers a value type factory method with the ORB for a particular value type. The method returns a null pointer if no previous factory was registered for the type. If a factory is already registered for the value type, the method replaces the factory and returns a pointer to the previous factory for which the caller assumes ownership.

Parameters

<code>id</code>	A repository ID that identifies the factory.
<code>factory</code>	The application-specific factory method that the ORB calls whenever it needs to create the value type during the unmarshaling of value instances.

When a value type factory is registered with the ORB, the ORB invokes `ValueFactoryBase::_add_ref()` once on the factory before returning from `register_value_factory()`. When the ORB is done using that factory, the reference count is decremented once with `ValueFactoryBase::_remove_ref()`. This can occur in any of the following circumstances:

- If the factory is explicitly unregistered via `unregister_value_factory()`, the ORB invokes `ValueFactoryBase::_remove_ref()` once on the factory.
- If the factory is implicitly unregistered due to a call to `shutdown()`, the ORB invokes `ValueFactoryBase::_remove_ref()` once on each registered factory.
- If you replace a factory by calling this `register_value_factory()` again, you should invoke `ValueFactoryBase::_remove_ref()` once on the previous factory.

See Also CORBA::ValueFactory

```

CORBA::ORB::lookup_value_factory()
CORBA::ORB::unregister_value_factory()

```

ORB::RequestSeq Sequence

```
class RequestSeq {
```

```

public:
    // default constructor
    RequestSeq();
    // initial maximum length constructor
    RequestSeq(ULong max);
    // data constructor
    RequestSeq(
        ULong max,
        ULong length,
        Request *data,
        Boolean release = FALSE
    );
    // copy constructor
    RequestSeq(const RequestSeq&);
    // destructor
    ~RequestSeq();
    // assignment operator
    RequestSeq &operator=(const RequestSeq&);
    ULong maximum() const;
    void length(ULong);
    ULong length() const;
    // subscript operators
    Request &operator[](ULong index);
    const Request &operator[](ULong index) const;
    Boolean release() const;
    void replace(
        ULong max,
        ULong length,
        Request *data,
        Boolean release = FALSE
    );
    // buffer reference
    Request* get_buffer(Boolean orphan = FALSE);
    // buffer access
    const Request* get_buffer() const;
};

```

A sequence of Request objects.

See AlsoCORBA::Request

```
CORBA::ORB::send_multiple_requests_oneway()
CORBA::ORB::send_multiple_requests_deferred()
```

```
ORB::resolve_initial_references()
```

```
Object_ptr resolve_initial_references(
```

```
    const char* id
);
```

Returns an object reference for a desired service.

Parameters

```
id
```

The name of the desired service. Use `list_initial_services()` to obtain the list of services supported.

Applications require a portable means by which to obtain some initial object references such as the root POA, the interface repository, and various object services instances. The functionality of `resolve_initial_references()` and `list_initial_services()` is like a simplified, local version of the naming service that has only a small set of objects in a flattened single-level name space.

The object reference returned must be narrowed to the correct object type. For example, the object reference returned from resolving the `id` name `InterfaceRepository` must be narrowed to the type `CORBA::Repository`.

See AlsoCORBA::ORB::list_initial_services()

```
ORB::run()
```

```
void run();
```

A thread method that enables the ORB to perform work using the main thread. If called by any thread other than the main thread, this method simply waits until the ORB has shut down.

This method provides execution resources to the ORB so that it can perform its internal functions. Single threaded ORB implementations, and some multi-threaded ORB implementations need to use the main thread. For maximum portability, your applications should call either `run()` or `perform_work()` on the main thread.

`run()` returns after the ORB has completed the shutdown process, initiated when some thread calls `shutdown()`.

See AlsoCORBA::ORB::perform_work()


```

CORBA::ORB::work_pending()
CORBA::ORB::shutdown()
CORBA::ORB::destroy()

```

```

ORB::send_multiple_requests_deferred()
void send_multiple_requests_deferred(

```

```

    const RequestSeq &req
);

```

Initiates a number of requests in parallel.

Parameters

```
req
```

A sequence of requests.

The method does not wait for the requests to finish before returning to the caller. The caller can use `get_next_response()` or `Request::get_response()` to determine the outcome of the requests. Memory leakage will result if one of these methods is not called for a request issued with `send_multiple_requests_oneway()` or `Request::send_deferred()`.

See Also `CORBA::ORB::send_multiple_requests_oneway()`

```

CORBA::Request::get_response()
CORBA::Request::send_deferred()
CORBA::ORB::get_next_response()

```

```

ORB::send_multiple_requests_oneway()
void send_multiple_requests_oneway(

```

```

    const RequestSeq &req
);

```

Initiates a number of requests in parallel. It does not wait for the requests to finish before returning to the caller.

Parameters

```
req
```

A sequence of requests. The operations in this sequence do not have to be IDL oneway operations. The caller does not expect a response, nor does it expect out or inout parameters to be updated.

See Also CORBA::Request::send_oneway()

```
CORBA::ORB::send_multiple_requests_deferred()
```

```
ORB::shutdown()
```

```
void shutdown(
```

```
    Boolean wait_for_completion
);
```

This thread method instructs the ORB to shut down in preparation for ORB destruction.

Parameters

```
wait_for_completion
```

Designates whether or not to wait for completion before continuing.

If the value is 1 (true), this method blocks until all ORB processing has completed, including request processing and object deactivation or other methods associated with object adapters.

If the value is 0 (false), then shut down may not have completed upon return of the method.

While the ORB is in the process of shutting down, the ORB operates as normal, servicing incoming and outgoing requests until all requests have been completed. Shutting down the ORB causes all object adapters to be shut down because they cannot exist without an ORB.

Once an ORB has shutdown, you can invoke only object reference management methods including CORBA::_duplicate(), release(), and is_nil() on the ORB or any object reference obtained from the ORB. An application may also invoke ORB::destroy() on the ORB itself. Invoking any other method raises exception `BAD_INV_ORDER` system with the OMG minor code 4.

Exceptions

```
BAD_INV_ORDER, minor code 3
```

An application calls this method in a thread that is currently servicing an invocation because blocking would result in a deadlock.

See Also CORBA::ORB::run()

```
CORBA::ORB::destroy()
```

```
ORB::string_to_object()
```

```
Object_var string_to_object(
```

```
    const char *obj_ref_string
);
```

Returns an object reference by converting a string representation of an object reference.

Parameters

```
obj_ref_string
```

String representation of an object reference to be converted.

To guarantee that an ORB will understand the string form of an object reference, the string must have been produced by a call to `object_to_string()`.

See Also CORBA::ORB::object_to_string()

```
ORB::unregister_value_factory()
```

```
virtual void unregister_value_factory(
```

```
    const char* id
) = 0;
```

Unregisters a value type factory method from the ORB.

Parameters

```
id
```

A repository ID that identifies a value type factory method.

See AlsoCORBA::ValueFactory

```
CORBA::ORB::lookup_value_factory()  
CORBA::ORB::register_value_factory()
```

ORB::work_pending()

Boolean work_pending();

This thread method returns an indication of whether the ORB needs the main thread to perform some work. A return value of 1 (true) indicates that the ORB needs the main thread to perform some work and a return value of 0 (false) indicates that the ORB does not need the main thread.

Exceptions

BAD_INV_ORDER , minor code 4

The method is called after the ORB has shutdown.

See AlsoCORBA::ORB::run()

```
CORBA::ORB::perform_work()
```

CORBA::Policy Interface

An ORB or CORBA service may choose to allow access to certain choices that affect its operation. This information is accessed in a structured manner using interfaces derived from the `Policy` interface defined in the CORBA module. A CORBA service is not required to use this method of accessing operating options, but may choose to do so.

This chapter is divided into the following sections:

- [Quality of Service Framework](#)
- [Policy Methods](#)

The following policies are available. These are classes that inherit from the `CORBA::Policy` class:

Table 7: Policies

Category	Policy
CORBA and IT_CORBA	<code>CORBA::ConstructionPolicy</code> <code>IT_CORBA::WellKnownAddressingPolicy</code>
PortableServer and IT_PortableServer	<code>PortableServer::ThreadPolicy</code> <code>PortableServer::LifespanPolicy</code> <code>PortableServer::IdUniquenessPolicy</code> <code>PortableServer::IdAssignmentPolicy</code> <code>PortableServer::ImplicitActivationPolicy</code> <code>PortableServer::ServantRetentionPolicy</code> <code>PortableServer::RequestProcessingPolicy</code> <code>IT_PortableServer::ObjectDeactivationPolicy</code> <code>IT_PortableServer::PersistenceModePolicy</code>
Messaging	<code>RebindPolicy</code> <code>SyncScopePolicy</code> <code>RoutingPolicy</code>

You create instances of a policy by calling `CORBA::ORB::create_policy()`.

Quality of Service Framework

A `Policy` is the key component for a standard *Quality of Service framework* (QoS). In this framework, all qualities are defined as interfaces derived from `CORBA::Policy`. This framework is how all service-specific qualities are defined. The components of the framework include:

<code>Policy</code>	This base interface from which all QoS objects derive.
<code>PolicyList</code>	A sequence of <code>Policy</code> objects.
<code>PolicyManager</code>	An interface with operations for querying and overriding QoS policy settings.
Policy Transport Mechanisms	Mechanisms for transporting policy values as part of interoperable object references and within requests. These include: - TAG_POLICIES - A Profile Component containing the sequence of QoS policies exported with the object reference by an object adapter. - INVOCATION_POLICIES - A Service Context containing a sequence of QoS policies in effect for the invocation.

Most policies are appropriate only for management at either the server or client, but not both. Server-side policies are associated with a POA. Client-side policies are divided into ORB-level, thread-level, and object-level policies. At the thread and ORB levels, use the `PolicyManager` interface to query the current set of policies and override these settings.

POA Policies for Servers

Server-side policy management is handled by associating QoS `Policy` objects with a POA. Since all QoS are derived from interface `Policy`, those that are applicable to server-side behavior can be passed as arguments to `POA::create_POA()`. Any such policies that affect the behavior of requests (and therefore must be accessible by the ORB at the client side) are exported within the object references that the POA creates. It is clearly noted in a POA policy definition when that policy is of interest to the client. For those policies that can be exported within an object reference, the absence of a value for that policy type implies that the target supports any legal value of that `PolicyType`.

ORB-level Policies for Clients

You obtained the ORB's locality-constrained `PolicyManager` through an invocation of `CORBA::ORB::resolve_initial_references()`, specifying an identifier of `ORBPolicyManager`. This `PolicyManager` has operations through which a set of policies can be applied and the current overriding policy settings can be obtained. Policies applied at the ORB level override any system defaults.

Thread-level Policies for Clients

You obtained a thread's locality-constrained `PolicyCurrent` through an invocation of `CORBA::ORB::resolve_initial_references()`, specifying an identifier of `PolicyCurrent`. Policies applied at the thread-level override any system defaults or values set at the ORB level. When accessed from a newly spawned thread, the `PolicyCurrent` initially has no overridden policies. The `PolicyCurrent` also has no overridden values when a POA with `ThreadPolicy` of `ORB_CONTROL_MODEL` dispatches an invocation to a servant. Each time an invocation is dispatched through a `SINGLE_THREAD_MODEL` POA, the thread-level overrides are reset to have no overridden values.

Object-level Policies for Clients

Operations are defined on the base `Object` interface through which a set of policies can be applied. Policies applied at the object level override any system defaults or values set at the ORB or thread levels. In addition, accessors are defined for querying the current overriding policies set at the object level, and for obtaining the current effective client-side policy of a given `PolicyType`. The effective client-side policy is the value of a `PolicyType` that would be in effect if a request were made. This is determined by checking for overrides at the object level, then at the thread level, and finally at the ORB level. If no overriding policies are set at any level, the system-dependent default value is returned. Portable applications are expected to override the ORB-level policies since default values are not specified in most cases.

Policy Methods

The `Policy` interface is as follows:

```
// IDL in module CORBA
interface Policy {
    readonly attribute PolicyType [policy_type](#policy-methods);
    Policy [copy()](#policy-methods);
    void [destroy()](#cosnamingbindingiterator-interface);
};
```

Policy::policy_type Attribute

// IDL

```
readonly attribute PolicyType policy_type;
```

This read-only attribute returns the constant value of type PolicyType that corresponds to the type of the `Policy` object.

Policy::copy()

// IDL

```
Policy copy();
```

This operation copies the `Policy` object. The copy does not retain any relationships that the original policy had with any domain, or object.

Policy::destroy()

// IDL

```
void destroy();
```

This operation destroys the `Policy` object. It is the responsibility of the `Policy` object to determine whether it can be destroyed.

EnhancementOrbix guarantees to always destroy all local objects it creates when the last reference to them is released so you do not have to call `destroy()`. However, code that relies on this feature is not strictly CORBA compliant and may leak resources with other ORBs. (According to the CORBA specification, simply calling `CORBA::release()` on all references to a policy object does not delete the object or its components so each policy object created must be explicitly destroyed to avoid memory leaks.)

Exceptions

`NO_PERMISSION`

The policy object determines that it cannot be destroyed.

CORBA::PolicyCurrent Class

The `PolicyCurrent` interface allows access to policy settings at the current programming context level. Within a client, you obtain a `PolicyCurrent` object reference to set the quality of service for all invocations in the current thread. You obtain a reference to this interface by invoking `ORB::resolve_initial_references()` with the ObjectId `PolicyCurrent`.

The `PolicyCurrent` interface is derived from the `PolicyManager` and the `Current` interfaces. The `PolicyManager` interface allows you to change the policies for each invocation and the `Current` interface allows control from the current thread.

Policies applied at the thread level override any system defaults or values set at the ORB level. When accessed from a newly spawned thread, the `PolicyCurrent` initially has no overridden policies. The `PolicyCurrent` also has no overridden values when a POA with `ThreadPolicy` of `ORB_CONTROL_MODEL` dispatches an invocation to a servant. Each time an invocation is dispatched through a POA of the `SINGLE_THREAD_MODEL`, the thread-level overrides are reset to have no overridden values.

```
class IT_ART_API PolicyCurrent :
    public virtual PolicyManager,
    public virtual Current
{
public:
    typedef CORBA::PolicyCurrent_ptr _ptr_type;
    typedef CORBA::PolicyCurrent_var _var_type;
    virtual [~PolicyCurrent()](#corbapolicycurrent-class);
    static PolicyCurrent_ptr [_narrow](#corbapolicycurrent-class)(
        CORBA::Object_ptr obj
    );
    static PolicyCurrent_ptr [_unchecked_narrow](#corbapolicycurrent-class)(
        CORBA::Object_ptr obj
    );
    inline static PolicyCurrent_ptr [_duplicate](#corbapolicycurrent-class)(
        PolicyCurrent_ptr p
    );
    inline static PolicyCurrent_ptr [_nil()](#corbapolicycurrent-class);
    static const IT_FWString _it_fw_type_id;
};
```

`PolicyCurrent::_duplicate()`

`inline static PolicyCurrent_ptr _duplicate(`

```
PolicyCurrent_ptr p
);
```

Returns a duplicate object reference and increments the reference count of the object.

Parameters

```
p
```

The current object reference to duplicate.

See Also

PolicyCurrent::_narrow()

static PolicyCurrent_ptr _narrow(

```
CORBA::Object_ptr obj
);
```

Returns a new object reference to a `PolicyCurrent` object given an existing reference.

Parameters

```
obj
```

A reference to an object.

See Also CORBA::PolicyCurrent::_unchecked_narrow()

PolicyCurrent::_nil()

inline static PolicyCurrent_ptr _nil();

Returns a nil object reference to a `PolicyCurrent` object.

See Also

PolicyCurrent::~PolicyCurrent() Destructor

virtual ~PolicyCurrent();

The destructor for the object.

PolicyCurrent::_unchecked_narrow()

static PolicyCurrent_ptr _unchecked_narrow(

```
    CORBA::Object_ptr obj  
);
```

Returns a new object reference to a `PolicyCurrent` object given an existing reference.

Parameters

obj

A reference to an object.

See Also `CORBA::PolicyCurrent::_narrow()`

CORBA::PolicyManager Class

`PolicyManager` is an interface with operations for querying and overriding QoS policy settings. It includes mechanisms for obtaining policy override management operations at each relevant application scope. You obtain the ORB's `PolicyManager` by invoking `ORB::resolve_initial_references()` with the `ObjectId` `ORBPolicyManager`.

You use a `CORBA::PolicyCurrent` object, derived from `CORBA::Current`, for managing the thread's QoS policies. You obtain a reference to this interface by invoking `ORB::resolve_initial_references()` with the `ObjectId` `PolicyCurrent`.

- Accessor operations on `CORBA::Object` allow querying and overriding of QoS at the object reference scope.
- The application of QoS on a POA is done through the currently existing mechanism of passing a `PolicyList` to `POA::create_POA()`.

```

class IT_ART_API PolicyManager : public virtual CORBA::Object {
public:
    typedef CORBA::PolicyManager_ptr _ptr_type;
    typedef CORBA::PolicyManager_var _var_type;
    virtual [~PolicyManager()](#corbapolicymanager-class);
    static PolicyManager_ptr [_narrow](#corbapolicycurrent-class)(
        CORBA::Object_ptr obj
    );
    static PolicyManager_ptr [_unchecked_narrow](#corbapolicycurrent-
class)(
        CORBA::Object_ptr obj
    );
    inline static PolicyManager_ptr [_duplicate](#corbapolicycurrent-
class)(
        PolicyManager_ptr p
    );
    inline static PolicyManager_ptr [_nil()](#corbapolicycurrent-class);
    virtual PolicyList* [get_policy_overrides](#corbapolicymanager-class)(
        const PolicyTypeSeq & ts
    ) = 0;
    virtual void [set_policy_overrides](#corbapolicymanager-class)(
        const PolicyList & policies,
        SetOverrideType set_add
    ) = 0;
    static const IT_FWString _it_fw_type_id;
};

```

PolicyManager::_duplicate()

inline static PolicyManager_ptr _duplicate(

```

    PolicyManager_ptr p
);

```

Returns a duplicate object reference and increments the reference count of the object.

Parameters

p

The current object reference to duplicate.

See Also

PolicyManager::get_policy_overrides()

virtual PolicyList* get_policy_overrides(

```
    const PolicyTypeSeq & ts
) = 0;
```

Parameters Returns a list containing the overridden policies for the requested policy types. This returns only those policy overrides that have been set at the specific scope corresponding to the target `PolicyManager` (no evaluation is done with respect to overrides at other scopes). If none of the requested policy types are overridden at the target `PolicyManager`, an empty sequence is returned.

Parameters

ts

A sequence of policy types to get. If the specified sequence is empty, the method returns all policy overrides at this scope.

See Also `CORBA::PolicyManager::set_policy_overrides()`

`PolicyManager::_narrow()`

`static PolicyManager_ptr _narrow(`

```
    CORBA::Object_ptr obj
);
```

Returns a new object reference to a `PolicyManager` object given an existing reference.

Parameters

obj

A reference to an object.

See Also `CORBA::PolicyManager::_unchecked_narrow()`

`PolicyManager::_nil()`

`inline static PolicyManager_ptr _nil();`

Returns a nil object reference to a `PolicyManager` object.

See Also

`PolicyManager::~~PolicyManager()` Destructor

```
virtual ~PolicyManager();
```

The destructor for the object.

```
PolicyManager::set_policy_overrides()
```

```
virtual void set_policy_overrides(
```

```
    const PolicyList & policies,
    SetOverrideType set_add
) = 0;
```

Modifies the current set of overrides with the requested list of policy overrides.

Parameters

<code>policies</code>	A sequence of references to policy objects.
<code>set_add</code>	Indicates whether the policies in the <code>policies</code> parameter should be added to existing overrides in the <code>PolicyManager</code> or used to replace existing overrides: - Use <code>ADD_OVERRIDE</code> to add policies onto any other overrides that already exist in the <code>PolicyManager</code>. - Use <code>SET_OVERRIDE</code> to create a clean <code>PolicyManager</code> free of any other overrides.

Invoking the method with an empty sequence of policies and a mode of `SET_OVERRIDE` removes all overrides from a `PolicyManager`.

There is no evaluation of compatibility with policies set within other policy managers.

Exceptions

<code>NO_PERMISSION</code>	Only certain policies that pertain to the invocation of an operation at the client end can be overridden using this operation. This exception is raised if you attempt to override any other policy.
<code>InvalidPolicy</code>	The request would put the set of overriding policies for the target <code>PolicyManager</code> in an inconsistent state. No policies are changed or added.

```
PolicyManager::_unchecked_narrow()
```


static PolicyManager_ptr _unchecked_narrow(

```
    CORBA::Object_ptr obj  
);
```

Returns a new object reference to a `PolicyManager` object given an existing reference.

Parameters

obj

A reference to an object.

See Also `CORBA::PolicyManager::_narrow()`

CORBA::PrimitiveDef Interface

Interface `PrimitiveDef` represents an IDL primitive type such as `short`, `long`, and others. `PrimitiveDef` objects are anonymous (unnamed) and owned by the interface repository.

Objects of type `PrimitiveDef` cannot be created directly. You can obtain a reference to a `PrimitiveDef` by calling `Repository::get_primitive()`.

```
// IDL in module CORBA.
interface PrimitiveDef: IDLType {
    readonly attribute PrimitiveKind [kind](#corbaprimivedef-interface);
};
```

See Also `CORBA::PrimitiveKind`

```
CORBA::IDLType
CORBA::Repository::get_primitive()
```

`PrimitiveDef::kind` Attribute

// IDL

```
readonly attribute PrimitiveKind kind;
```

Identifies which of the IDL primitive types is represented by this `PrimitiveDef`.

A `PrimitiveDef` with a `kind` of type `pk_string` represents an unbounded string, a bounded string is represented by the interface `StringDef`. A `PrimitiveDef` with a `kind` of type `pk_objref` represents the IDL type `Object`. A `PrimitiveDef` with a `kind` of type `pk_value_base` represents the IDL type `ValueBase`.

See Also `CORBA::IDLType`

```
CORBA::Object
CORBA::StringDef
```

CORBA::Repository Interface

The interface repository itself is a container for IDL type definitions. Each interface repository is represented by a global root `Repository` object.

The `Repository` interface describes the top-level object for a repository name space. It contains definitions of constants, typedefs, exceptions, interfaces, value types, value boxes, native types, and modules.

You can use the `Repository` operations to look up any IDL definition, by either name or identity, that is defined in the global name space, in a module, or in an interface. You can also use other `Repository` operations to create information for the interface repository. See [Table 8](#):

Table 8: Operations of the Repository Interface

Read Operations	Write Operations
<code>describe_contents()</code>	<code>create_array()</code>
<code>get_canonical_typecode()</code>	<code>create_fixed()</code>
<code>get_primitive()</code>	<code>create_sequence()</code>
<code>lookup_id()</code>	<code>create_string()</code>
	<code>create_wstring()</code>

The five `create_type` operations create new interface repository objects defining anonymous types. Each anonymous type definition must be used in defining exactly one other object. Because the interfaces for these anonymous types are not derived from `Contained`, it is your responsibility to invoke in your application `destroy()` on the returned object if it is not successfully used in creating a definition that is derived from `Contained`.

The `Repository` interface is as follows:

```
// IDL in module CORBA.
interface Repository : Container {
    Contained [lookup_id](#corbarepository-interface)(
        in RepositoryId search_id
    );
    TypeCode [get_canonical_typecode](#corbarepository-interface)(
        in TypeCode tc
    );
    PrimitiveDef [get_primitive](#corbarepository-interface)(
        in PrimitiveKind kind
    );
    StringDef [create_string](#corbarepository-interface)(
        in unsigned long bound
    );
    WstringDef [create_wstring](#corbarepository-interface)(
        in unsigned long bound
    );
    SequenceDef [create_sequence](#corbarepository-interface)(
        in unsigned long bound,
        in IDLType element_type
    );
    ArrayDef [create_array](#corbarepository-interface)(
        in unsigned long length,
        in IDLType element_type
    );
    FixedDef [create_fixed](#corbarepository-interface)(
        in unsigned short digits,
        in short scale
    );
};
```

The inherited [describe_contents\(\)](#) is also described.

Note that although a `Repository` does not have a `RepositoryId` associated with it (because it derives only from `Container` and not from `Contained`) you can assume that its default `RepositoryId` is an empty string. This allows a value to be assigned to the `defined_in` field of each description structure for `ModuleDef`, `InterfaceDef`, `ValueDef`, `ValueBoxDef`, `TypedefDef`, `ExceptionDef` and `ConstantDef` that may be contained immediately within a `Repository` object.

See Also `CORBA::Container`

`Repository::create_array()`

// IDL

```
ArrayDef create_array(
    in unsigned long length,
    in IDLType element_type
);
```

Returns a new array object defining an anonymous (unnamed) type. The new array object must be used in the definition of exactly one other object. It is deleted when the object it is contained in is deleted. If the created object is not successfully used in the definition of a Contained object, it is your application's responsibility to delete it.

Parameters

<code>length</code>	The number of elements in the array.
<code>element_type</code>	The type of element that the array will contain.

See Also `CORBA::ArrayDef`

```
CORBA::IRObject
```

`Repository::create_fixed()`

// IDL

```
FixedDef create_fixed (
    in unsigned short digits,
    in short scale
);
```

Returns a new fixed-point object defining an anonymous (unnamed) type. The new object must be used in the definition of exactly one other object. It is deleted when the object it is contained in is deleted. If the created object is not successfully used in the definition of a Contained object, it is your application's responsibility to delete it.

Parameters

<code>digits</code>	The number of digits in the fixed-point number. Valid values must be between 1 and 31, inclusive.

<code>scale</code>	The scale.

Repository::create_sequence()

// IDL

```
SequenceDef create_sequence (
    in unsigned long bound,
    in IDLType element_type
);
```

Returns a new sequence object defining an anonymous (unnamed) type. The new sequence object must be used in the definition of exactly one other object. It is deleted when the object it is contained in is deleted. If the created object is not successfully used in the definition of a Contained object, it is your application's responsibility to delete it.

Parameters

<code>bound</code>	The number of elements in the sequence. A <code>bound</code> of <code>0</code> indicates an unbounded sequence.
<code>element_type</code>	The type of element that the sequence will contain.

See Also CORBA::SequenceDef

Repository::create_string()

// IDL

```
StringDef create_string(
    in unsigned long bound
);
```

Returns a new string object defining an anonymous (unnamed) type. The new string object must be used in the definition of exactly one other object. It is deleted when the object it is contained in is deleted. If the created object is not successfully used in the definition of a Contained object, it is your application's responsibility to delete it.

Parameters

bound

The maximum number of characters in the string. (This cannot be 0.)

Use `get_primitive()` to create unbounded strings.

See Also `CORBA::StringDef`

```
CORBA::Repository::get_primitive()
```

`Repository::create_wstring()`

// IDL

```
StringDef create_wstring (
    in unsigned long bound
);
```

Returns a new wide string object defining an anonymous (unnamed) type. The new wide string object must be used in the definition of exactly one other object. It is deleted when the object it is contained in is deleted. If the created object is not successfully used in the definition of a Contained object, it is your application's responsibility to delete it.

Parameters

bound

The maximum number of characters in the string. (This cannot be 0.)

Use `get_primitive()` to create unbounded strings.

See Also `CORBA::WstringDef`

```
CORBA::Repository::get_primitive()
```

`Repository::describe_contents()`

// IDL

```
sequence<Description> describe_contents(
    in InterfaceName restrict_type,
    in boolean    exclude_inherited,
    in long      max_returned_objs
);
```

The operation `describe_contents()` is inherited from interface `Container`. It returns a sequence of `Container::Description` structures; one such structure for each top level item in the repository.

Parameters

<code>restrict_type</code>	If this is set to <code>dk_all</code> , then all of the contained interface repository objects are returned. If set to the <code>DefinitionKind</code> for a particular interface repository kind, it returns only objects of that kind. For example, if set to <code>dk_Operation</code> , then it returns contained operations only.
<code>exclude_inherited</code>	Applies only to interfaces. If true, no inherited objects are returned. If false, objects are returned even if they are inherited.
<code>max_returned_objs</code>	The number of objects that can be returned in the call. Setting a value of <code>-1</code> means return all contained objects.

See Also `CORBA::Container::describe_contents()`

```
CORBA::Container::Description
CORBA::DefinitionKind
```

`Repository::get_canonical_typecode()`

// IDL

```
TypeCode get_canonical_typecode(
    in TypeCode tc
);
```

Returns a `TypeCode` that is equivalent to `tc` that also includes all repository ids, names, and member names.

Parameters


```
tc
```

The TypeCode to lookup.

If the top level TypeCode does not contain a RepositoryId (such as array and sequence type codes or type codes from older ORBs) or if it contains a RepositoryId that is not found in the target `Repository`, then a new TypeCode is constructed by recursively calling `get_canonical_typecode()` on each member TypeCode of the original TypeCode.

Repository::get_primitive()

// IDL

```
PrimitiveDef get_primitive(
    in PrimitiveKind kind
);
```

Returns a reference to a PrimitiveDef of the specified PrimitiveKind. All PrimitiveDefobjects are owned by the `Repository`, one primitive object per primitive type (for example, `short`, `long`, `unsigned short`, `unsigned long` and so on).

Parameters

```
kind
```

The kind of primitive to get.

See Also CORBA::PrimitiveDef

Repository::lookup_id()

// IDL

```
Contained lookup_id(
    in RepositoryId search_id
);
```

Returns an object reference to a Contained object within the repository given its RepositoryId. If the repository does not contain a definition for the given ID, a nil object reference is returned.

Parameters

`search_id`

The RepositoryId of the IDL definition to lookup.

See Also CORBA::Contained

CORBA::Request Class

This class is the key support class for the Dynamic Invocation Interface (DII), whereby an application may issue a request for any interface, even if that interface was unknown at the time the application was compiled.

Orbix allows invocations, that are instances of class `Request`, to be constructed by specifying at runtime the target object reference, the operation name and the parameters. Such calls are termed dynamic because the IDL interfaces used by a program do not have to be statically determined at the time the program is designed and implemented.

You create a request using methods `Object::_create_request()` or `Object::_request()`.

```

class Request {
public:
    Object_ptr [target](#corbarequest-class)() const;
    const char *[operation](#corbarequest-class)() const;
    NVList_ptr [arguments](#corbarequest-class)();
    NamedValue_ptr [result](#corbaserverrequest-class)();
    Environment_ptr [env](#corbarequest-class)();
    ExceptionList_ptr [exceptions](#corbarequest-class)();
    ContextList_ptr [contexts](#corbarequest-class)();
    void [ctx](#corbaserverrequest-class)(Context_ptr);
    Context_ptr [ctx](#corbaserverrequest-class)() const;
    // argument manipulation helper functions
    Any &[add_in_arg](#corbarequest-class)();
    Any &[add_in_arg](#corbarequest-class)(const char* name);
    Any &[add_inout_arg](#corbarequest-class)();
    Any &[add_inout_arg](#corbarequest-class)(const char* name);
    Any &[add_out_arg](#corbarequest-class)();
    Any &[add_out_arg](#corbarequest-class)(const char* name);
    void [set_return_type](#corbarequest-class)(TypeCode_ptr tc);
    Any &[return_value](#corbarequest-class)();
    void [invoke](#corbarequest-class)();
    void [send_oneway](#corbarequest-class)();
    void [send_deferred](#corbarequest-class)();
    void [get_response](#corbarequest-class)();
    Boolean [poll_response](#corbarequest-class)();
    // additional Messaging functions
    virtual void [sendc](#corbarequest-class)(CORBA::Object_ptr handler) =
0;
    virtual CORBA::Object_ptr [sendp()](#corbarequest-class) = 0;
    virtual void [prepare](#corbarequest-class)(CORBA::Object_ptr p) = 0;
};

```

See Also CORBA::Object::_request()

```
CORBA::Object::_create_request()
```

Request::add_in_arg()

Any &add_in_arg();

Any &add_in_arg(

```
    const char* name
);
```

Returns an `any` value for the input argument that is added.

Parameters

```
name
```

The name for the argument that is added to the request.

See Also `CORBA::Request::arguments()`

```
CORBA::Request::add_inout_arg()
CORBA::Request::add_out_arg()
```

`Request::add_inout_arg()`

`Any &add_inout_arg();`

`Any &add_inout_arg(`

```
    const char* name
);
```

Returns an `any` value for the in/out argument that is added.

Parameters

```
name
```

The name for the argument that is added to the request.

See Also `CORBA::Request::arguments()`

```
CORBA::Request::add_in_arg()
CORBA::Request::add_out_arg()
```

Request::add_out_arg()

Any &add_out_arg();

Any &add_out_arg(

```
    const char* name
);
```

Returns an `any` value for the output argument that is added.

Parameters

name

The name for the argument that is added to the request.

See Also CORBA::Request::arguments()

```
CORBA::Request::add_in_arg()
CORBA::Request::add_inout_arg()
```

Request::arguments()

NVList_ptr arguments();

Returns the arguments to the requested operation in an NVList. Ownership of the return value is maintained by the `Request` and must not be freed by the caller. You can add additional arguments to the request using the `add_*_arg()` helper methods.

See Also CORBA::NVList

```
CORBA::Request::add_in_arg()
CORBA::Request::add_inout_arg()
CORBA::Request::add_out_arg()
```

Request::contexts()

```
ContextList_ptr contexts();
```

Returns a pointer to a list of contexts for the request. Ownership of the return value is maintained by the `Request` and must not be freed by the caller.

See Also CORBA::ContextList

```
Request::ctx()
```

```
Context_ptr ctx() const;
```

Returns the Context associated with a request. Ownership of the return value is maintained by the `Request` and must not be freed by the caller.

```
void ctx(
```

```
    Context_ptr c
);
```

Inserts a Context into a request.

Parameters

```
c
```

The context to insert with the request.

See Also CORBA::Context

```
Request::env()
```

```
Environment_ptr env();
```

Returns the `Environment` associated with the request from which exceptions raised in DII calls can be accessed. Ownership of the return value is maintained by the `Request` and must not be freed by the caller.

See Also CORBA::Environment

```
Request::exceptions()
```

```
ExceptionList_ptr exceptions();
```

Returns a pointer to list of possible application-specific exceptions for the request. Ownership of the return value is maintained by the `Request` and must not be freed by the caller.

See Also CORBA::ExceptionList

Request::get_response()

void get_response();

Determines whether a request has completed successfully. It returns only when the request, invoked previously using send_deferred(), has completed.

See Also CORBA::Request::result()

```
CORBA::Request::send_deferred()
```

Request::invoke()

void invoke();

Instructs the ORB to make a request. The parameters to the request must already be set up. The caller is blocked until the request has been processed by the target object or an exception occurs.

To make a non-blocking request, see send_deferred() and send_oneway().

See Also CORBA::Request::send_oneway()

```
CORBA::Request::send_deferred()
CORBA::Request::result()
```

Request::operation()

const char *operation() const;

Returns the operation name of the request. Ownership of the return value is maintained by the Request and must not be freed by the caller.

Request::poll_response()

Boolean poll_response();

Returns 1 (true) if the operation has completed successfully and indicates that the return value and out and inout parameters in the request are valid. Returns 0 (false) otherwise. The method returns immediately.

If your application makes an operation request using send_deferred(), it can call poll_response() to determine whether the operation has completed. If the operation has completed, you can get the result by calling Request::result().

See Also CORBA::Request::send_deferred()

```
CORBA::Request::get_response()
CORBA::Request::result()
```

Request::prepare()

virtual void prepare(

```
    CORBA::Object_ptr p
) = 0;
```

Associates an initialized `Request` with a previous operation that was initiated via `sendp()`. The `Request` must be created and associated with the operation's out arguments and return value prior to calling `prepare()`. Once `prepare()` has been called, it is as if that prepared `Request` was the one that actually had `sendp()` used.

Parameters

p

An object reference.

This function along with `sendp()` and `sendc()` enable dynamic time-Independent invocations and dynamic use of the Messaging callback model.

Exceptions

BAD_INV_ORDER	<code>prepare()</code> is invoked on a <code>Request</code> that had previously been used for a send or one of its variants.
BAD_PARAM	<code>prepare()</code> is invoked with an object reference that was not previously returned from an invocation of <code>sendp()</code> .

See Also CORBA::Request::sendp()

```
CORBA::Request::sendc()
```

Request::result()

```
NamedValue_ptr result();
```

Returns the result of the operation request in a NamedValue. Ownership of the return value is maintained by the `Request` and must not be freed by the caller.

```
Request::return_value()
```

```
Any &return_value();
```

Returns an `any` value for the returned value of the operation.

```
Request::sendc()
```

```
virtual void sendc(
```

```
    CORBA::Object_ptr handler
) = 0;
```

Initiates an operation according to the information in the `Request`.

Parameters

```
handler
```

Pass in the callback `Messaging::ReplyHandler` as a base `CORBA::Object`. The results of invocations made with `sendc()` will be available through this handler.

A truly dynamic client can implement the `ReplyHandler` using the DSI.

Exceptions A system exception may be raised if a failure is detected before control is returned to the client, but this is not guaranteed. Any other exceptions are passed to the `ReplyHandler`.

See Also `CORBA::Request::sendp()`

```
CORBA::Request::prepare()
```

```
Request::send_deferred()
```

```
void send_deferred();
```

Instructs the ORB to make the request. The arguments to the request must already be set up. The caller is not blocked, and thus may continue in parallel with the processing of the call by the target object.

To make a blocking request, use `invoke()`. You can use `poll_response()` to determine whether the operation completed.

See Also `CORBA::Request::send_oneway()`

```
CORBA::ORB::send_multiple_requests_deferred()
CORBA::Request::invoke()
CORBA::Request::poll_response()
CORBA::Request::get_response()
```

`Request::send_oneway()`

```
void send_oneway();
```

Instructs Orbix to make the oneway request. The arguments to the request must already be set up. The caller is not blocked, and thus may continue in parallel with the processing of the call by the target object.

You can use this method even if the operation has not been defined to be oneway in its IDL definition, however, do not expect any output or inout parameters to be updated.

To make a blocking request, use `invoke()`.

See Also `CORBA::Request::send_deferred()`

```
CORBA::ORB::send_multiple_requests_oneway()
CORBA::Request::invoke()
CORBA::Request::poll_response()
CORBA::Request::get_response()
```

`Request::sendp()`

```
virtual CORBA::Object_ptr sendp() = 0;
```

Initiates an operation according to the information in the `Request`. The results of invocations made with `sendp()` will be available once the caller uses `get_response()` or `get_next_response()`. The out parameters and return value of the initiated operation must not be used before the operation is done.

Exceptions A system exception may be raised if a failure is detected before control is returned to the client, but this is not guaranteed. Any other exceptions will be raised when `get_response()` is called.

See Also `CORBA::Request::sendc()`

```
CORBA::Request::prepare()
```

```
Request::set_return_type()
```

```
void set_return_type(
```

```
    TypeCode_ptr tc  
);
```

Sets the TypeCode associated with a `Request` object. When using the DII with the Internet Inter-ORB Protocol (IIOP), you must set the return type of a request before invoking the request.

Parameters

```
tc
```

The TypeCode for the return type of the operation associated with the `Request` object.

```
Request::target()
```

```
Object_ptr target() const;
```

Gets the target object of the `Request`. Ownership of the return value is maintained by the `Request` and must not be freed by the caller.

CORBA::SequenceDef Interface

Interface `SequenceDef` represents an IDL sequence definition in the interface repository. It inherits from the interface `IDLType`.

```
// IDL in module CORBA.
interface SequenceDef : IDLType {
    attribute unsigned long [bound](#corbstringdef-interface);
    readonly attribute TypeCode [element_type](#corbaarraydef-interface);
    attribute IDLType [element_type_def](#corbaarraydef-interface);
};
```

The inherited `type` attribute is also described.

See Also `CORBA::IDLType`

```
CORBA::Repository::create_sequence()
```

SequenceDef::bound Attribute

// IDL

```
attribute unsigned long bound;
```

The maximum number of elements in the sequence. A `bound` of `0` indicates an unbounded sequence.

Changing the `bound` attribute will also update the inherited `type` attribute.

See Also `CORBA::SequenceDef::type`

SequenceDef::element_type Attribute

// IDL

```
readonly attribute TypeCode element_type;
```

The type of element contained within this sequence. The attribute `element_type_def` contains the same information.

See Also CORBA::SequenceDef::element_type_def

SequenceDef::element_type_def Attribute

// IDL

```
attribute IDLType element_type_def;
```

Describes the type of element contained within this sequence. The attribute `element_type` contains the same information. Setting the `element_type_def` attribute also updates the `element_type` and `IDLType::type` attributes.

See Also CORBA::SequenceDef::element_type

```
CORBA::IDLType::type
```

SequenceDef::type Attribute

// IDL

```
readonly attribute TypeCode type;
```

The `type` attribute is inherited from interface `IDLType`. This attribute is a `tk_sequence` `TypeCode` that describes the sequence. It is updated automatically whenever the attributes `bound` or `element_type_def` are changed.

See Also CORBA::SequenceDef::element_type_def

```
CORBA::SequenceDef::bound
```

CORBA::ServerRequest Class

Class `ServerRequest` describes a Dynamic Skeleton Interface (DSI) operation request. It is analogous to the Request class used in the Dynamic Invocation Interface (DII).

An instance of `ServerRequest` is created by the ORB when it receives an incoming request that is to be handled by the DSI—that is, an instance of the `PortableServer::DynamicImplementation` class has been registered to handle the target interface.

An instance of `ServerRequest` is a pseudo-object so an instance of a `ServerRequest` cannot be transmitted in an IDL operation.

You should not define derived classes of `ServerRequest`.

The following code is the complete class definition:

```
// in CORBA namespace
class ServerRequest {
public:
    const char* [operation](#corbarequest-class)() const;
    void [arguments](#corbarequest-class)(
        NVList_ptr& parameters
    );
    Context_ptr [ctx](#corbaserverrequest-class)();
    void set_result(
        const Any& value
    );
    void (
        const Any& value
    );
};
```

`ServerRequest::arguments()`

`void arguments(`

```
    NVList_ptr& parameters
);
```

Allows a redefinition of the following method to specify the values of incoming arguments:

```
PortableServer::DynamicImplementation::invoke()
```

Parameters

```
parameters
```

Obtains output and input arguments.

This method must be called *exactly* once in each execution of `invoke()`.

See Also CORBA::ServerRequest::params()

```
PortableServer::DynamicImplementation::invoke()
```

```
ServerRequest::ctx()
```

```
Context_ptr ctx();
```

Returns the Context associated with the call.

This function can be called once or not at all. If it is called, it must be called before `params()` or `ServerRequest::arguments()`.

See Also CORBA::Context

```
ServerRequest::operation()
```

```
const char* operation() const;
```

Parameters Returns the name of the operation being invoked.

This method must be called at least once in each execution of the dynamic implementation routine, that is, in each redefinition of the method:

```
PortableServer::DynamicImplementation::invoke()
```

See Also CORBA::ServerRequest::op_name()


```
PortableServer::DynamicImplementation::invoke()
```

See Also

ServerRequest::set_exception()

void set_exception(

```
    const Any& value
);
```

Allows (a redefinition of) `PortableServer::DynamicImplementation::invoke()` to return an exception to the caller.

Parameters

```
value
```

A pointer to an Any, which holds the exception returned to the caller.

See Also CORBA::Environment()

```
PortableServer::DynamicImplementation::invoke()
```

ServerRequest::set_result()

void set_result(

```
    const Any& value
);
```

Allows `PortableServer::DynamicImplementation::invoke()` to return the result of an operation request in an Any.

Parameters

value

A pointer to a Any, which holds the result returned to the caller.

This method must be called once for operations with non-void return types and not at all for operations with void return types. If it is called, then set_exception() cannot be used.

See Also CORBA::ServerRequest::set_exception()

CORBA::String_var Class

The class `String_var` implements the `_var` type for IDL strings required by the standard C++ mapping. The `String_var` class contains a `char*` value and ensures that this is properly freed when a `String_var` object is deallocated, for example when execution goes out of scope.

```
class String_var {
public:
    [String_var](#corbasting_var-class)();
    [String_var](#corbasting_var-class)(char *p);
    [String_var](#corbasting_var-class)(const char *p);
    [String_var](#corbasting_var-class)(const String_var &s);
    [~String_var](#corbasting_var-class)();
    String_var & [operator=](#corbawstring_var-class)(char *p);
    String_var & [operator=](#corbawstring_var-class)(const char *p);
    String_var & [operator=](#corbawstring_var-class)(const String_var &s);
    operator [char\*](#corbawstring_var-class)();
    operator const [char\*](#corbawstring_var-class)() const;
    const char* [in](#corbawstring_var-class)() const;
    char*& [inout](#corbawstring_var-class)();
    char*& [out](#corbawstring_var-class)();
    char* [_retn](#corbawstring_var-class)();
    char & [operator\[ \]](#corbawstring_var-class)(ULong index);
    char [operator\[ \]](#corbawstring_var-class)(ULong index) const;
};
```

`String_var::char*()`

`operator char*();`

`operator const char*() const;`

Converts a `String_var` object to a `char*`.

See Also `CORBA::String_var::operator=()`

`String_var::in()`

`const char* in() const;`

Returns the proper string for use as an input parameter.

See Also `CORBA::String_var::out()`

```
CORBA::String_var::inout()
CORBA::String_var::_retn()
```

String_var::inout()

char*& inout();

Returns the proper string for use as an inout parameter.

See Also CORBA::String_var::in()

```
CORBA::String_var::out()
CORBA::String_var::_retn()
```

String_var::operator=() Assignment Operators

String_var &operator=(

```
    char *p
);
```

String_var &operator=(

```
    const char *p
);
```

String_var &operator=(

```
    const String_var &s
);
```

Assignment operators allow you to assign values to a `String_var` from a `char*` or from another `String_var` type.

Parameters

<code>p</code>	A character string to assign to the <code>String_var</code> .
<code>s</code>	A <code>String_var</code> to assign to the <code>String_var</code> .

See Also `CORBA::String_var::char*()`

`String_var::operator[]()` Subscript Operators

`char &operator[]()`

```
        ULong index
    );
```

`char operator[]()`

```
        ULong index
    ) const;
```

Return the character at the given location of the string. Subscript operators allow access to the individual characters in the string.

Parameters

`index`

The index location in the string.

`String_var::out()`

`char*& out();`

Returns the proper string for use as an output parameter.

See Also `CORBA::String_var::in()`

```
CORBA::String_var::inout()
CORBA::String_var::_retn()
```

`String_var::String_var()` Constructors

```
String_var();
```

The default constructor.

```
String_var(
```

```
    char *p
);
```

```
String_var(
```

```
    const char *p
);
```

Constructors that convert from a `char*` to a `String_var`.

```
String_var(
```

```
    const String_var &s
);
```

The copy constructor.

Parameters

<code>p</code>	The character string to convert to a <code>String_var</code> . The <code>String_var</code> assumes ownership of the parameter.
<code>s</code>	The original <code>String_var</code> that is copied.

See Also `CORBA::String_var::~~String_var()`

`String_var::~~String_var()` Destructor

```
~String_var();
```

The destructor.

See Also `CORBA::String_var::String_var()`

```
String_var::_retn()
```

```
char* _retn();
```

Returns the proper string for use as a method's return value.

See Also CORBA::String_var::inout()

```
CORBA::String_var::in()  
CORBA::String_var::out()
```

CORBA::StringDef Interface

Interface `StringDef` represents an IDL bounded string type in the interface repository. A `StringDef` object is anonymous, which means it is unnamed.

Use `Repository::create_string()` to obtain a new `StringDef`. Use `Repository::get_primitive()` for unbounded strings.

```
// IDL in module CORBA.
interface StringDef : IDLType {
    attribute unsigned long [bound](#corbstringdef-interface);
};
```

The inherited `type` attribute is also described.

See Also `CORBA::IDLType`

```
CORBA::Repository::create_string()
```

`StringDef::bound` Attribute

// IDL

```
attribute unsigned long bound;
```

Specifies the maximum number of characters in the string. This cannot be zero.

`StringDef::type` Attribute

// IDL

```
readonly attribute TypeCode type;
```

The `type` attribute is inherited from interface `IDLType`. This attribute is a `tk_string` `TypeCode` that describes the string.

See Also `CORBA::IDLType::type`

CORBA::StructDef Interface

Interface `StructDef` describes an IDL structure in the interface repository.

```
// IDL in module CORBA.
interface StructDef : TypedefDef, Container {
    attribute StructMemberSeq [members](#it_loadbalancingobjectgroup-
interface);
};
```

The inherited operation `describe()` is also described.

See Also `CORBA::Contained`

```
CORBA::Container::create_struct()
```

`StructDef::describe()`

// IDL

```
Description describe();
```

`describe()` returns a `Contained::Description` structure. `describe()` is inherited from `Contained` (which `TypedefDef` inherits).

The `DefinitionKind` for the `kind` member is `dk_Struct`. The `value` member is an `any` whose `TypeCode` is `_tc_TypeDescription` and whose value is a structure of type `TypeDescription`.

See Also `CORBA::TypedefDef::describe()`

`StructDef::members` Attribute

// IDL

```
attribute StructMemberSeq members;
```

Describes the members of the structure.

You can modify this attribute to change the members of a structure. Only the `name` and `type_def` fields of each `StructMember` should be set (the `type` field should be set to `_tc_void` and it will be set automatically to the `TypeCode` of the `type_def` field).

See Also `CORBA::TypedefDef`

CORBA::TypeCode Class

The class `TypeCode` is used to describe IDL type structures at runtime. A `TypeCode` is a value that represents an IDL invocation argument type or an IDL attribute type. A `TypeCode` is typically used as follows:

- In the dynamic invocation interface (DII) to indicate the type of an actual argument.
- By the interface repository to represent the type specification that is part of an OMG IDL declaration.
- To describe the data held by an `any` type.

A `TypeCode` consists of a *kind* that classifies the `TypeCode` as to whether it is a basic type, a structure, a sequence and so on. See the data type `TCKind` for all possible kinds of `TypeCode` objects.

A `TypeCode` may also include a sequence of parameters. The parameters give the details of the type definition. For example, the IDL type `sequence<long, 20>` has the kind `tk_sequence` and has parameters `long` and `20`.

You typically obtain a `TypeCode` from the interface repository or it may be generated by the IDL compiler. You do not normally create a `TypeCode` in your code so the class contains no constructors, only methods to decompose the components of an existing `TypeCode`. However, if your application does require that you create a `TypeCode`, see the set of `create_Type_tc()` methods in the ORB class.

For functions that require `TypeCode` parameters, such as with the DII, you can use the appropriate constant from the following list:

CORBA::_tc_any	CORBA::_tc_octet
CORBA::_tc_boolean	CORBA::_tc_Principal
CORBA::_tc_char	CORBA::_tc_short
CORBA::_tc_double	CORBA::_tc_string
CORBA::_tc_float	CORBA::_tc_TypeCode
CORBA::_tc_long	CORBA::_tc_ulong
CORBA::_tc_longdouble	CORBA::_tc_ulonglong
CORBA::_tc_longlong	CORBA::_tc_ushort
CORBA::_tc_NamedValue	CORBA::_tc_void
CORBA::_tc_null	CORBA::_tc_wchar
CORBA::_tc_Object	CORBA::_tc_wstring

The class `TypeCode` contains the following methods:

```
// C++
class TypeCode {
public:
    class [Bounds](#corbatypecode-class) : public UserException { ... };
    class [BadKind](#corbatypecode-class) : public UserException { ... };
    Boolean [equal](#dynamicanydynany-class)(TypeCode_ptr) const;
    Boolean [equivalent](#corbatypecode-class)(TypeCode_ptr) const;
    TCKind [kind](#corbatypecode-class)() const;
    TypeCode_ptr [get_compact_typecode](#corbatypecode-class)() const;
    const char* [id](#dslogadminlog-interface)() const;
    const char* [name](#corbanamedvalue-class)() const;
    ULong [member_count](#corbatypecode-class)() const;
    const char* [member_name](#dynamicanydynunion-class)(ULong index)
const;
    TypeCode_ptr [member_type](#corbatypecode-class)(ULong index) const;
    Any* [member_label](#corbatypecode-class)(ULong index) const;
    TypeCode_ptr [discriminator_type](#corbatypecode-class)() const;
    Long [default_index](#corbatypecode-class)() const;
    ULong [length](#corbatypecode-class)() const;
    TypeCode_ptr [content_type](#corbatypecode-class)() const;
    UShort [fixed_digits](#corbatypecode-class)() const;
    Short [fixed_scale](#corbatypecode-class)() const;
    Visibility [member_visibility](#corbatypecode-class)(ULong index)
const;
    ValueModifier [type_modifier](#corbatypecode-class)() const;
    TypeCode_ptr [concrete_base_type](#corbatypecode-class)() const;
    static TypeCode_ptr [_duplicate](#corbapolicycurrent-class)
(TypeCode_ptr tc);
    static TypeCode_ptr [_nil](#corbapolicycurrent-class)();
};
```

See AlsoCORBA::TCKind

TypeCode::BadKind Exception

```
class BadKind : public UserException { ... };
```

The `BadKind` exception is raised if a `TypeCode` member method is invoked for a kind that is not appropriate.

TypeCode::Bounds Exception

```
class Bounds : public UserException { ... };
```

The `Bounds` exception is raised if an attempt is made to use an index for a type's member that is greater than or equal to the number of members for the type.

The type of IDL constructs that have members include enumerations, structures, unions, value types, and exceptions. Some of the `TypeCode` methods return information about specific members

of these IDL constructs. The first member has index value 0, the second has index value 1, and so on up to `n-1` where `n` is the count of the total number of members.

The order in which members are presented in the interface repository is the same as the order in which they appeared in the IDL specification.

This exception is not the same as the `CORBA::Bounds` exception.

See Also `CORBA::TypeCode::member_count()`

```
CORBA::TypeCode::member_label()
CORBA::TypeCode::member_name()
CORBA::TypeCode::member_type()
CORBA::TypeCode::member_visibility()
```

`TypeCode::concrete_base_type()`

`TypeCode_ptr concrete_base_type() const;`

Returns a `TypeCode` for the concrete base if the value type represented by this `TypeCode` has a concrete base value type. Otherwise it returns a nil `TypeCode` reference. This method is valid to use only if the kind of `TypeCode` has a TCKind value of `tk_value`.

Exceptions

BadKind

The kind of `TypeCode` is not valid for this method.

`TypeCode::content_type()`

`TypeCode_ptr content_type() const;`

For sequences and arrays this method returns a reference to the element type. For aliases it returns a reference to the original type. For a boxed value type it returns a reference to the boxed type. This method is valid to use if the kind of `TypeCode` is one of the following TCKind values:

```
tk_alias
tk_array
tk_sequence
tk_value_box
```

Exceptions

BadKind

The kind of `TypeCode` is not valid for this method.

`TypeCode::default_index()`

Long `default_index()` const;

Returns the index of the default union member, or -1 if there is no default member. This method is valid to use only if the kind of `TypeCode` has a TCKind value of `tk_union`.

Exceptions**BadKind**

The kind of `TypeCode` is not valid for this method.

See Also `CORBA::TypeCode::member_label()`

`TypeCode::discriminator_type()`

`TypeCode_ptr discriminator_type()` const;

Returns a `TypeCode` for the union discriminator type. This method is valid to use only if the kind of `TypeCode` has a TCKind value of `tk_union`.

Exceptions**BadKind**

The kind of `TypeCode` is not valid for this method.

See Also `CORBA::TypeCode::default_index()`

```
CORBA::TypeCode::member_label()
```

`TypeCode::_duplicate()`

static `TypeCode_ptr _duplicate(`

```
    TypeCode_ptr obj
);
```

Increments the reference count of `obj` and returns a new reference to the `TypeCode` object.

Parameters

obj

A reference to the original `TypeCode` to duplicate.

See Also `CORBA::release()`

`TypeCode::equal()`

Boolean `equal()`

```
    TypeCode_ptr tc
) const;
```

Returns 1 (true) if this `TypeCode` and the `tc` parameter are equal. Returns 0 (false) otherwise. Two type codes are equal if the set of legal operations is the same and invoking an operation from one set returns the same results as invoking the operation from the other set.

Parameters

tc

The `TypeCode` to compare.

See Also `CORBA::TypeCode::equivalent()`

`TypeCode::equivalent()`

Boolean `equivalent()`

```
    TypeCode_ptr tc
) const;
```

Returns 1 (true) if this `TypeCode` and the `tc` parameter are equivalent. Returns 0 (false) otherwise.

Parameters

tc

The `TypeCode` to compare.

`equivalent()` is typically used by the ORB to determine type equivalence for values stored in an IDL any. You can use `equal()` to compare type codes in your application. `equivalent()` would return true if used to compare a type and an alias of that type while `equal()` would return false.

See Also `CORBA::TypeCode::equal()`

TypeCode::fixed_digits()

UShort fixed_digits() const;

Returns the number of digits in the fixed point type. This method is valid to use only if the kind of `TypeCode` has a TCKind value of tk_fixed.

Exceptions

BadKind

The kind of `TypeCode` is not valid for this method.

See Also CORBA::TypeCode::fixed_scale()

TypeCode::fixed_scale()

Short fixed_scale() const;

Returns the scale of the fixed point type. This method is valid to use only if the kind of `TypeCode` has a TCKind value of tk_fixed.

Exceptions

BadKind

The kind of `TypeCode` is not valid for this method.

See Also CORBA::TypeCode::fixed_digits()

TypeCode::get_compact_typecode()

TypeCode_ptr get_compact_typecode() const;

Removes all optional name and member name fields from the `TypeCode` and returns a reference to the compact `TypeCode`. This method leaves all alias type codes intact.

TypeCode::id()

const char* id() const;

Returns the RepositoryId that globally identifies the type.

Type codes that always have a RepositoryId. include object references, value types, boxed value types, native, and exceptions. Other type codes that also always have a RepositoryId and are obtained from the interface repository or ORB :: create_operation_list() include structures, unions, enumerations, and aliases. In other cases `id()` could return an empty string.

The `TypeCode` object maintains the memory of the return value; this return value must not be freed by the caller.

This method is valid to use if the kind of `TypeCode` has a TCKind value of one of the following:

```
tk_abstract_interface
tk_alias
tk_enum
tk_except
tk_native
tk_objref
tk_struct
tk_union
tk_value
tk_value_box
```

Exceptions

BadKind

The kind of `TypeCode` is not valid for this method.

`TypeCode::kind()`

`TCKind kind() const;`

Returns the kind of the `TypeCode` which is an enumerated value of type `TCKind`. You can use `kind()` on any `TypeCode` to help determine which other `TypeCode` methods can be invoked on the `TypeCode`.

See Also `CORBA::TCKind`

`TypeCode::length()`

`ULong length() const;`

For strings, wide strings, and sequences, `length()` returns the bound, with zero indicating an unbounded string or sequence. For arrays, `length()` returns the number of elements in the array. This method is valid to use if the kind of `TypeCode` has a `TCKind` value of one of the following:

```
tk_array
tk_sequence
tk_string
tk_wstring
```

Exceptions

BadKind

The kind of `TypeCode` is not valid for this method.

TypeCode::member_count()

ULong member_count() const;

Returns the number of members in the type. This method is valid to use if the kind of `TypeCode` has a TCKind value of one of the following:

```
tk_enum
tk_except
tk_struct
tk_union
tk_value
```

Exceptions

BadKind

The kind of `TypeCode` is not valid for this method.

TypeCode::member_label()

Any *member_label(

```
    ULong index
) const;
```

Returns the label of the union member. For the default member, the label is the zero octet. This method is valid to use only if the kind of `TypeCode` has a TCKind value of `tk_union`.

Parameters

index

The index indicating which union member you want.

Exceptions

BadKind	The kind of <code>TypeCode</code> is not valid for this method.
Bounds	The <code>index</code> parameter is greater than or equal to the number of members for the type.

See Also CORBA::TypeCode::default_index()

```
CORBA::TypeCode::member_count()
```

```
TypeCode::member_name()
```

```
const char* member_name(
```

```
    ULong index
) const;
```

Returns the simple name of the member. Because names are local to a repository, the name returned from a `TypeCode` may not match the name of the member in any particular repository, and may even be an empty string.

Parameters

```
index
```

The index indicating which member to use.

This method is valid to use if the kind of `TypeCode` has a TCKind value of one of the following:

```
tk_enum
tk_except
tk_struct
tk_union
tk_value
```

The `TypeCode` object maintains the memory of the return value; this return value must not be freed by the caller.

Exceptions

<code>BadKind</code>	The kind of <code>TypeCode</code> is not valid for this method.
<code>Bounds</code>	The <code>index</code> parameter is greater than or equal to the number of members for the type.

See Also `CORBA::TypeCode::member_count()`

```
TypeCode::member_type()
```

```
TypeCode_ptr member_type(
```

```
        ULong index
    ) const;
```

Returns a reference to the `TypeCode` of the member identified by `index`.

Parameters

`index`

The index indicating which member you want.

This method is valid to use if the kind of `TypeCode` has a TCKind value of one of the following:

```
tk_except
tk_struct
tk_union
tk_value
```

Exceptions

<code>BadKind</code>	The kind of <code>TypeCode</code> is not valid for this method.
<code>Bounds</code>	The <code>index</code> parameter is greater than or equal to the number of members for the type.

See Also `CORBA::TypeCode::member_count()`

`TypeCode::member_visibility()`

Visibility `member_visibility()`

```
        ULong index
    ) const;
```

Returns the Visibility of a value type member. This method is valid to use only if the kind of `TypeCode` has a TCKind value of `tk_value`.

Parameters

`index`

The index indicating which value type member you want.

Exceptions

BadKind	The kind of <code>TypeCode</code> is not valid for this method.
Bounds	The <code>index</code> parameter is greater than or equal to the number of members for the type.

See Also

CORBA::Visibility

```
CORBA::TypeCode::member_count()
```

```
CORBA::TypeCode::member_count()TypeCode::name()
```

```
const char* name() const;
```

Returns the simple name identifying the type within its enclosing scope. Because names are local to a repository, the name returned from a `TypeCode` may not match the name of the type in any particular repository, and may even be an empty string.

The `TypeCode` object maintains the memory of the return value; this return value must not be freed by the caller.

This method is valid to use if the kind of `TypeCode` has a `TCKind` value of one of the following:

```
tk_abstract_interface
tk_alias
tk_enum
tk_except
tk_native
tk_objref
tk_struct
tk_union
tk_value
tk_value_box
```

Exceptions

BadKind

The kind of `TypeCode` is not valid for this method.

```
TypeCode::_nil()
```

```
static TypeCode_ptr _nil();
```

Returns a nil object reference for a `TypeCode` .

See Also `CORBA::is_nil()`

`TypeCode::type_modifier()`

`ValueModifier type_modifier() const;`

Returns the `ValueModifier` that applies to the value type represented by this `TypeCode` . This method is valid to use only if the kind of `TypeCode` has a `TCKind` value of `tk_value`.

Exceptions

BadKind

The kind of `TypeCode` is not valid for this method.

CORBA::TypedefDef Interface

The abstract interface `TypedefDef` is simply a base interface for interface repository interfaces that define named types. Named types are types for which a name must appear in their definition such as structures, unions, and so on. Interfaces that inherit from `typedefDef` include:

- `AliasDef`
- `EnumDef`
- `NativeDef`
- `StructDef`
- `UnionDef`
- `ValueBoxDef`

Anonymous types such as `PrimitiveDef`, `StringDef`, `SequenceDef` and `ArrayDef` do not inherit from `TypedefDef`.

```
//IDL in module CORBA.
interface TypedefDef : Contained, IDLType {};
```

The inherited operation `describe()` is described here.

`TypedefDef::describe()`

//IDL

```
Description describe();
```

Inherited from `Contained`, `describe()` returns a structure of type `Contained::Description`.

The `DefinitionKind` type for the `kind` member is `dk_Typedef`. The value member is an `any` whose `TypeCode` is `_tc_TypeDescription` and whose value is a structure of type `TypeDescription`.

See Also `CORBA::Contained::describe()`

```
CORBA::Contained::Description
CORBA::TypeDescription
```


CORBA::UnionDef Interface

Interface `UnionDef` represents an IDL union in the interface repository.

```
// IDL in module CORBA.
interface UnionDef : TypedefDef {
    readonly attribute TypeCode [discriminator_type](#corbauniondef-
interface);
    attribute IDLType [discriminator_type_def](#corbauniondef-interface);
    attribute UnionMemberSeq [members](#it_loadbalancingobjectgroup-
interface);
};
```

The inherited operation `describe()` is also described.

See Also `CORBA::Contained`

```
CORBA::TypedefDef
CORBA::Container::create_union()
```

`UnionDef::describe()`

```
// IDL
Description describe();
```

Inherited from `Contained` (which `TypedefDef` inherits), `describe()` returns a structure of type `Contained::Description`.

The `DefinitionKind` for the `kind` member is `dk_Union`. The value member is an `any` whose `TypeCode` is `_tc_TypeDescription` and whose value is a structure of type `TypeDescription`.

See Also `CORBA::TypedefDef::describe()`

`UnionDef::discriminator_type` Attribute

```
// IDL
readonly attribute TypeCode discriminator_type;
```

Describes the discriminator type for this union. For example, if the union currently contains a `long`, the `discriminator_type` is `_tc_long`. The attribute `discriminator_type_def` contains the same information.

See Also CORBA::TypeCode

UnionDef::discriminator_type_def Attribute

```
// IDL
attribute IDLType discriminator_type_def;
```

Describes the discriminator type for this union. The attribute `discriminator_type` contains the same information.

Changing this attribute will automatically update the `discriminator_type` attribute and the `IDLType::type` attribute.

See Also CORBA::IDLType::type

```
CORBA::UnionDef::discriminator_type
```

UnionDef::members Attribute

```
// IDL
attribute UnionMemberSeq members;
```

Contains a description of each union member: its name, label, and type (`type` and `type_def` contain the same information).

The `members` attribute can be modified to change the union's members. Only the `name`, `label` and `type_def` fields of each `UnionMember` should be set (the `type` field should be set to `_tc_void`, and it will be set automatically to the `TypeCode` of the `type_def` field).

See Also CORBA::TypedefDef

CORBA::ValueBase Class

All value types have a conventional base type called `ValueBase`. `ValueBase` serves a similar role for value types that the `Object` class serves for interfaces. `ValueBase` serves as an abstract base class for all value type classes. You must implement concrete value type classes that inherit from `ValueBase`. `ValueBase` provides several pure virtual reference counting methods inherited by all value type classes.

```
namespace CORBA {
    class ValueBase {
    public:
        virtual ValueBase* [_add_ref](#it_corbarefcountedlocalobjectnc-class)
() = 0;
        virtual void [_remove_ref](#it_corbarefcountedlocalobjectnc-class)()
= 0;
        virtual ValueBase* [_copy_value](#corbavaluebase-class)() = 0;
        virtual ULong [_refcount_value](#corbavaluebase-class)() = 0;
        static ValueBase* [_downcast](#messagingexceptionholder-value-type)
(ValueBase*);
    protected:
        [ValueBase](#corbavaluebase-class)();
        [ValueBase](#corbavaluebase-class)(const ValueBase&);
        virtual [~ValueBase](#corbavaluebase-class)();
        ...
    };
}
```

The names of these methods begin with an underscore to keep them from clashing with your application-specific methods in derived value type classes.

See Also `CORBA::ValueFactory`

`ValueBase::_add_ref()`

`virtual ValueBase* _add_ref() = 0;`

Increments the reference count of a value type instance and returns a pointer to this value type.

See Also `CORBA::ValueBase::_remove_ref()`

`ValueBase::_copy_value()`

`virtual ValueBase* _copy_value() = 0;`

Makes a deep copy of the value type instance and returns a pointer to the copy. The copy has no connections with the original instance and has a lifetime independent of that of the original.

Portable applications should not assume covariant return types but should use downcasting to regain the most derived type of a copied value type. A covariant return type means that a class derived from `ValueBase` can override `_copy_value()` to return a pointer to the derived class rather than the base class, `ValueBase*`.

See Also `CORBA::ValueBase::_downcast()`

`ValueBase::_downcast()`

`static ValueBase* _downcast(`

```
ValueBase* vt
);
```

Returns a pointer to the base type for a derived value type class.

Parameters

```
vt
```

Pointer to the value type class to be downcast.

`ValueBase::_refcount_value()`

`virtual ULong _refcount_value() = 0;`

Returns the current value of the reference count for this value type instance.

See Also `CORBA::ValueBase::_add_ref()`

```
CORBA::ValueBase::_remove_ref()
```

`ValueBase::_remove_ref()`

`virtual _remove_ref() = 0;`

Decrements the reference count of a value type instance and deletes the instance when the reference count drops to zero.

If you use `delete()` to destroy instances, you must use the `new` operator to allocate all value type instances.

See Also `CORBA::ValueBase::_add_ref()`

`ValueBase::~~ValueBase()` Destructor

protected:

```
virtual ~ValueBase();
```

The default destructor.

The destructor is protected to prevent direct deletion of instances of classes derived from `ValueBase`.

See Also `CORBA::ValueBase::ValueBase()`

`ValueBase::ValueBase()` Constructors

protected:

```
ValueBase();
```

The default constructor.

protected:

```
ValueBase(
    const ValueBase& vt
);
```

The copy constructor. Creates a new object that is a copy of `vt`.

The copy constructor is protected to disallow copy construction of derived value type instances except from within derived class methods.

Parameters

```
vt
```

The original value type from which a copy is made.

See Also CORBA::ValueBase::~~ValueBase()

CORBA::ValueBoxDef Interface

The `ValueBoxDef` interface describes an IDL value box type in the interface repository. A value box is a value type with no inheritance or operations and with a single state member. A value box is a shorthand IDL notation used to simplify the use of value types for simple containment. It behaves like an additional namespace that contains only one name.

```
// IDL in module CORBA.
interface ValueBoxDef : IDLType {
    attribute IDLType [original_type_def](#corbaaliasdef-interface);
};
```

The inherited `type` attribute is also described.

See Also `CORBA::Container::create_value_box()`

`ValueBoxDef::original_type_def` Attribute

// IDL

```
attribute IDLType original_type_def;
```

Identifies the IDL `type_def` that is being “boxed”. Setting the `original_type_def` attribute also updates the `type` attribute.

See Also `CORBA::ValueBoxDef::type`

`ValueBoxDef::type` Attribute

// IDL

```
readonly attribute TypeCode type;
```

Inherited from `IDLType`, this attribute is a `tk_value_box` `TypeCode` describing the value box.

See Also `CORBA::IDLType::type`

CORBA::ValueDef Interface

A `ValueDef` object represents an IDL value type definition in the interface repository. It can contain constants, types, exceptions, operations, and attributes.

A `ValueDef` used as a Container may only contain `TypedefDef`, (including definitions derived from `TypedefDef`), `ConstantDef`, and `ExceptionDef` definitions.


```

// IDL in module CORBA.
interface ValueDef : Container, Contained, IDLType {
    // read/write interface
    attribute InterfaceDef [supported_interfaces](#corbavaluedef-interface);
    attribute InitializerSeq [initializers](#corbavaluedef-interface);
    attribute ValueDef [base_value](#corbavaluedef-interface);
    attribute ValueDefSeq [abstract_base_values](#corbavaluedef-interface);
    attribute boolean [is_abstract](#corbavaluedef-interface);
    attribute boolean [is_custom](#corbavaluedef-interface);
    attribute boolean [is_truncatable](#corbavaluedef-interface);
    // read interface
    boolean [is_a](#corbainterfacedef-interface)(
        in RepositoryId id
    );
    struct [FullValueDescription](#corbavaluedef-interface) {
        Identifier name;
        RepositoryId id;
        boolean is_abstract;
        boolean is_custom;
        RepositoryId defined_in;
        VersionSpec version;
        OpDescriptionSeq operations;
        AttrDescriptionSeq attributes;
        ValueMemberSeq members;
        InitializerSeq initializers;
        RepositoryIdSeq supported_interfaces;
        RepositoryIdSeq abstract_base_values;
        boolean is_truncatable;
        RepositoryId base_value;
        TypeCode type;
    };
    FullValueDescription [describe_value](#corbavaluedef-interface)();
    ValueMemberDef [create_value_member](#corbavaluedef-interface)(
        in RepositoryId id,
        in Identifier name,
        in VersionSpec version,
        in IDLType type,
        in Visibility access
    );
    AttributeDef [create_attribute](#corbainterfacedef-interface)(
        in RepositoryId id,
        in Identifier name,
        in VersionSpec version,
        in IDLType type,
        in AttributeMode mode
    );
};

```

```

    OperationDef [create_operation](#corbainterfacedef-interface)(
        in RepositoryId id,
        in Identifier name,
        in VersionSpec version,
        in IDLType result,
        in OperationMode mode,
        in ParDescriptionSeq params,
        in ExceptionDefSeq exceptions,
        in ContextIdSeq contexts
    );
}; // End ValueDef Interface

```

The inherited [describe\(\)](#) and [contents\(\)](#) operations are also described.

See Also CORBA::Container::create_value()

ValueDef::abstract_base_values Attribute

// IDL

```
attribute ValueDefSeq abstract_base_values;
```

The `abstract_base_values` attribute lists the abstract value types from which this value inherits.

Exceptions

`BAD_PARAM`, minor code 5

The `name` attribute of any object contained by this `ValueDef` conflicts with the `name` attribute of any object contained by any of the specified bases.

ValueDef::base_value Attribute

// IDL

```
attribute ValueDef base_value;
```

The `base_value` attribute describes the value type from which this value inherits.

Parameters

`BAD_PARAM`, minor code 5

The `name` attribute of any object contained by the minor code 5 is raised if the `name` attribute of any object contained by this `ValueDef` conflicts with the `name` attribute of any object contained by any of the specified bases.

`ValueDef::contents()`

// IDL

```
ContainedSeq contents(
    in DefinitionKind limit_type,
    in boolean exclude_inherited
);
```

Inherited from `Container`, `contents()` returns the list of constants, types, and exceptions defined in this `ValueDef` and the list of attributes, operations, and members either defined or inherited in this `ValueDef`.

Parameters

<code>limit_type</code>	If set to <code>dk_all</code> , all of the contained objects in the <code>ValueDef</code> are returned. If set to the <code>DefinitionKind</code> for a specific interface type, it returns only interfaces of that type. For example, if set to, <code>dk_Operation</code> , then it returns contained operations only.
<code>exclude_inherited</code>	Applies only to interfaces. If true, only attributes, operations and members defined within this value type are returned. If false, all attributes, operations and members are returned.

See Also `CORBA::Container::contents()`

`ValueDef::create_attribute()`

// IDL

```
AttributeDef create_attribute(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in IDLType type,
    in AttributeMode mode
);
```

Returns a new `AttributeDef` object contained in the `ValueDef` on which it is invoked.

Parameters

<code>id</code>	The repository ID to use for the new AttributeDef. An AttributeDef inherits the <code>id</code> attribute from Contained.
<code>name</code>	The <code>name</code> to use for the new AttributeDef. An AttributeDef inherits the <code>name</code> attribute from Contained.
<code>version</code>	The <code>version</code> to use for the new AttributeDef. An AttributeDef inherits the <code>version</code> attribute from Contained.
<code>type</code>	The IDL data type for the new AttributeDef. Both the <code>type_def</code> and <code>type</code> attributes are set for AttributeDef.
<code>mode</code>	The read or read/write <code>mode</code> to use for the new AttributeDef.

The `defined_in` attribute (which the AttributeDef inherits from Contained) is initialized to identify the containing `ValueDef`.

Exceptions

<code>BAD_PARAM</code> , minor code 5	The <code>name</code> attribute of any object contained by minor code 2 is raised if an object with the specified <code>id</code> already exists in the repository.
<code>BAD_PARAM</code> , minor code 3	An object with the same <code>name</code> already exists in this <code>ValueDef</code> .

See Also CORBA::AttributeDef

CORBA::Contained

ValueDef::create_operation()

// IDL

```

OperationDef create_operation(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in IDLType result,
    in OperationMode mode,
    in ParDescriptionSeq params,
    in ExceptionDefSeq exceptions,
    in ContextIdSeq contexts
);

```

Returns a new OperationDef object contained in the `ValueDef` on which it is invoked.

Parameters

<code>id</code>	The repository ID to use for the new OperationDef. An OperationDef inherits the <code>id</code> attribute from Contained.
<code>name</code>	The <code>name</code> to use for the new OperationDef. An OperationDef inherits the <code>name</code> attribute from Contained.
<code>version</code>	The <code>version</code> to use for the new OperationDef. An OperationDef inherits the <code>version</code> attribute from Contained.
<code>result</code>	The IDL data type of the return value for the new OperationDef. Both the <code>result_def</code> and <code>result</code> attributes are set for the OperationDef.
<code>mode</code>	The <code>mode</code> to use for the new OperationDef. Specifies whether the operation is normal (OP_NORMAL) or oneway (OP_ONeway).
<code>params</code>	The parameters for this OperationDef.
<code>exceptions</code>	The list of exceptions to use for the OperationDef. These are exceptions the operation can raise.
<code>contexts</code>	The list of context identifiers to use for the OperationDef. These represent the context clause of the operation.

The `defined_in` attribute (which the OperationDef inherits from Contained) is initialized to identify the containing `ValueDef`.

Exceptions

<code>BAD_PARAM</code> , minor code 5	The <code>name</code> attribute of any object contained by minor code 2 is raised if an object with the specified <code>id</code> already exists in the repository.
<code>BAD_PARAM</code> , minor code 3	An object with the same <code>name</code> already exists in this <code>ValueDef</code> .

See Also CORBA::OperationDef

CORBA::Contained

ValueDef::create_value_member()

// IDL

```
ValueMemberDef create_value_member(
    in RepositoryId id,
    in Identifier name,
    in VersionSpec version,
    in IDLType type,
    in Visibility access
);
```

Returns a new ValueMemberDef contained in the `ValueDef` on which it is invoked.

Parameters

<code>id</code>	The repository ID to use for the new ValueMemberDef. An ValueMemberDef inherits the <code>id</code> attribute from Contained.
<code>name</code>	The <code>name</code> to use for the new ValueMemberDef. An ValueMemberDef inherits the <code>name</code> attribute from Contained.
<code>version</code>	The <code>version</code> to use for the new ValueMemberDef. An ValueMemberDef inherits the <code>version</code> attribute from Contained.
<code>type</code>	The IDL data type for the new ValueMemberDef. Both the <code>type_def</code> and <code>type</code> attributes are set for ValueMemberDef.

<code>access</code>	The visibility to use for the new ValueMemberDef. IDL value types can have state members that are either public or private.

The `defined_in` attribute (which the ValueMemberDef inherits from Contained) is initialized to identify the containing ValueDef.

Exceptions

<code>BAD_PARAM</code> , minor code <code>5</code>	The <code>name</code> attribute of any object contained by minor code 2 is raised if an object with the specified <code>id</code> already exists in the repository.
A <code>BAD_PARAM</code> , minor code <code>3</code>	An object with the same <code>name</code> already exists in this ValueDef.

See Also CORBA::ValueMemberDef

CORBA::Contained

ValueDef::describe()

// IDL

```
ValueDescription describe();
```

Inherited from Contained, `describe()` for a ValueDef returns a ValueDescription object. Use `describe_value()` for a full description of the value.

See Also CORBA::ValueDescription

```
CORBA::Contained::describe()
CORBA::ValueDef::describe_value()
```

ValueDef::describe_value()

// IDL

```
FullValueDescription describe_value();
```

Returns a FullValueDescription object describing the value, including its operations and attributes.

See Also CORBA::FullValueDescription

```
CORBA::ValueDef::describe()
```

ValueDef::FullValueDescription Structure

// IDL

```
struct FullValueDescription {
    Identifier name;
    RepositoryId id;
    boolean is_abstract;
    boolean is_custom;
    RepositoryId defined_in;
    VersionSpec version;
    OpDescriptionSeq operations;
    AttrDescriptionSeq attributes;
    ValueMemberSeq members;
    InitializerSeq initializers;
    RepositoryIdSeq supported_interfaces;
    RepositoryIdSeq abstract_base_values;
    boolean is_truncatable;
    RepositoryId base_value;
    TypeCode type;
};
```

A full description of a value type in the interface repository.

<code>name</code>	The name of the value type.
<code>id</code>	The repository ID of the value type.
<code>is_abstract</code>	Has a value of 1 (true) if the value is an abstract value type. A value of 0 is false.
<code>is_custom</code>	Has a value of 1 (true) if the value uses custom marshalling. A value of 0 is false.

<code>defined_in</code>	The repository ID that identifies where this value type is defined.
<code>version</code>	The version of the value type.
<code>operations</code>	A list of operations that the value type supports.
<code>attributes</code>	A list of attributes that the value type supports.
<code>members</code>	A list of value type members.
<code>initializers</code>	A list of initializer values for the value type.
<code>supported_interfaces</code>	A list of interfaces this value type supports.
<code>abstract_base_values</code>	A list of repository IDs that identify abstract base values.
<code>is_truncatable</code>	Has a value of 1 (true) if the value type is truncatable. A value of 0 is false.
<code>base_value</code>	A repository ID that identifies a base value.
<code>type</code>	The IDL type of the value type.

See Also CORBA::ValueDef::describe_value()

ValueDef::initializers Attribute

// IDL

```
attribute InitializerSeq initializers;
```

Lists the initializers this value type supports.

ValueDef::is_a()

// IDL

```
boolean is_a(
    in RepositoryId id
);
```

Returns 1 (true) if this value type is either identical to or inherits, directly or indirectly, from the interface or value identified by the `id` parameter. Otherwise it returns 0 (false).

Parameters

`id`

The repository ID of the value type or interface to compare with this value type.

ValueDef::is_abstract Attribute

// IDL

```
attribute boolean is_abstract;
```

Returns 1 (true) if this value type is an abstract value type. Otherwise it returns 0 (false).

ValueDef::is_custom Attribute

// IDL

```
attribute boolean is_custom;
```

Returns 1 (true) if this value type uses custom marshalling. Otherwise it returns 0 (false).

ValueDef::is_truncatable Attribute

// IDL

```
attribute boolean is_truncatable;
```

Returns 1 (true) if this value type inherits safely (supports truncation) from another value. Otherwise it returns 0 (false).

ValueDef::supported_interfaces Attribute

// IDL

```
attribute InterfaceDef supported_interfaces;
```

Lists the interfaces that this value type supports.

Exceptions

`BAD_PARAM`, minor code `5`

The `name` attribute of any object contained by the minor code 5 is raised if the `name` attribute of any object contained by this `ValueDef` conflicts with the `name` attribute of any object contained by any of the specified bases.

CORBA::ValueFactory

This describes the mapping of the IDL native type `CORBA::ValueFactory`. For native IDL types, each language mapping specifies how repository IDs are used to find the appropriate factory for an instance of a value type so that it may be created as it is unmarshaled off the wire.

```
// IDL in module CORBA
native ValueFactory;
```

Recall that value types allow objects to be passed by value which implies that the ORB must be able to create instances of your value type classes during unmarshaling. However, because the ORB cannot know about all potential value type classes, you must implement factory classes for those types and register them with the ORB so the ORB can create value instances when necessary.

The C++ mapping for the IDL `CORBA::ValueFactory` native type includes the following:

- The `ValueFactory` type which is a pointer to a `ValueFactoryBase` class.
- The `ValueFactoryBase` class which is the base class for all value type factory classes.

Just as your applications must provide concrete value type classes (see `CORBA::ValueBase`), your applications must also provide factory classes for those concrete classes.

If the ORB is unable to locate and use the appropriate factory, then a `MARSHAL` exception with a minor code is raised.

CORBA::ValueFactory Type

// C++ in namespace CORBA

```
typedef ValueFactoryBase* ValueFactory;
```

The `ValueFactory` is a pointer to a `ValueFactoryBase` class. Applications derive concrete factory classes from `ValueFactoryBase`, and register instances of those factory classes with the ORB via `ORB::register_value_factory()`.

See Also `CORBA::ValueFactoryBase`

```

CORBA::ORB::lookup_value_factory()
CORBA::ORB::register_value_factory()
CORBA::ORB::unregister_value_factory()

```

CORBA::ValueFactoryBase Class

When unmarshaling value instances, the ORB needs to be able to call up to the application to ask it to create those instances. Value instances are normally created via their type-specific value factories so as to preserve any invariants they might have for their state. However, creation for unmarshaling is different because the ORB has no knowledge of application-specific factories, and in fact in most cases may not even have the necessary arguments to provide to the type-specific factories.

To allow the ORB to create value instances required during unmarshaling, the `ValueFactoryBase` class provides the private `create_for_unmarshal()` pure virtual function. The function is private so that only the ORB, can invoke it. Your applications do not invoke `create_for_unmarshal()`, however, your derived classes must override `create_for_unmarshal()` and implement it such that it creates a new value instance and returns a pointer to the instance. The caller (in this case the ORB) assumes ownership of the returned instance. Once the ORB has created a value instance via the `create_for_unmarshal()` function, it uses the value data member modifier functions to set the state of the new value instance from the unmarshaled data.

```

// C++ in namespace CORBA
class ValueFactoryBase {
public:
    virtual [~ValueFactoryBase](#corbavaluefactorybase-class)();
    virtual void [_add_ref](#it_corbarefcountedlocalobjectnc-class)();
    virtual void [_remove_ref](#it_corbarefcountedlocalobjectnc-class)();
    static ValueFactory [_downcast](#messagingexceptionholder-value-type)
(ValueFactory vf);
protected:
    [ValueFactoryBase](#corbavaluefactorybase-class)();
private:
    virtual ValueBase* create_for_unmarshal() = 0;
    ...
};

```

See Also `CORBA::ValueBase`

`ValueFactoryBase::_add_ref()`

```
virtual void _add_ref();
```

Increases this object factory's reference count by one. The `ValueFactoryBase` uses reference counting to prevent itself from being destroyed while still in use by the application. A `ValueFactoryBase` object initially has a reference count of one.

See Also `CORBA::ValueFactoryBase::_remove_ref()`

```
ValueFactoryBase::_downcast()
```

```
static ValueFactory _downcast(
```

```
    ValueFactory vf
);
```

Returns a pointer to the type-specific factory object.

Parameters

```
vf
```

The original value factory object.

You can use `_downcast()` on the return type of the function `ORB::lookup_value_factory()` to obtain a pointer to a type-specific factory object. Memory management of the return value from `_downcast()` is *not* the responsibility of the caller, and thus you should not call `_remove_ref()` on it.

See Also `CORBA::ORB::lookup_value_factory()`

```
CORBA::ValueFactoryBase::_remove_ref()
```

```
ValueFactoryBase::_remove_ref()
```

```
virtual void _remove_ref();
```

Decreases this object factory's reference count by one, and if the resulting reference count equals zero, the object factory is destroyed.

See Also `CORBA::ValueFactoryBase::_add_ref()`

```
ValueFactoryBase::~ValueFactoryBase() Destructor
```

```
virtual ~ValueFactoryBase();
```

The default destructor.

See Also CORBA :: ValueFactoryBase :: ValueFactoryBase()

ValueFactoryBase::ValueFactoryBase() Constructor

protected:

```
ValueFactoryBase();
```

The default constructor.

See Also CORBA :: ValueFactoryBase :: ~ValueFactoryBase()

CORBA::ValueMemberDef Interface

The `ValueMemberDef` interface provides the definition of a value type member in the interface repository.

```
// IDL in module CORBA.
interface ValueMemberDef : Contained {
    readonly attribute TypeCode [type](#corbaattributedef-interface);
    attribute IDLType [type_def](#corbaattributedef-interface);
    attribute Visibility [access](#corbavaluememberdef-interface);
};
```

ValueMemberDef::access Attribute

// IDL

```
attribute Visibility access;
```

Contains an indicator of the visibility of an IDL value type state member. IDL value types can have state members that are either public or private.

ValueMemberDef::type Attribute

// IDL

```
readonly attribute TypeCode type;
```

Describes the type of this `ValueMemberDef`.

See Also CORBA::ValueMemberDef::type_def

ValueMemberDef::type_def Attribute

// IDL

```
attribute IDLType type_def;
```

Identifies the object that defines the IDL type of this `ValueMemberDef`. The same information is contained in the `type` attribute.

You can change the type of a `ValueMemberDef` by changing its `type_def` attribute. This also changes its `type` attribute.

See Also CORBA :: ValueMemberDef::type

CORBA::WString_var Class

The class `WString_var` implements the `_var` type for IDL wide strings required by the standard C++ mapping. The `WString_var` class contains a `char*` value and ensures that this is properly freed when a `WString_var` object is deallocated, for example when execution goes out of scope.

```
class WString_var {
public:
    [WString_var](#corbawstring_var-class)();
    [WString_var](#corbawstring_var-class)(char *p);
    [WString_var](#corbawstring_var-class)(const char *p);
    [WString_var](#corbawstring_var-class)(const WString_var &s);
    [~WString_var](#corbawstring_var-class)();
    WString_var & [operator=](#corbawstring_var-class)(char *p);
    WString_var & [operator=](#corbawstring_var-class)(const char *p);
    WString_var & [operator=](#corbawstring_var-class)(const WString_var &s);
    operator [char\*](#corbawstring_var-class)();
    operator const [char\*](#corbawstring_var-class)() const;
    const char* [in](#corbawstring_var-class)() const;
    char*& [inout](#corbawstring_var-class)();
    char*& [out](#corbawstring_var-class)();
    char* [_retn](#corbawstring_var-class)();
    char & [operator\[\]](#corbawstring_var-class)(ULong index);
    char [operator\[\]](#corbawstring_var-class)(ULong index) const;
};
```

`WString_var::char*()`

`operator char*();`

`operator const char*() const;`

Converts a `WString_var` object to a `char*`.

See Also `CORBA::WString_var::operator=()`

`WString_var::in()`

`const char* in() const;`

Returns the proper string for use as an input parameter.

See Also `CORBA::WString_var::out()`

```
CORBA::WString_var::inout()
CORBA::WString_var::_retn()
```

WString_var::inout()

char*& inout();

Returns the proper string for use as an inout parameter.

See Also CORBA::WString_var::in()

```
CORBA::WString_var::out()
CORBA::WString_var::_retn()
```

WString_var::operator=() Assignment Operators

WString_var &operator=(

```
    char *p
);
```

WString_var &operator=(

```
    const char *p
);
```

WString_var &operator=(

```
    const WString_var &s
);
```

Assignment operators allow you to assign values to a `WString_var` from a `char*` or from another `WString_var` type.

Parameters

<code>p</code>	A character string to assign to the <code>WString_var</code> .
<code>s</code>	A <code>WString_var</code> to assign to the <code>WString_var</code> .

See Also `CORBA::WString_var::char*()`

`WString_var::operator[]()` Subscript Operators

`char &operator[]()`

```
    ULong index
);
```

`char operator[]()`

```
    ULong index
) const;
```

Return the character at the given location of the string. Subscript operators allow access to the individual characters in the string.

Parameters

`index`

The index location in the string.

`WString_var::out()`

`char*& out();`

Returns the proper string for use as an output parameter.

See Also `CORBA::WString_var::in()`

```
CORBA::WString_var::inout()
CORBA::WString_var::_retn()
```

`WString_var::WString_var()` Constructors

```
WString_var();
```

The default constructor.

```
WString_var(
```

```
    char *p
);
```

```
WString_var(
```

```
    const char *p
);
```

Constructors that convert from a `char*` to a `WString_var`.

```
WString_var(
```

```
    const WString_var &s
);
```

The copy constructor.

Parameters

<code>p</code>	The character string to convert to a <code>WString_var</code> . The <code>WString_var</code> assumes ownership of the parameter.
<code>s</code>	The original <code>WString_var</code> that is copied.

See Also `CORBA::WString_var::~~WString_var()`

`WString_var::~~WString_var()` Destructor

```
~WString_var();
```

The destructor.

See Also `CORBA::WString_var::WString_var()`

```
WString_var::_retn()
```

```
char* _retn();
```

Returns the proper string for use as a method's return value.

See Also CORBA::WString_var::inout()

```
CORBA::WString_var::in()  
CORBA::WString_var::out()
```

CORBA::WstringDef Interface

Interface `WstringDef` represents a bounded IDL wide string type in the interface repository. A `WstringDef` object is anonymous, which means it is unnamed. Use `Repository::create_wstring()` to obtain a new `WstringDef` object.

Unbounded strings are primitive types represented with the `PrimitiveDef` interface. Use `Repository::get_primitive()` to obtain unbounded wide strings.

```
// IDL in module CORBA.
interface WstringDef : IDLType {
    attribute unsigned long [bound](#corbastringdef-interface);
};
```

The inherited `type` attribute is also described.

See Also `CORBA::IDLType`

```
CORBA::Repository::create_wstring()
CORBA::PrimitiveDef
CORBA::StringDef
```

`WstringDef::bound` Attribute

// IDL

```
attribute unsigned long bound;
```

Specifies the maximum number of characters in the wide string. This cannot be zero.

`WstringDef::type` Attribute

// IDL

```
readonly attribute TypeCode type;
```

The `type` attribute is inherited from interface `IDLType`. This attribute is a `tk_wstring` `TypeCode` that describes the wide string.

See Also CORBA :: IDLType::type

CosEventChannelAdmin Module

The `CosEventChannelAdmin` module specifies the interfaces and exceptions for connecting suppliers and consumers to an event channel. It also provides the methods for managing these connections.

It contains the following interfaces:

CosEventChannelAdmin Exceptions

exception `AlreadyConnected` {};

An `AlreadyConnected` exception is raised when an attempt is made to connect an object to the event channel when that object is already connected to the channel.

exception `TypeError` {};

The `TypeError` exception is raised when a proxy object tries to connect an object that does not support the proper typed interface.

CosEventComm Module

The `CosEventComm` module specifies the interfaces which define the event service consumers and suppliers.

CosEventComm Exceptions

`CosEventComm::Disconnected`

exception `Disconnected {};`

`Disconnected` is raised when an attempt is made to contact a proxy that has not been connected to an event channel.

CosNaming Overview

The `CosNaming` module contains all IDL definitions for the CORBA naming service. The interfaces consist of:

- [CosNaming::BindingIterator Interface](#)
- [CosNaming::NamingContext Interface](#)
- [CosNaming::NamingContextExt Interface](#)

Use the `NamingContext` and `BindingIterator` interfaces to access standard naming service functionality. Use the `NamingContextExt` interface to use URLs and string representations of names.

The rest of this chapter describes data types common to the `CosNaming` module that are defined directly within its scope.

CosNaming::Binding Structure

// IDL

```
struct Binding {
    Name binding_name;
    BindingType binding_type;
};
```

A `Binding` structure represents a single binding in a naming context. A `Binding` structure indicates the name and type of the binding:

<code>binding_name</code>	The full compound name of the binding.
<code>binding_type</code>	The binding type, indicating whether the name is bound to an application object or a naming context.

When browsing a naming graph in the naming service, an application can list the contents of a given naming context, and determine the name and type of each binding in it. To do this, the application calls the `NamingContext::list()` method on the target `NamingContext` object. This method returns a list of `Binding` structures.

See Also `CosNaming::BindingList`

```
CosNaming::BindingType
NamingContext::list()
```

CosNaming::BindingList Sequence

```
// IDL
```

```
typedef sequence<Binding> BindingList;
```

A sequence containing a set of Binding structures, each of which represents a single name binding.

An application can list the bindings in a given naming context using the NamingContext::list() method. An output parameter of this method returns a value of type BindingList.

See Also CosNaming::Binding

```
CosNaming::BindingType
NamingContext::list()
```

About Sequences

CosNaming::BindingType Enumeration

```
// IDL
```

```
enum BindingType {nobject, ncontext};
```

The enumerated type BindingType represents these two forms of name bindings:

nobject	Describes a name bound to an application object.
ncontext	Describes a name bound to a naming context in the naming service.

There are two types of name binding in the CORBA naming service: names bound to application objects, and names bound to naming contexts. Names bound to application objects cannot be used in a compound name, except as the last element in that name. Names bound to naming contexts can be used as any component of a compound name and allow you to construct a naming graph in the naming service.

Name bindings created using NamingContext::bind() or NamingContext::rebind() are nobject bindings.

Name bindings created using the operations `NamingContext :: bind_context()` or `NamingContext :: rebind_context()` are `ncontext` bindings.

See Also `CosNaming :: Binding`

```
CosNaming::BindingList
```

`CosNaming::Istring` Data Type

```
// IDL
```

```
typedef string Istring;
```

Type `Istring` is a place holder for an internationalized string format.

`CosNaming::Name` Sequence

```
// IDL
```

```
typedef sequence<NameComponent> Name;
```

A `Name` represents the name of an object in the naming service. If the object name is defined within the scope of one or more naming contexts, the name is a compound name. For this reason, type `Name` is defined as a sequence of name components.

Two names that differ only in the contents of the `kind` field of one `NameComponent` structure are considered to be different names.

Names with no components, that is sequences of length zero, are illegal.

See Also `CosNaming :: NameComponent`

[About Sequences](#)

`CosNaming::NameComponent` Structure

```
// IDL
```

```
struct NameComponent {
    Istring id;
    Istring kind;
};
```

A `NameComponent` structure represents a single component of a name that is associated with an object in the naming service. The members consist of:

<code>id</code>	The identifier that corresponds to the name of the component.
<code>kind</code>	The element that adds secondary type information to the component name.

The `id` field is intended for use purely as an identifier. The semantics of the `kind` field are application-specific and the naming service makes no attempt to interpret this value.

A name component is uniquely identified by the combination of both `id` and `kind` fields. Two name components that differ only in the contents of the `kind` field are considered to be different components.

See Also `CosNaming :: Name`

CosNaming::BindingIterator Interface

A `CosNaming.BindingIterator` object stores a list of name bindings and allows application to access the elements of this list.

The `NamingContext . list()` method obtains a list of bindings in a naming context. This method allows applications to specify a maximum number of bindings to be returned. To provide access to all other bindings in the naming context, the method returns an object of type `CosNaming.BindingIterator`.

```
// IDL
// In module CosNaming
interface BindingIterator {
    boolean [next_one](#cosnamingbindingiterator-interface)(
        out Binding b
    );
    boolean [next_n](#cosnamingbindingiterator-interface)(
        in unsigned long how_many,
        out BindingList bl
    );
    void [destroy](#cosnamingbindingiterator-interface)();
};
```

See Also `CosNaming :: NamingContext :: list()`

`BindingIterator :: destroy()`

// IDL

```
void destroy();
```

Deletes the `CosNaming::BindingIterator` object on which it is called.

`BindingIterator::next_n()`

```
// IDL
boolean next_n(
    in unsigned long how_many,
    out BindingList bl
);
```

Gets the next `how_many` elements in the list of bindings, subsequent to the last element obtained by a call to `next_n()` or `next_one()`. If the number of elements in the list is less than the value of `how_many`, all the remaining elements are obtained.

Returns `true` if one or more bindings are obtained, but returns `false` if no more bindings remain.

Parameters

<code>how_many</code>	The maximum number of bindings to be obtained in parameter <code>bl</code> .
<code>bl</code>	The list of name bindings.

See Also `CosNaming::BindingIterator::next_one()`

```
CosNaming::BindingList
```

`BindingIterator::next_one()`

```
// IDL
```

```
boolean next_one(
    out Binding b
);
```

Gets the next element in the list of bindings, subsequent to the last element obtained by a call to `next_n()` or `next_one()`.

Returns `true` if a binding is obtained, but returns `false` if no more bindings remain.

Parameters

```
b
```

The name binding.

See Also `CosNaming :: BindingIterator :: next_n()`

`CosNaming::Binding`

CosNaming::NamingContext Interface

The interface `CosNaming::NamingContext` provides operations to access the main features of the CORBA naming service, such as binding and resolving names. Name bindings are the associations the naming service maintains between an object reference and a useful name for that reference.

```

// IDL
// In module CosNaming
interface NamingContext {
    enum [NotFoundReason](#cosnamingnamingcontext-interface) {missing_node,
not_context, not_object};
    exception [NotFound](#cosnamingnamingcontext-interface) {
        NotFoundReason why;
        Name rest_of_name;
    };
    exception [CannotProceed](#cosnamingnamingcontext-interface) {
        NamingContext cxt;
        Name rest_of_name;
    };
    exception [InvalidName](#portableinterceptororbinitinfo-interface) {};
    exception [AlreadyBound](#cosnamingnamingcontext-interface) {};
    exception [NotEmpty](#cosnamingnamingcontext-interface) {};
    void [bind](#cosnamingnamingcontext-interface)(
        in Name n,
        in Object obj
    )
        raises (NotFound, CannotProceed, InvalidName, AlreadyBound);
    void [rebind](#cosnamingnamingcontext-interface)(
        in Name n,
        in Object obj
    )
        raises (NotFound, CannotProceed, InvalidName );
    void [bind_context](#cosnamingnamingcontext-interface)(
        in Name n,
        in NamingContext nc
    )
        raises (NotFound, CannotProceed, InvalidName, AlreadyBound);
    void [rebind_context](#cosnamingnamingcontext-interface)(
        in Name n,
        in NamingContext nc
    )
        raises (NotFound, CannotProceed, InvalidName );
    Object [resolve](#costradingregister-interface)(
        in Name n
    )
        raises (NotFound, CannotProceed, InvalidName );
    void [unbind](#cosnamingnamingcontext-interface)(
        in Name n
    )
        raises (NotFound, CannotProceed, InvalidName );
    NamingContext [new_context](#cosnamingnamingcontext-interface)();
    NamingContext [bind_new_context](#cosnamingnamingcontext-interface)(

```

```

        in Name n
    )
    raises (NotFound, CannotProceed, InvalidName, AlreadyBound);
void [destroy](#cosnamingbindingiterator-interface)() raises (NotEmpty);
void [list](#cosnamingnamingcontext-interface)(
    in unsigned long how_many,
    out BindingList bl,
    out BindingIterator bi
);
};

```

NamingContext::AlreadyBound Exception

// IDL

```
exception AlreadyBound {};
```

If an application calls a method that attempts to bind a name to an object or naming context, but the specified name has already been bound, the method throws an exception of type `AlreadyBound`.

The following methods can throw this exception:

```

bind()
bind_context()
bind_new_context()

```

NamingContext::bind()

// IDL

```

void bind(
    in Name n,
    in Object obj
)
    raises (NotFound, CannotProceed, InvalidName, AlreadyBound);

```

Creates a name binding, relative to the target naming context, between a name and an object.

Parameters

<code>n</code>	The name to be bound to the target object, relative to the naming context on which the method is called.
<code>obj</code>	The application object to be associated with the specified name.

If the name passed to this method is a compound name with more than one component, all except the last component are used to find the sub-context in which to add the name binding.

Exceptions The method can throw these exceptions:

```

NotFound
CannotProceed
InvalidName
AlreadyBound

```

The contexts associated with the components must already exist, otherwise the method throws a `NotFound` exception.

See Also `CosNaming::NamingContext::rebind()`

```
CosNaming::NamingContext::resolve()
```

`NamingContext::bind_context()`

```
// IDL
```

```

void bind_context(
    in Name n,
    in NamingContext nc
)
    raises (NotFound, CannotProceed, InvalidName, AlreadyBound);

```

Creates a binding, relative to the target naming context, between a name and another, specified naming context.

Parameters

<code>n</code>	The name to be bound to the target naming context, relative to the naming context on which the method is called. All but the final naming context specified in parameter <code>n</code> must already exist.
<code>nc</code>	The NamingContext object to be associated with the specified name. This object must already exist. To create a new NamingContext object, call <code>NamingContext : : new_context()</code> . The entries in naming context <code>nc</code> can be resolved using compound names.

This new binding can be used in any subsequent name resolutions. The naming graph built using `bind_context()` is not restricted to being a tree: it can be a general naming graph in which any naming context can appear in any other naming context.

Exceptions The method can throw these exceptions:

```

NotFound
CannotProceed
InvalidName
AlreadyBound

```

This method throws an `AlreadyBound` exception if the name specified by `n` is already in use.

See Also `CosNaming . NamingContext . bind_new_context()`

```

CosNaming.NamingContextnew_context()
CosNamingNamingContext.rebind_context()
CosNamingNamingContextresolve()

```

`NamingContext::bind_new_context()`

```
// IDL
```

```

NamingContext bind_new_context(
    in Name n
)
    raises (NotFound, CannotProceed, InvalidName, AlreadyBound);

```

Creates a new NamingContext object in the naming service and binds the specified name to it, relative to the naming context on which the method is called. The method returns a reference to the newly created NamingContext object.

Parameters

`n`

The name to be bound to the newly created naming context, relative to the naming context on which the method is called. All but the final naming context specified in parameter `n` must already exist.

This method has the same effect as a call to `NamingContext::new_context()` followed by a call to `NamingContext::bind_context()`.

The new name binding created by this method can be used in any subsequent name resolutions: the entries in the returned naming context can be resolved using compound names.

Exceptions The method can throw these exceptions:

```
NotFound
CannotProceed
InvalidName
AlreadyBound
```

This method throws an `AlreadyBound` exception if the name specified by `n` is already in use.

See Also `CosNaming::NamingContext::bind_context()`

```
CosNaming::NamingContext::new_context()
```

`NamingContext::CannotProceed` Exception

```
// IDL
```

```
exception CannotProceed {
    NamingContext cxt;
    Name rest_of_name;
};
```

If a naming service method fails due to an internal error, the method throws a `CannotProceed` exception.

A `CannotProceed` exception consists of two member fields:

<code>cxt</code>	The NamingContext object associated with the component at which the method failed.
<code>rest_of_name</code>	The remainder of the compound name, after the binding for the component at which the method failed.

The application might be able to use the information returned in this exception to complete the method later. For example, if you use a naming service federated across several hosts and one of these hosts is currently unavailable, a naming service method might fail until that host is available again.

The following methods can throw this exception:

```
bind()
bind_context()
bind_new_context()
rebind()
rebind_context()
resolve()
unbind()
```

See Also `CosNaming::Name`

`CosNaming::NamingContext`

`NamingContext::destroy()`

```
// IDL
```

```
void destroy()
    raises (NotEmpty);
```

Deletes the NamingContext object on which it is called. Before deleting a NamingContext in this way, ensure that it contains no bindings.

To avoid leaving name bindings with no associated objects in the naming service, call `NamingContext . unbind()` to unbind the context name before calling `destroy()`. See `resolve()` for information about the result of resolving names of context objects that no longer exist.

Exceptions


```
NamingContext::NotEmpty
```

`destroy()` is called on a NamingContext that contains existing bindings.

See Also `CosNaming::NamingContext::resolve()`

```
CosNaming::NamingContext::unbind()
```

NamingContext::InvalidName Exception

```
// IDL
```

```
exception InvalidName {};
```

If a method receives an `in` parameter of type `CosNaming . Name` for which the sequence length is zero, the method throws an `InvalidName` exception.

The following methods can throw this exception:

```
bind()
bind_context()
bind_new_context()
rebind()
rebind_context()
resolve()
unbind()
```

NamingContext::list()

```
// IDL
```

```
void list(
    in unsigned long how_many,
    out BindingList bl,
    out BindingIterator bi
);
```

Gets a list of the name bindings in the naming context on which the method is called.

Parameters

<code>how_many</code>	The maximum number of bindings to be obtained in the <code>BindingList</code> parameter, <code>bl</code> .
<code>bl</code>	The list of bindings contained in the naming context on which the method is called.
<code>bi</code>	A <code>BindingIterator</code> object that provides access to all remaining bindings contained in the naming context on which the method is called. If the naming context contains more than the requested number of bindings, the <code>BindingIterator</code> contains the remaining bindings. If the naming context does not contain any additional bindings, the parameter <code>bi</code> is a nil object reference.

See Also `CosNaming :: BindingIterator`

```
CosNaming::BindingList
```

`NamingContext::new_context()`

```
// IDL
```

```
NamingContext new_context();
```

Creates a new `NamingContext` object in the naming service, without binding a name to it. The method returns a reference to the newly created `NamingContext` object.

After creating a naming context with this method, your application can bind a name to it by calling `NamingContext :: bind_context()`. There is no relationship between this object and the `NamingContext` object on which the application call the method.

See Also `CosNaming :: NamingContext :: bind_context()`

```
CosNaming::NamingContext::bind_new_context()
```

`NamingContext::NotEmpty` Exception

```
// IDL
```

```
exception NotEmpty {};
```

An application can call the `NamingContext :: destroy()` method to delete a naming context object in the naming service. For this method to succeed, the naming context must contain no bindings. If bindings exist in the naming context, the method throws a `NotEmpty` exception.

NamingContext::NotFound Exception

```
// IDL
```

```
exception NotFound {
    NotFoundReason why;
    Name rest_of_name;
};
```

Several methods in the interface `CosNaming :: NamingContext` require an existing name binding to be passed as an input parameter. If such a method receives a name binding that it determines is invalid, the method throws a `NotFound` exception. This exception contains two member fields:

<code>why</code>	The reason why the name binding is invalid.
<code>rest_of_name</code>	The remainder of the compound name following the invalid portion of the name that the method determined to be invalid.

The following methods can throw this exception:

```
bind()
bind_context()
bind_new_context()
rebind()
rebind_context()
resolve()
unbind()
```

See Also `CosNaming :: NamingContext :: NotFoundReason`

NamingContext::NotFoundReason Enumeration

```
// IDL
```

```
enum NotFoundReason {missing_node, not_context, not_object};
```

If an method throws a NotFound exception, a value of enumerated type `NotFoundReason` indicates the reason why the exception was thrown. The reasons consists of:

<code>missing_node</code>	The component of the name passed to the method did not exist in the naming service.
<code>not_context</code>	The method expected to receive a name that is bound to a naming context, for example using <code>NamingContext :: bind_context()</code> , but the name received did not satisfy this requirement.
<code>not_object</code>	The method expected to receive a name that is bound to an application object, for example using <code>NamingContext :: bind()</code> , but the name received did not satisfy this requirement.

See Also `CosNaming :: NamingContext :: NotFound`

`NamingContext::rebind()`

```
// IDL
```

```
void rebind(
    in Name n,
    in Object obj
)
    raises (NotFound, CannotProceed, InvalidName);
```

Creates a binding between an object and a name that is already bound in the target naming context. The previous name is unbound and the new binding is created in its place.

Parameters

<code>n</code>	The name to be bound to the specified object, relative to the naming context on which the method is called.
<code>obj</code>	The application object to be associated with the specified name.

As is the case with `NamingContext :: bind()`, all but the last component of a compound name must exist, relative to the naming context on which you call the method.

ExceptionsThe method can throw these exceptions:

```
NotFound
CannotProceed
InvalidName
```

See Also`CosNaming :: NamingContext :: bind()`

```
CosNaming::NamingContext::resolve()
```

`NamingContext::rebind_context()`

```
// IDL
```

```
void rebind_context(
    in Name n,
    in NamingContext nc
)
    raises (NotFound, CannotProceed, InvalidName);
```

The `rebind_context()` method creates a binding between a naming context and a name that is already bound in the context on which the method is called. The previous name is unbound and the new binding is made in its place.

Parameters

<code>n</code>	The name to be bound to the specified naming context, relative to the naming context on which the method is called.
<code>nc</code>	The naming context to be associated with the specified name.

As is the case for `NamingContext :: bind_context()`, all but the last component of a compound name must name an existing `NamingContext`.

ExceptionsThe method can throw these exceptions:

```

NotFound
CannotProceed
InvalidName

```

See Also `CosNaming :: NamingContext :: bind_context()`

```
CosNaming::NamingContext::resolve()
```

`NamingContext::resolve()`

```
// IDL
```

```

Object resolve(
    in Name n
)
    raises (NotFound, CannotProceed, InvalidName);

```

Returns the object reference that is bound to the specified name, relative to the naming context on which the method was called. The first component of the specified name is resolved in the target naming context.

Parameters

```
n
```

The name to be resolved, relative to the naming context on which the method is called.

An IDL `Object` maps to the type `CORBA::Object_ptr` in C++. You must narrow the result to the appropriate type before using it in your application.

Exceptions The method can throw these exceptions:

```

NotFound
CannotProceed
InvalidName

```

If the name `n` refers to a naming context, it is possible that the corresponding `NamingContext` object no longer exists in the naming service. For example, this could happen if you call `NamingContext::destroy()` to destroy a context without first unbinding the context name. In this case, `resolve()` throws a CORBA system exception.

See Also `CosNaming::NamingContext::CannotProceed`

```

CosNaming::NamingContext::InvalidName
CosNaming::NamingContext::NotFound

```

`NamingContext::unbind()`

```
// IDL
```

```

void unbind(
    in Name n
)
    raises (NotFound, CannotProceed, InvalidName);

```

Removes the binding between a specified name and the object associated with it.

Parameters

```
n
```

The name to be unbound in the naming service, relative to the naming context on which the method is called.

Unbinding a name does not delete the application object or naming context object associated with the name. For example, if you want to remove a naming context completely from the naming service, you should first unbind the corresponding name, then delete the `NamingContext` object by calling `NamingContext::destroy()`.

Exceptions The method can throw these exceptions:

```
NotFound  
CannotProceed  
InvalidName
```

See Also `CosNaming :: NamingContext :: CannotProceed`

```
CosNaming::NamingContext::destroy()  
CosNaming::NamingContext::InvalidName  
CosNaming::NamingContext::NotFound
```


CosNaming::NamingContextExt Interface

The `NamingContextExt` interface, derived from `NamingContext`, provides the capability for applications to use strings and Uniform Resource Locator (URL) strings to access names in the naming service.

```
// IDL
// In module CosNaming
interface NamingContextExt: NamingContext {
    typedef string [StringName](#cosnamingnamingcontextext-interface);
    typedef string [Address](#cosnamingnamingcontextext-interface);
    typedef string [URLString](#cosnamingnamingcontextext-interface);
    StringName [to_string](#cosnamingnamingcontextext-interface)(
        in Name n
    )
        raises(InvalidName);
    Name [to_name](#cosnamingnamingcontextext-interface)(
        in StringName sn
    )
        raises(InvalidName);
    exception [InvalidAddress](#cosnamingnamingcontextext-interface) {};
    URLString [to_url](#cosnamingnamingcontextext-interface)(
        in Address addr,
        in StringName sn
    )
        raises(InvalidAddress, InvalidName);
    Object [resolve_str](#cosnamingnamingcontextext-interface)(
        in StringName n
    )
        raises(NotFound, CannotProceed, InvalidName, AlreadyBound);
};
```

NameContextExt::Address Data Type

// IDL

```
typedef string Address;
```

A URL address component is a host name optionally followed by a port number (delimited by a colon). Examples include the following:

```
my_backup_host.555xyz.com:900
myhost.xyz.com
myhost.555xyz.com
```

NameContextExt::InvalidAddress Exception

// IDL

```
exception InvalidAddress {};
```

The to_url() method throws an `InvalidAddress` exception when an invalid URL address component is passed to it.

See Also CosNaming :: NamingContextExt :: to_url()

NameContextExt::resolve_str()

// IDL

```
Object resolve_str(
    in StringName sn
)
    raises(NotFound, CannotProceed, InvalidName, AlreadyBound);
```

Resolves a naming service name to the object it represents in the same manner as NamingContext :: resolve(). This method accepts a string representation of a name as an argument instead of a Name data type.

Parameters

```
sn
```

String representation of a name to be resolved to an object reference.

Exceptions The method can throw these exceptions:

```

NotFound
CannotProceed
InvalidName
AlreadyBound

```

NameContextExt::StringName Data Type

// IDL

```
typedef string StringName;
```

A string representation of an object's name in the naming service.

See Also CosNaming::Name

NameContextExt::to_name()

// IDL

```

Name to_name(
    in StringName sn
)
    raises(InvalidName);

```

Returns a naming service Name given a string representation of it.

Parameters

```
sn
```

String representation of a name in the naming service to be converted to a Name data type.

Exceptions

```
InvalidName
```

The string name is syntactically malformed or violates an implementation limit.

NameContextExt::to_string()

// IDL

```
StringName to_string(
    in Name n
)
    raises(InvalidName);
```

Returns a string representation of a naming service Name data type.

Parameters

n

The naming service Name to be converted to a string.

Exceptions

InvalidName

Name is invalid.

NameContextExt::to_url()

// IDL

```
URLString to_url(
    in Address addr,
    in StringName sn
)
    raises(InvalidAddress, InvalidName);
```

Returns a fully formed URL string, given a URL address component and a string representation of a name. It adds the necessary escape sequences to create a valid URLString.

Parameters

addr	The URL address component. An empty address means the local host.

<code>sn</code>	The string representation of a naming service name. An empty string is allowed.

ExceptionsThe method can throw these exceptions:

```
InvalidAddress
InvalidName
```

NameContextExt::URLString Data Type

// IDL

```
typedef string URLString;
```

A valid Uniform Resource Locator (URL) string. URL strings describe the location of a resource that is accessible via the Internet.

CosNotification Module

The `CosNotification` module defines the structured event data type, and a data type used for transmitting sequences of structured events. In addition, this module provides constant declarations for each of the standard quality of service (QoS) and administrative properties supported by the notification service. Some properties also have associated constant declarations to indicate their possible settings. Finally, administrative interfaces are defined for managing sets of QoS and administrative properties.

CosNotification Data Types

CosNotification::StructuredEvent Data Structure

```
//IDL
struct EventType {
    string domain_name;
    string type_name;
};
struct FixedEventHeader {
    EventType event_type;
    string event_name;
};
struct EventHeader {
    FixedEventHeader fixed_header;
    OptionalHeaderFields variable_header;
};
struct StructuredEvent {
    EventHeader header;
    FilterableEventBody filterable_data;
    any remainder_of_body;
}; // StructuredEvent
```

The `StructuredEvent` data structure defines the fields which make up a structured event. A detailed description of structured events is provided in the *CORBA Notification Service Guide*.

CosNotification::EventTypeSeq Type

```
//IDL
struct EventType {
    string domain_name;
    string type_name;
};
typedef sequence <EventType> EventTypeSeq
```

CosNotification::EventBatch Type

The `CosNotification` module defines the `EventBatch` data type as a sequence of structured events. The `CosNotifyComm` module defines interfaces supporting the transmission and receipt the `EventBatch` data type.

QoS and Administrative Constant Declarations

The `CosNotification` module declares several constants related to QoS properties, and the administrative properties of event channels.

```

// IDL in CosNotification module
const string EventReliability = "EventReliability";
const short BestEffort = 0;
const short Persistent = 1;
const string ConnectionReliability = "ConnectionReliability";
// Can take on the same values as EventReliability
const string Priority = "Priority";
const short LowestPriority = -32767;
const short HighestPriority = 32767;
const short DefaultPriority = 0;
const string StartTime = "StartTime";
// StartTime takes a value of type TimeBase::UtcT
const string StopTime = "StopTime";
// StopTime takes a value of type TimeBase::UtcT
const string Timeout = "Timeout";
// Timeout takes on a value of type TimeBase::TimeT
const string OrderPolicy = "OrderPolicy";
const short AnyOrder = 0;
const short FifoOrder = 1;
const short PriorityOrder = 2;
const short DeadlineOrder = 3;
const string DiscardPolicy = "DiscardPolicy";
// DiscardPolicy takes on the same values as OrderPolicy, plus
const short LifoOrder = 4;
const string MaximumBatchSize = "MaximumBatchSize";
// MaximumBatchSize takes on a value of type long
const string PacingInterval = "PacingInterval";
// PacingInterval takes on a value of type TimeBase::TimeT
const string StartTimeSupported = "StartTimeSupported";
// StartTimeSupported takes on a boolean value
const string StopTimeSupported = "StopTimeSupported";
// StopTimeSupported takes on a boolean value
const string MaxEventsPerConsumer = "MaxEventsPerConsumer";
// MaxEventsPerConsumer takes on a value of type long

```


QoS and Admin Data Types

The `CosNotification` module defines several data types related to QoS properties, and the administrative properties of event channels.

`CosNotification::PropertyName` Type

```
typedef string PropertyName;
```

`PropertyName` is a `string` holding the name of a QoS or an Admin property.

`CosNotification::PropertyValue` Type

```
typedef any PropertyValue;
```

`PropertyValue` is an `any` holding the setting of QoS or Admin properties.

`CosNotification::PropertySeq` Type

```
//IDL in CosNotification module
struct Property
{
    [PropertyName](#costrading-data-types) name;
    [PropertyValue](#costrading-data-types) value;
};
typedef sequence <Property> PropertySeq;
```

`PropertySeq` is a set of name-value pairs that encapsulate QoS or Admin properties and their values.

Members

<code>name</code>	A <code>string</code> identifying the QoS or Admin property.
<code>value</code>	An <code>Any</code> containing the setting of the QoS or Admin property.

`CosNotification::QoSProperties` Type

```
typedef [PropertySeq](#costrading-data-types) QoSProperties;
```

`QoSProperties` is a name-value pair of [PropertySeq](#) used to specify QoS properties.

CosNotification::AdminProperties Type

```
typedef [PropertySeq](#costrading-data-types) AdminProperties;
```

`AdminProperties` is a name-value pair of [PropertySeq](#) used to specify Admin properties.

CosNotification::QoSError_code Enum

```
enum QoSError_code
{
    UNSUPPORTED_PROPERTY,
    UNAVAILABLE_PROPERTY,
    UNSUPPORTED_VALUE,
    UNAVAILABLE_VALUE,
    BAD_PROPERTY,
    BAD_TYPE,
    BAD_VALUE
};
```

`QoSError_code` specifies the error codes for [UnsupportedQoS](#) and [UnsupportedAdmin](#) exceptions. The return codes are:

<code>UNSUPPORTED_PROPERTY</code>	Orbix does not support the property for this type of object
<code>UNAVAILABLE_PROPERTY</code>	This property cannot be combined with existing QoS properties.
<code>UNSUPPORTED_VALUE</code>	The value specified for this property is invalid for the target object.
<code>UNAVAILABLE_VALUE</code>	The value specified for this property is invalid in the context of other QoS properties currently in force.
<code>BAD_PROPERTY</code>	The property name is unknown.
<code>BAD_TYPE</code>	The type supplied for the value of this property is incorrect.

BAD_VALUE

The value specified for this property is illegal.

CosNotification::PropertyErrorSeq Type

```
// IDL from CosNotification module
struct PropertyRange
{
    [PropertyValue](#costrading-data-types) low_val;
    [PropertyValue](#costrading-data-types) high_val;
};
struct PropertyError
{
    [QoSError_code](#qos-and-admin-data-types) code;
    [PropertyName](#costrading-data-types) name;
    PropertyRange available_range;
};
typedef sequence <PropertyError> PropertyErrorSeq;
```

A `PropertyErrorSeq` is returned when [UnsupportedQoS](#) or [UnsupportedAdmin](#) is raised. It specifies a sequence containing the reason for the exception, the property that caused it, and a range of valid settings for the property.

CosNotification::NamedPropertyRangeSeq Type

```
struct NamedPropertyRange
{
    [PropertyName](#costrading-data-types) name;
    PropertyRange range;
};
typedef sequence <NamedPropertyRange> NamedPropertyRangeSeq;
```

Specifies a range of values for the named property.

QoS and Admin Exceptions

The `CosNotification` module defines two exceptions related to QoS properties, and the administrative properties of event channels.

`CosNotification::UnsupprtedQoS`

```
exception UnsupportedQoS { [PropertyErrorSeq] (#qos-and-admin-data-types)
  qos_err; };
```

Raised when setting QoS properties on notification channel objects, or when validating QoS properties. It returns with a [PropertyErrorSeq](#) specifying the reason for the exception, which property was invalid, and a list of valid settings for the QoS property.

`CosNotification::UnsupportedAdmin`

```
exception UnsupportedAdmin { [PropertyErrorSeq] (#qos-and-admin-data-types)
  admin_err; };
```

Raised when setting Admin properties on notification channels. It returns with a [PropertyErrorSeq](#) specifying the reason for the exception, which property was invalid, and a list of valid settings for the property.

CosNotification::AdminPropertiesAdmin Interface

```
//IDL
interface AdminPropertiesAdmin {
    [AdminProperites](#qos-and-admin-data-types) get_admin();
    void set_admin (in [AdminProperites](#qos-and-admin-data-types) admin)
        raises ( [UnsupportedAdmin](#qos-and-admin-exceptions));
};
```

The `AdminPropertiesAdmin` interface defines operations enabling clients to manage the values of administrative properties. This interface is an abstract interface which is inherited by the Event Channel interfaces defined in the `CosNotifyChannelAdmin` module.

`AdminPropertiesAdmin::get_admin()`

```
[AdminProperites](#qos-and-admin-data-types) get_admin();
```

Returns a sequence of name-value pairs encapsulating the current administrative settings for the target channel.

`AdminPropertiesAdmin::set_admin()`

```
void set_admin (in [AdminProperites](#qos-and-admin-data-types) admin)
    raises ( [UnsupportedAdmin](#qos-and-admin-exceptions));
```

Sets the specified administrative properties on the target object.

Parameters

`admin`

A sequence of name-value pairs encapsulating administrative property settings.

Exceptions

[UnsupportedAdmin] (#qos-and-admin-exceptions)

Raised if If any of the requested settings cannot be satisfied by the target object.

CosNotification::QoSAdmin Interface

```
//IDL
interface QoSAdmin {
    QoSProperties get_qos();
    void set_qos ( in [QoSProperties](#qos-and-admin-data-types) qos)
        raises ( [UnsupportedQoS](#qos-and-admin-exceptions) );
    void validate_qos (
        in [QoSProperties](#qos-and-admin-data-types) required_qos,
        out [NamedPropertyRangeSeq](#qos-and-admin-data-types)
        available_qos )
        raises ( [UnsupportedQoS](#qos-and-admin-exceptions) );
}
```

The `QoSAdmin` interface defines operations enabling clients to manage the values of QoS properties. It also defines an operation to verify whether or not a set of requested QoS property settings can be satisfied, along with returning information about the range of possible settings for additional QoS properties. `QoSAdmin` is an abstract interface which is inherited by the proxy, admin, and event channel interfaces defined in the `CosNotifyChannelAdmin` module.

`QoSAdmin::get_qos()`

```
[QoSProperties](#qos-and-admin-data-types) get_qos();
```

Returns a sequence of name-value pairs encapsulating the current quality of service settings for the target object (which could be an event channel, admin, or proxy object).

`QoSAdmin::set_qos()`

```
void set_qos ( in [QoSProperties](#qos-and-admin-data-types) qos)
    raises ( [UnsupportedQoS](#qos-and-admin-exceptions) );
```

Sets the specified QoS properties on the target object (which could be an event channel, admin, or proxy object).

Parameters

`qos`

A sequence of name-value pairs encapsulating quality of service property settings

Exceptions

[UnsupportedQoS] (#qos-and-admin-exceptions)

The implementation of the target object is incapable of supporting some of the requested quality of service settings, or one of the requested settings are in conflict with a QoS property defined at a higher level of the object hierarchy.

QoSAdmin::validate_qos()

```
void validate_qos (
    in [QoSProperties] (#qos-and-admin-data-types) required_qos,
    out [NamedPropertyRangeSeq] (#qos-and-admin-data-types) available_qos )
    raises ( [UnsupportedQoS] (#qos-and-admin-exceptions) );
```

Enables a client to discover if the target object is capable of supporting a set of QoS settings. If all requested QoS property value settings can be satisfied by the target object, the operation returns successfully (without actually setting the QoS properties on the target object).

Parameters

<code>required_qos</code>	A sequence of QoS property name-value pairs specifying a set of QoS settings.
<code>available_qos</code>	An output parameter that contains a sequence of <code>NamedPropertyRange</code> . Each element in this sequence includes the name of an additional QoS property supported by the target object which could have been included on the input list and resulted in a successful return from the operation, along with the range of values that would have been acceptable for each such property.

Exceptions

[UnsupportedQoS] (#qos-and-admin-exceptions)

Raised if any of the requested settings cannot be satisfied by the target object.

CosNotifyChannelAdmin Module

The `CosNotifyChannelAdmin` module specifies the interfaces, exceptions, and data types for connecting suppliers and consumers to an event channel. It also provides the methods for managing these connections.

CosNotifyChannelAdmin Data Types

`CosNotifyChannelAdmin` specifies data types that facilitate the connection of clients to an event channel. The data types specify the proxy type used by a client, the type of events a client can send or receive, and how the clients receive subscription information. Several data types identify the client and the event channel objects responsible for managing it.

`CosNotifyChannelAdmin::ProxyType` Enum

```
// IDL in CosNotifyChannelAdmin
enum ProxyType
{
    PUSH_ANY,
    PULL_ANY,
    PUSH_STRUCTURED,
    PULL_STRUCTURED,
    PUSH_SEQUENCE,
    PULL_SEQUENCE,
    PUSH_TYPED,
    PULL_TYPED
}
```

Specifies the type of proxy used by a client to connect to an event channel. The type of proxy must match the type of client it connects to the channel. For example, a structured push consumer must use a `PUSH_STRUCTURED` proxy.

`CosNotifyChannelAdmin::ObtainInfoMode` Enum

```
// IDL in CosNotifyChannelAdmin Module
enum ObtainInfoMode
{
    ALL_NOW_UPDATES_ON,
    ALL_NOW_UPDATES_OFF,
    NONE_NOW_UPDATES_ON,
    NONE_NOW_UPDATES_OFF
}
```

Specifies how the client wishes to be notified of changes in subscription/publication information. The values have the following meanings:

<code>ALL_NOW_UPDATE S_ON</code>	Returns the current subscription/publication information and enables automatic updates.
<code>ALL_NOW_UPDATE S_OFF</code>	Returns the current subscription/publication information and disables automatic updates.
<code>NONE_NOW_UPDAT ES_ON</code>	Enables automatic updates of subscription/publication information without returning the current information.
<code>NON_NOW_UPDATE S_OFF</code>	Disables automatic updates of subscription/publication information without returning the current information.

CosNotifyChannelAdmin::ProxyID Type

```
typedef long ProxyID;
```

Specifies the ID of a proxy in an event channel.

CosNotifyChannelAdmin::ProxyIDSeq Type

```
typedef sequence <ProxyID> ProxyIDSeq
```

Contains a list of `ProxyID` values.

CosNotifyChannelAdmin::ClientType Enum

```
// IDL in CosNotifyChannelAdmin
enum ClientType
{
    ANY_EVENT,
    STRUCTURED_EVENT,
    SEQUENCE_EVENT
}
```

Specifies the type of messages a client handles. The values have the following meanings:

<code>ANY_EVENT</code>	The client sends or receives messages as an <code>Any</code> . Consumers set with <code>ANY_EVENT</code> can receive structured messages, but the consumer is responsible for decoding it.
<code>STRUCTURED_EVENT</code>	The client sends or receives messages as a <code>CosNotification::StructuredEvent</code> .
<code>SEQUENCE_EVENT</code>	The client sends or receives messages as a <code>CosNotification::EventBatch</code> .

CosNotifyChannelAdmin::InterFilterGroupOperator Enum

```
// IDL in CosNotifyChannelAdmin
enum InterFilterGroupOperator
{
    AND_OP,
    OR_OP
}
```

Specifies the relationship between filters set on an admin object and the filters set on its associated filter objects. The values have the following meanings:

<code>AND_OP</code>	Events must pass at least one filter in both the proxy and the admin in order to be forwarded along the delivery path.
<code>OR_OP</code>	Events must pass at least one filter in either the proxy or the admin in order to be forwarded along the delivery path.

CosNotifyChannelAdmin::AdminID Type

```
typedef long AdminID;
```

Specifies the ID of an admin object in an event channel.

CosNotifyChannelAdmin::AdminIDSeq

```
typedef sequence <AdminID> AdminIDSeq;
```

Contains a list of IDs for admin objects in an event channel.

CosNotifyChannelAdmin::AdminLimit Type

```
//IDL in CosNotifyChannelAdmin
struct AdminLimit
{
    CosNotification::PropertyName name;
    CosNotification::PropertyValue value;
}
```

Specifies the administration property whose limit is exceeded and the value of that property. It is returned by an [CosNotifyChannelAdmin::AdminLimitExceeded](#) exception.

Members

name	Name of the admin property that caused the exception.
value	The current value of the property.

CosNotifyChannelAdmin::ChannelID Type

```
typedef long ChannelID;
```

Specifies an event channel in the notification service.

CosNotifyChannelAdmin::ChannelIDSeq Type

```
typedef sequence <ChannelID> ChannelIDSeq;
```

Contains a list of IDs for event channels in the notification service.

CosNotifyChannelAdmin Exceptions

The `CosNotifyChannelAdmin` module defines exceptions to handle errors generated while managing client connections to an event channel.

`CosNotifyChannelAdmin::ConnectionAlreadyActive` Exception

```
exception ConnectionAlreadyActive{};
```

Raised when attempting to resume an already active connection between a client and an event channel.

`CosNotifyChannelAdmin::ConnetionAlreadyInactive` Exception

```
exception ConnectionAlreadyInactive{};
```

Raised when attempting to suspend a connection between a client and an event channel while it is suspended.

`CosNotifyChannelAdmin::NotConnected` Exception

```
exception NotCennected{};
```

Raised when attempting to suspend or resume a connection between a client and an event channel when the client is not connected to the channel.

`CosNotifyChannelAdmin::AdminNotFound` Exception

```
exception AdminNotFound{};
```

Raised when the specified Admin ID cannot be resolved.

`CosNotifyChannelAdmin::ProxyNotFound` Exception

```
exception ProxyNotFound{};
```

Raised when the specified proxy ID cannot be resolved.

CosNotifyChannelAdmin::AdminLimitExceeded Exception

```
exception AdminLimitExceeded{ [AdminLimit](#cosnotifychanneladmin-data-types)
  admin_property_err };
```

Raised when an attempt to obtain a proxy and the new connection will put the event channel over the limit set by its `MaxConsumers` or `MaxSuppliers` setting.

The returned [AdminLimit](#) specifies which property caused the exception and the current setting of the property.

CosNotifyChannelAdmin::ChannelNotFound Exception

```
exception ChannelNotFound{};
```

Raised when the specified channel ID cannot be resolved.

CosNotifyChannelAdmin::ConsumerAdmin Interface

```

//IDL
interface ConsumerAdmin :
    CosNotification::QoSAdmin,
    CosNotifyComm::NotifySubscribe,
    CosNotifyFilter::FilterAdmin,
    CosEventChannelAdmin::ConsumerAdmin
{
    readonly attribute [AdminID](#cosnotifychanneladmin-data-types) MyID;
    readonly attribute EventChannel MyChannel;
    readonly attribute [InterFilterGroupOperator](#cosnotifychanneladmin-
data-types) MyOperator;
    attribute CosNotifyFilter::MappingFilter priority_filter;
    attribute CosNotifyFilter::MappingFilter lifetime_filter;
    readonly attribute [ProxyIDSeq](#cosnotifychanneladmin-data-types)
pull_suppliers;
    readonly attribute [ProxyIDSeq](#cosnotifychanneladmin-data-types)
push_suppliers;
    [ProxySupplier](../cosnotifychanneladminproxysupplier_interface/
cosnotifychanneladminproxysupplier_interface.md) [get_proxy_supplier]
(#cosnotifychanneladminconsumeradmin-interface) ( in [ProxyID]
(#cosnotifychanneladmin-data-types) proxy_id )
        raises ( [ProxyNotFound](#cosnotifychanneladmin-exceptions) );
    [ProxySupplier](../cosnotifychanneladminproxysupplier_interface/
cosnotifychanneladminproxysupplier_interface.md)
obtain_notification_pull_supplier (
        in [ClientType](#cosnotifychanneladmin-data-types) ctype,
        out [ProxyID](#cosnotifychanneladmin-data-types) proxy_id)
        raises ( [AdminLimitExceeded](#cosnotifychanneladmin-exceptions) );
    [ProxySupplier](../cosnotifychanneladminproxysupplier_interface/
cosnotifychanneladminproxysupplier_interface.md)
[obtain_notification_push_supplier](#cosnotifychanneladminconsumeradmin-
interface) (
        in [ClientType](#cosnotifychanneladmin-data-types) ctype,
        out [ProxyID](#cosnotifychanneladmin-data-types) proxy_id)
        raises ( [AdminLimitExceeded](#cosnotifychanneladmin-exceptions) );
    [ProxySupplier](../cosnotifychanneladminproxysupplier_interface/
cosnotifychanneladminproxysupplier_interface.md)
obtain_txn_notification_pull_supplier (
        in [ClientType](#cosnotifychanneladmin-data-types) ctype,
        out [ProxyID](#cosnotifychanneladmin-data-types) proxy_id)
        raises ( [AdminLimitExceeded](#cosnotifychanneladmin-exceptions) );
    void destroy();
};

```


The **ConsumerAdmin** interface defines the behavior of objects that create and manage lists of proxy supplier objects within an event channel. A event channel can have any number of **ConsumerAdmin** instances associated with it. Each instance is responsible for creating and managing a list of proxy supplier objects that share a common set of QoS property settings, and a common set of filter objects. This feature enables clients to group proxy suppliers within a channel into groupings that each support a set of consumers with a common set of QoS requirements and event subscriptions.

The ConsumerAdmin interface inherits the QoSAdmin interface defined within CosNotification, enabling each ConsumerAdmin to manage a set of QoS property settings. These QoS property settings are assigned as the default QoS property settings for any proxy supplier object created by a ConsumerAdmin. The ConsumerAdmin interface also inherits from the FilterAdmin interface defined within CosNotifyFilter. This enables each ConsumerAdmin to maintain a list of filters. These filters encapsulate subscriptions that apply to all proxy supplier objects that have been created by a given ConsumerAdmin.

The ConsumerAdmin interface also inherits from the NotifySubscribe interface defined in CosNotifyComm. This inheritance enables a ConsumerAdmin to be registered as the callback object for notification of subscription changes made on filters. This optimizes the notification of a group of proxy suppliers that have been created by the same ConsumerAdmin of changes to these shared filters.

The ConsumerAdmin interface also inherits from `CosEventChannelAdmin::ConsumerAdmin`. This inheritance enables clients to use the ConsumerAdmin interface to create pure OMG event service style proxy supplier objects. Proxy supplier objects created in this manner do not support configuration of QoS properties, and do not have associated filters. Proxy suppliers created through the inherited `CosEventChannelAdmin::ConsumerAdmin` interface do not have unique identifiers associated with them, whereas proxy suppliers created by operations supported by the ConsumerAdmin interface do have unique identifiers.

The ConsumerAdmin interface supports a read-only attribute that maintains a reference to the EventChannel instance that created it. The ConsumerAdmin interface also supports a read-only attribute that contains a unique numeric identifier which is assigned event channel upon creation of a `ConsumerAdmin` instance. This identifier is unique among all ConsumerAdmin instances created by a given channel.

As described above, a ConsumerAdmin can maintain a list of filters that are applied to all proxy suppliers it creates. Each proxy supplier can also support a list of filters that apply only to the proxy. When combining these two lists during the evaluation of a given event, either **AND** or **OR** semantics may be applied. The choice is determined by an input flag when creating of the ConsumerAdmin, and the operator that is used for this purpose by a given ConsumerAdmin is maintained in a read-only attribute.

The ConsumerAdmin interface also supports attributes that maintain references to priority and lifetime mapping filter objects. These mapping filter objects are applied to all proxy supplier objects created by a given ConsumerAdmin.

Each ConsumerAdmin assigns a unique numeric identifier to each proxy supplier it maintains. The ConsumerAdmin interface supports attributes that maintain the list of these unique identifiers associated with the proxy pull and the proxy push suppliers created by a given ConsumerAdmin. The ConsumerAdmin interface also supports an operation that, given the unique identifier of a proxy supplier, returns the object reference of that proxy supplier. Finally, the ConsumerAdmin interface supports operations that create the various styles of proxy supplier objects supported by the event channel.

ConsumerAdmin::MyID

```
readonly attribute [AdminID](#cosnotifychanneladmin-data-types) MyID;
```

Maintains the unique identifier of the target **ConsumerAdmin** instance that is assigned to it upon creation by the event channel.

ConsumerAdmin::MyChannel

```
readonly attribute [EventChannel](../  
cosnotifychanneladmin-eventchannel_interface/  
cosnotifychanneladmin-eventchannel_interface.md) MyChannel
```

Maintains the object reference of the event channel that created a given **ConsumerAdmin** instance.

ConsumerAdmin::MyOperator

```
readonly attribute [InterFilterGroupOperator](#cosnotifychanneladmin-data-  
types) MyOperator;
```

Maintains the information regarding whether **AND** or **OR** semantics are used during the evaluation of a given event when combining the filter objects associated with the target **ConsumerAdmin** and those defined locally on a given proxy supplier.

ConsumerAdmin::priority_filter

```
attribute CosNotifyFilter::MappingFilter priority_filter;
```

Maintains a reference to a mapping filter object that affects how each proxy supplier created by the target **ConsumerAdmin** treats events with respect to priority.

Each proxy supplier also has an associated attribute which maintains a reference to a mapping filter object for the priority property. This local mapping filter object is only used by the proxy supplier in the event that the `priority_filter` attribute of the `ConsumerAdmin` instance that created it is set to `OBJECT_NIL`.

`ConsumerAdmin::lifetime_filter`

```
attribute CosNotifyFilter::MappingFilter lifetime_filter;
```

Maintains a reference to a mapping filter that affects how each proxy supplier created by the target **ConsumerAdmin** treats events with respect to lifetime.

Each proxy supplier object also has an associated attribute that maintains a reference to a mapping filter object for the lifetime property. This local mapping filter object is only used by the proxy supplier in the event that the `lifetime_filter` attribute of the `ConsumerAdmin` instance that created it is set to `OBJECT_NIL`.

`ConsumerAdmin::pull_suppliers`

```
readonly attribute [ProxyIDSeq](#cosnotifychanneladmin-data-types)
pull_suppliers;
```

Contains the list of unique identifiers that have been assigned by a **ConsumerAdmin** instance to each pull-style proxy supplier it has created.

`ConsumerAdmin::push_suppliers`

```
readonly attribute [ProxyIDSeq](#cosnotifychanneladmin-data-types)
push_suppliers;
```

Contains the list of unique identifiers that have been assigned by a **ConsumerAdmin** instance to each push-style proxy supplier it has created.

`ConsumerAdmin::get_proxy_supplier()`

```
[ProxySupplier](../cosnotifychanneladminproxysupplier_interface/
cosnotifychanneladminproxysupplier_interface.md) get_proxy_supplier (in
[ProxyID](#cosnotifychanneladmin-data-types) proxy_id)
    raises ( [ProxyNotFound](#cosnotifychanneladmin-exceptions) );
```

Returns an object reference to the proxy supplier whose unique id was passed to the method.

Parameters

proxy_id

A numeric identifier associated with one of the proxy suppliers that created by the target `ConsumerAdmin`.

Exceptions

```
[ProxyNotFound](#cosnotifychanneladmin-exceptions)
```

The input parameter does not correspond to the unique identifier of a proxy supplier object created by the target `ConsumerAdmin`.

`ConsumerAdmin::obtain_notification_pull_supplier()`

```
[ProxySupplier](../cosnotifychanneladminproxysupplier_interface/
cosnotifychanneladminproxysupplier_interface.md)
obtain_notification_pull_supplier (
    in [ClientType](#cosnotifychanneladmin-data-types) ctype,
    out [ProxyID](#cosnotifychanneladmin-data-types) proxy_id)
    raises ( [AdminLimitExceeded](#cosnotifychanneladmin-exceptions) );
```

Creates instances of the pull-style proxy suppliers defined in `CosNotifyChannelAdmin` and returns an object reference to the new proxy.

Three varieties of pull-style proxy suppliers are defined in this module:

- The [ProxyPullSupplier](#) interface supports connections to pull consumers that receive events as `Anys`.
- The [StructuredProxyPullSupplier](#) interface supports connections to pull consumers that receive structured events.

- The [SequenceProxyPullSupplier](#) interface support connections to pull consumers that receive sequences of structured events.

The input parameter flag indicates which type of pull style proxy instance to create.

The target ConsumerAdmin creates the new pull-style proxy supplier and assigns a numeric identifier to it that is unique among all proxy suppliers the `ConsumerAdmin` has created.

Parameters

<code>ctype</code>	A flag that indicates which style of pull-style proxy supplier to create.
<code>proxy_id</code>	The unique identifier of the new proxy supplier.

Exceptions

`[AdminLimitExceeded] (#cosnotifychanneladmin-exceptions)`

The number of consumers currently connected to the channel with which the target **ConsumerAdmin** is associated exceeds the value of the **MaxConsumers** administrative property.

`ConsumerAdmin::obtain_notification_push_supplier()`

```
[ProxySupplier](../cosnotifychanneladminproxysupplier_interface/
cosnotifychanneladminproxysupplier_interface.md)
obtain_notification_push_supplier (
    in [ClientType] (#cosnotifychanneladmin-data-types) ctype,
    out [ProxyID] (#cosnotifychanneladmin-data-types) proxy_id)
    raises ( [AdminLimitExceeded] (#cosnotifychanneladmin-exceptions) );
```

Creates instances of the push-style proxy supplier objects defined in `CosNotifyChannelAdmin` and returns an object reference to the new proxy.

Three varieties of push-style proxy suppliers are defined in this module:

- The [ProxyPushSupplier](#) interface supports connections to push consumers that receive events as `Anys`.
- The [StructuredProxyPushSupplier](#) interface supports connections to push consumers that receive structured events.
- The [SequenceProxyPushSupplier](#) interface supports connections to push consumers that receive sequences of structured events.

The input parameter flag indicates which type of push-style proxy to create.

The target **ConsumerAdmin** creates the new push-style proxy supplier and assigns a numeric identifier to it that is unique among all proxy suppliers the **ConsumerAdmin** has created.

Parameters

<code>ctype</code>	A flag indicating which style of push-style proxy supplier to create.
<code>proxy_id</code>	The unique identifier of the new proxy supplier.

Exceptions

[AdminLimitExceeded] (#cosnotifychanneladmin-exceptions)

The number of consumers currently connected to the channel with which the target **ConsumerAdmin** is associated exceeds the value of the **MaxConsumers** administrative property.

ConsumerAdmin::destroy()

```
void destroy();
```

Destroys all proxies under the administration of the target object, and then destroys the target object itself. When destroying each object, it frees any storage associated with the object in question, and then invalidates the object's IOR.

CosNotifyChannelAdmin::EventChannel Interface

```
//IDL
interface EventChannel :
    CosNotification::QoSAdmin,
    CosNotification::AdminPropertiesAdmin,
    CosEventChannelAdmin::EventChannel
{
    readonly attribute EventChannelFactory MyFactory;
    readonly attribute [ConsumerAdmin](../
cosnotifychanneladminconsumeradmin_interface/
cosnotifychanneladminconsumeradmin_interface.md) default_consumer_admin;
    readonly attribute [SupplierAdmin](../
cosnotifychanneladminsupplieradmin_interface/
cosnotifychanneladminsupplieradmin_interface.md) default_supplier_admin;
    readonly attribute CosNotifyFilter::FilterFactory
                                default_filter_factory;
    [ConsumerAdmin](../cosnotifychanneladminconsumeradmin_interface/
cosnotifychanneladminconsumeradmin_interface.md) new_for_consumers(
        in [InterFilterGroupOperator](#cosnotifychanneladmin-data-types)
op,
        out [AdminID](#cosnotifychanneladmin-data-types) id );
    [SupplierAdmin](../cosnotifychanneladminsupplieradmin_interface/
cosnotifychanneladminsupplieradmin_interface.md) new_for_suppliers(
        in [InterFilterGroupOperator](#cosnotifychanneladmin-data-types)
op,
        out [AdminID](#cosnotifychanneladmin-data-types) id );
    [ConsumerAdmin](../cosnotifychanneladminconsumeradmin_interface/
cosnotifychanneladminconsumeradmin_interface.md) get_consumeradmin ( in
[AdminID](#cosnotifychanneladmin-data-types) id )
        raises ([AdminNotFound](#cosnotifychanneladmin-exceptions));
    [SupplierAdmin](../cosnotifychanneladminsupplieradmin_interface/
cosnotifychanneladminsupplieradmin_interface.md) get_supplieradmin ( in
[AdminID](#cosnotifychanneladmin-data-types) id )
        raises ([AdminNotFound](#cosnotifychanneladmin-exceptions));
    [AdminIDSeq](#cosnotifychanneladmin-data-types) get_all_consumeradmins();
    [AdminIDSeq](#cosnotifychanneladmin-data-types) get_all_supplieradmins();
};
```

The **EventChannel** interface defines the behavior of an event channel. This interface inherits from **CosEventChannelAdmin::EventChannel**; this makes an instance of the notification service **EventChannel** interface fully compatible with an OMG event service style untyped event channel.

Inheritance of **CosEventChannelAdmin::EventChannel** enables an instance of the **EventChannel** interface to create event service style **ConsumerAdmin** and **SupplierAdmin** instances. These instances can subsequently be used to create pure event service style proxies, which support connections to pure event service style suppliers and consumers.

While notification service style proxies and admin objects have unique identifiers associated with them, enabling their references to be obtained by invoking operations on the notification service style admin and event channel interfaces, event service style proxies and admin objects do not have associated unique identifiers, and cannot be returned by invoking an operation on the notification service style admin or event channel interfaces.

The **EventChannel** interface also inherits from the **QoSAdmin** and the **AdminPropertiesAdmin** interfaces defined in **CosNotification**. Inheritance of these interfaces enables a notification service style event channel to manage lists of QoS and administrative properties.

The **EventChannel** interface supports a read-only attribute that maintains a reference to the **EventChannelFactory** that created it. Each instance of the **EventChannel** interface has an associated default **ConsumerAdmin** and an associated default **SupplierAdmin**, both of which exist upon creation of the channel and that have the unique identifier of zero. Admin object identifiers must only be unique among a given type of admin, which means that the identifiers assigned to **ConsumerAdmin** objects can overlap those assigned to **SupplierAdmin** objects. The **EventChannel** interface supports read-only attributes that maintain references to these default admin objects.

The **EventChannel** interface supports operations that create new **ConsumerAdmin** and **SupplierAdmin** instances. The **EventChannel** interface also supports operations that, when provided with the unique identifier of an admin object, can return references to the **ConsumerAdmin** and **SupplierAdmin** instances associated with a given **EventChannel**. Finally, the **EventChannel** interface supports operations that return the sequence of unique identifiers of all **ConsumerAdmin** and **SupplierAdmin** instances associated with a given **EventChannel**.

EventChannel::MyFactory

```
readonly attribute EventChannelFactory MyFactory;
```

Maintains the object reference of the event channel factory that created a given **EventChannel**.

EventChannel::default_consumer_admin


```
readonly attribute [ConsumerAdmin](../
cosnotifychanneladminconsumeradmin_interface/
cosnotifychanneladminconsumeradmin_interface.md) default_consumer_admin;
```

Maintains a reference to the default [ConsumerAdmin](#) associated with the target **EventChannel**. Each **EventChannel** instance has an associated default [ConsumerAdmin](#), that exists upon creation of the channel and is assigned the unique identifier of zero. Clients can create additional event service style [ConsumerAdmin](#) by invoking the inherited **for_consumers** operation, and additional notification service style [ConsumerAdmin](#) by invoking the **new_for_consumers** operation defined by the **EventChannel** interface.

EventChannel::default_supplier_admin

```
readonly attribute [SupplierAdmin](../
cosnotifychanneladminsupplieradmin_interface/
cosnotifychanneladminsupplieradmin_interface.md) default_supplier_admin;
```

Maintains a reference to the default [SupplierAdmin](#) associated with the target **EventChannel**. Each **EventChannel** has an associated default [SupplierAdmin](#), that exists upon creation of the channel and is assigned the unique identifier of zero. Clients can create additional event service style [SupplierAdmin](#) by invoking the inherited **for_suppliers** operation, and additional notification service style [SupplierAdmin](#) by invoking the **new_for_suppliers** operation defined by the **EventChannel** interface.

EventChannel::default_filter_factory

```
readonly attribute CosNotifyFilter::FilterFactory
default_filter_factory;
```

Maintains an object reference to the default factory to be used by its associated **EventChannel** for creating filters. If the target channel does not support a default filter factory, the attribute maintains the value of `OBJECT_NIL`.

EventChannel::new_for_consumers()

```
[ConsumerAdmin](../cosnotifychanneladminconsumeradmin_interface/
cosnotifychanneladminconsumeradmin_interface.md) new_for_consumers(
    in [InterFilterGroupOperator](#cosnotifychanneladmin-data-types) op,
    out [AdminID](#cosnotifychanneladmin-data-types) id );
```

Creates a notification service style [ConsumerAdmin](#). The new instance is assigned a unique identifier by the target **EventChannel** that is unique among all [ConsumerAdmins](#) currently associated with the channel. Upon completion, the operation returns the reference to the new [ConsumerAdmin](#), and the unique identifier assigned to the new [ConsumerAdmin](#) as the output parameter.

Parameters

<code>op</code>	A boolean flag indicating whether to use <code>AND</code> or <code>OR</code> semantics when the ConsumerAdmin's filters are combined with the filters associated with any supplier proxies the ConsumerAdmin creates.
<code>id</code>	The unique identifier assigned to the new ConsumerAdmin .

EventChannel::new_for_suppliers()

```
[SupplierAdmin](../cosnotifychanneladminsupplieradmin_interface/
cosnotifychanneladminsupplieradmin_interface.md) new_for_suppliers(
    in [InterFilterGroupOperator](#cosnotifychanneladmin-data-types) op,
    out [AdminID](#cosnotifychanneladmin-data-types) id );
```

Creates a notification service style [SupplierAdmin](#). The new [SupplierAdmin](#) is assigned an identifier by the target **EventChannel** that is unique among all [SupplierAdmins](#) currently associated with the channel. Upon completion, the operation returns the reference to the new [SupplierAdmin](#), and the unique identifier assigned to the new [SupplierAdmin](#) as the output parameter.

Parameters

<code>op</code>	A boolean flag indicating whether to use <code>AND</code> or <code>OR</code> semantics when the SupplierAdmin's filters are combined with the filters associated with any supplier proxies the SupplierAdmin creates.
<code>id</code>	The unique identifier assigned to the new SupplierAdmin .

EventChannel::get_consumeradmin()

```
[ConsumerAdmin](../cosnotifychanneladminconsumeradmin_interface/
cosnotifychanneladminconsumeradmin_interface.md) get_consumeradmin ( in
[AdminID](#cosnotifychanneladmin-data-types) id )
    raises ([AdminNotFound](#cosnotifychanneladmin-exceptions));
```

Returns a reference to one of the [ConsumerAdmins](#) associated with the target **EventChannel**.

Note

While a notification service event channel can support both event service and notification service style `ConsumerAdmins`, only notification service style [ConsumerAdmins](#) have unique identifiers.

Parameters

`id`

A numeric value that is the unique identifier of one of the [ConsumerAdmins](#) associated with the target **EventChannel**.

Exceptions

```
[AdminNotFound](#cosnotifychanneladmin-exceptions)
```

The `id` is not the identifier of one of the [ConsumerAdmins](#) associated with the target **EventChannel**.

`EventChannel::get_supplieradmin()`

```
SupplierAdmin get_supplieradmin ( in AdminID id )
    raises ([AdminNotFound](#cosnotifychanneladmin-exceptions));
```

Returns a reference to one of the [SupplierAdmins](#) associated with the target **EventChannel**.

Note

While a notification service style event channel can support both Event service and notification service style `SupplierAdmins`, only notification service style `SupplierAdmins` have unique identifiers.

Parameters

`id`

A numeric value that is the unique identifier of one of the [SupplierAdmins](#) associated with the target **EventChannel**.

Exceptions

```
[AdminNotFound] (#cosnotifychanneladmin-exceptions)
```

The `id` is not the unique identifier of one of the **SupplierAdmins** associated with the target **EventChannel**.

EventChannel::get_all_consumeradmins()

```
AdminIDSeq get_all_consumeradmins();
```

Returns a sequence of unique identifiers assigned to all notification service style **ConsumerAdmins** created by the target **EventChannel**.

EventChannel::get_all_supplieradmins()

```
AdminIDSeq get_all_supplieradmins();
```

Returns a sequence of unique identifiers assigned to all notification service style **SupplierAdmins** created by the target **EventChannel**.

CosNotifyChannelAdmin::ProxyConsumer Interface

```
//IDL in CosNotifyChannelAdmin
interface ProxyConsumer:
    CosNotification::QoSAdmin,
    CosNotifyFilter::FilterAdmin
{
    readonly attribute [ProxyType](#cosnotifychanneladmin-data-types) MyType;
    readonly attribute [SupplierAdmin](../
cosnotifychanneladminsupplieradmin_interface/
cosnotifychanneladminsupplieradmin_interface.md) MyAdmin;
    CosNotification::EventTypeSeq obtain_subscription_types(
        in [ObtainInfoMode](#cosnotifychanneladmin-
data-types) mode );
    void validate_event_qos (
        in CosNotification::QoSProperties required_qos,
        out CosNotification::NamedPropertyRangeSeq available_qos)
        raises(CosNotification::UnsupportedQoS);
};
```

The `ProxyConsumer` interface is an abstract interface that is inherited by the different proxy consumers that can be instantiated within an event channel. It encapsulates the behaviors common to all notification service proxy consumers. In particular, the `ProxyConsumer` interface inherits the `QoSAdmin` interface defined within the `CosNotificationmodule`, and the `FilterAdmin` interface defined within the `CosNotifyFiltermodule`. The former inheritance enables proxy consumers to administer a list of associated QoS properties. The latter inheritance enables proxy consumers to administer a list of associated filter objects. Locally, the `ProxyConsumer` interface defines a read-only attribute that contains a reference to the `SupplierAdmin` object that created it. The `ProxyConsumer` interface also defines an operation to return the list of event types a given proxy consumer instance can forward, and an operation to determine which QoS properties can be set on a per-event basis.

`ProxyConsumer::obtain_subscription_types()`

```
CosNotification::EventTypeSeq obtain_subscription_types(
    in [ObtainInfoMode](#cosnotifychanneladmin-
data-types) mode);
```

Returns a list of event type names that consumers connected to the channel are interested in receiving.

Parameters

mode

Specifies whether to automatically notify the supplier of changes to the subscription list.

ProxyConsumer::validate_event_qos()

```
void validate_event_qos (
    in CosNotification::QoSProperties required_qos,
    out CosNotification::NamedPropertyRangeSeq available_qos)
    raises (CosNotification::UnsupportedQoS);
```

Checks whether the target proxy object will honor the setting of the specified QoS properties on a per-event basis. If all requested QoS property value settings can be satisfied by the target object, the operation returns successfully with an output parameter that contains a sequence of NamedPropertyRange data structures.

Parameters

required_qos	A sequence of QoS property name-value pairs that specify a set of QoS settings that a client is interested in setting on an event.

!!! note

The QoS property settings contained in the optional header fields of a structured event may differ from those that are configured on a given proxy object.

<code>available_qos</code>	A sequence of NamedPropertyRange. Each element includes the name of a an additional QoS property whose setting is supported by the target object on a per-event basis. Each element also includes the range of values that are acceptable for each property.

Exceptions

UnsupportedQoS

Raised if any of the requested settings cannot be honored by the target object. This exception contains as data a sequence of data structures identifying the name of a QoS property in the input list whose requested setting could not be satisfied, along with an error code and a range of valid settings for the property.

Exceptions

CosNotifyChannelAdmin::ProxyPullConsumer Interface

```
//IDL
interface ProxyPullConsumer :
    [ProxyConsumer](../cosnotifychanneladminproxyconsumer_interface/
cosnotifychanneladminproxyconsumer_interface.md),
    CosEventComm::PullConsumer
{
    void connect_any_pull_supplier (
        in CosEventComm::PullSupplier pull_supplier)
    raises(CosEventChannelAdmin::AlreadyConnected,
        CosEventChannelAdmin::TypeError);
};
```

The **ProxyPullConsumer** interface supports connections to the channel by suppliers who make events, packaged as `Anys`, available to the channel using the pull model.

The ProxyPullConsumer interface extends the OMG event service pull-style suppliers of untyped events by supporting event filtering and the configuration of QoS properties. This interface enables OMG event service style untyped event suppliers to take advantage of the features offered by the notification service.

Through inheritance of the [ProxyConsumer](#) interface, the ProxyPullConsumer interface supports administration of QoS properties, administration of a list of associated filter objects, and a read-only attribute containing a reference to the [SupplierAdmin](#) object that created it. In addition, this inheritance implies that a ProxyPullConsumer instance supports an operation that returns the list of event types that consumers connected to the same channel are interested in receiving, and an operation that returns information about the instance's ability to accept a QoS request.

The ProxyPullConsumer interface also inherits from the PullConsumer interface defined within CosEventComm. This interface supports the operation to disconnect the ProxyPullConsumer from its associated supplier. Finally, the ProxyPullConsumer interface defines the operation to establish the connection over which the pull supplier can send events to the channel.

ProxyPullConsumer::connect_any_pull_supplier()


```
void connect_any_pull_supplier (
    in CosEventComm::PullSupplier pull_supplier)
    raises(CosEventChannelAdmin::AlreadyConnected,
        CosEventChannelAdmin::TypeError);
```

Establishes a connection between a pull-style supplier of events in the form of `Anys`, and the event channel. Once the connection is established, the proxy can proceed to receive events from the supplier by invoking `pull` or `try_pull` on the supplier (whether the proxy invokes `pull` or `try_pull`, and the frequency with which it performs such invocations, is a detail that is specific to the implementation of the channel).

Parameters

`pull_supplier`

A reference to an object supporting the `PullSupplier` interface defined within `CosEventComm`.

Exceptions

AlreadyConnected	Raised if the proxy is already connected to a pull supplier.
TypeError	An implementation of the <code>ProxyPullConsumer</code> interface may impose additional requirements on the interface supported by a pull supplier (for example, it may be designed to invoke some operation other than <code>pull</code> or <code>try_pull</code> in order to receive events). If the pull supplier being connected does not meet those requirements, this operation raises the <code>TypeError</code> exception.

CosNotifyChannelAdmin::ProxyPullSupplier Interface

```
//IDL
interface ProxyPullSupplier :
    [ProxySupplier](../cosnotifychanneladminproxysupplier_interface/
cosnotifychanneladminproxysupplier_interface.md),
    CosEventComm::PullSupplier
{
    void connect_any_pull_consumer (
        in CosEventComm::PullConsumer pull_consumer)
        raises(CosEventChannelAdmin::AlreadyConnected);
};
```

The **ProxyPullSupplier** interface supports connections to the channel by consumers that pull events from the channel as `Any`.

The ProxyPullSupplier interface extends the OMG event service pull-style consumers of untyped events by supporting event filtering and the configuration of QoS properties. This interface enables OMG event service style untyped event consumers to take advantage of the features offered by the notification service.

Through inheritance of the [ProxySupplier](#) interface, the ProxyPullSupplier interface supports administration of QoS properties, administration of a list of associated filter objects, mapping filters for event priority and lifetime, and a read-only attribute containing a reference to the [ConsumerAdmin](#) object that created it. This inheritance also means that a ProxyPullSupplier instance supports an operation that returns the list of event types that the proxy supplier will potentially supply, and an operation that returns information about the instance's ability to accept a QoS request.

The ProxyPullSupplier interface also inherits from the PullSupplier interface defined within the CosEventComm module of the OMG event service. This interface supports the pull and try_pull operations that the consumer connected to a ProxyPullSupplier instance invokes to receive an event from the channel in the form of an `Any`, and the operation to disconnect the ProxyPullSupplier from its associated consumer.

Finally, the ProxyPullSupplier interface defines the operation to establish a connection over which the pull consumer receives events from the channel.

ProxyPullSupplier::connect_any_pull_consumer()

```
void connect_any_pull_consumer (  
    in CosEventComm::PullConsumer pull_consumer)  
    raises(CosEventChannelAdmin::AlreadyConnected);
```

Establishes a connection between a pull consumer of events in the form of `Anys` and an event channel. Once established, the consumer can receive events from the channel by invoking `pull` or `try_pull` on its associated `ProxyPullSupplier`.

Parameters

`pull_consumer`

A reference to an object supporting the `PullConsumer` interface defined within the `CosEventComm` module of the OMG event service.

Exceptions

`AlreadyConnected`

The target object of this operation is already connected to a pull consumer object.

CosNotifyChannelAdmin::ProxyPushConsumer Interface

```
//IDL
interface ProxyPushConsumer :
    [ProxyConsumer](../cosnotifychanneladminproxyconsumer_interface/
cosnotifychanneladminproxyconsumer_interface.md),
    CosEventComm::PushConsumer
{
    void [connect_any_push_supplier](#cosnotifychanneladminproxypushconsumer-
interface) (
        in CosEventComm::PushSupplier push_supplier)
        raises(CosEventChannelAdmin::AlreadyConnected);
};
```

The `ProxyPushConsumer` interface supports connections to the channel by suppliers that push events to the channel as `Any`.

The `ProxyPushConsumer` extends the OMG event service push consumer interface by supporting event filtering and the configuration of various QoS properties. This interface enables OMG event service style untyped event suppliers to take advantage of these new features offered by the notification service.

Through inheritance of the `ProxyConsumer` interface, the `ProxyPushConsumer` interface supports administration of QoS properties, administration of a list of associated filter objects, and a read-only attribute containing a reference to the `SupplierAdmin` object that created it. In addition, this inheritance means that a `ProxyPushConsumer` instance supports an operation that returns the list of event types that consumers connected to the same channel are interested in receiving, and an operation that returns information about the instance's ability to accept a QoS request.

The `ProxyPushConsumer` interface also inherits from the `PushConsumer` interface defined within the `CosEventComm` module of the OMG event service. This interface supports the `push` operation which the supplier connected to a `ProxyPushConsumer` instance invokes to send an event to the channel in the form of an `Any`, and the operation to disconnect the `ProxyPushConsumer` from its associated supplier.

Finally, the `ProxyPushConsumer` interface defines the operation to establish the connection over which the push supplier sends events to the channel.

`ProxyPushConsumer::connect_any_push_supplier()`

```
void connect_any_push_supplier (
    in CosEventComm::PushSupplier push_supplier)
    raises(CosEventChannelAdmin::AlreadyConnected);
```

Establishes a connection between a push-style supplier of events in the form of an `any` and an event channel. Once established, the supplier can send events to the channel by invoking the **push** operation supported by the target **ProxyPushConsumer** instance.

Parameters

`push_supplier`

The reference to an object supporting the **PushSupplier** interface defined within the `CosEventComm` module.

Exceptions

`AlreadyConnected`

The target object of this operation is already connected to a push supplier object.

Exceptions

CosNotifyChannelAdmin::ProxyPushSupplier Interface

```
//IDL
interface ProxyPushSupplier :
    [ProxySupplier](../cosnotifychanneladminproxysupplier_interface/
cosnotifychanneladminproxysupplier_interface.md),
    CosEventComm::PushSupplier
{
    void connect_any_push_consumer (
        in CosEventComm::PushConsumer push_consumer)
    raises(CosEventChannelAdmin::AlreadyConnected,
        CosEventChannelAdmin::TypeError );
    void suspend_connection()
    raises(CosEventChannel::ConnectionAlreadyInactive);
    void resume_connection()
    raises(CosEventChannelAdmin::ConnectionAlreadyActive);
};
```

The **ProxyPushSupplier** interface supports connections to the channel by consumers that receive events from the channel as untyped *Anys*.

The ProxyPushSupplier interface extends the OMG event service push-style consumers of untyped events by supporting event filtering and the configuration of QoS properties. Thus, this interface enables OMG event service push-style untyped event consumers to take advantage of the features offered by the notification service.

Through inheritance of [ProxySupplier](#), the ProxyPushSupplier interface supports administration of QoS properties, administration of a list of associated filter objects, mapping filters for event priority and lifetime, and a read-only attribute containing a reference to the [ConsumerAdmin](#) that created it. This inheritance also implies that a ProxyPushSupplier instance supports an operation that returns the list of event types that the proxy supplier can supply, and an operation that returns information about the instance's ability to accept a QoS request.

The ProxyPushSupplier interface also inherits from the PushSupplier interface defined within CosEventComm. This interface supports the operation to disconnect a ProxyPushSupplier from its associated consumer.

The ProxyPushSupplier interface defines the operation to establish the connection over which the push consumer can receive events from the channel. The ProxyPushSupplier interface also defines a pair of operations that can suspend and resume the connection between a ProxyPushSupplier and its associated PushConsumer. During the time a connection is suspended, the ProxyPushSupplier accumulates events destined for the consumer but does not transmit them until the connection is resumed.

ProxyPushSupplier::connect_any_push_consumer()

```
void connect_any_push_consumer (
    in CosEventComm::PushConsumer push_consumer)
raises(CosEventChannelAdmin::AlreadyConnected,
    CosEventChannelAdmin::TypeError );
```

Establishes a connection between a push-style consumer of events in the form of `Anys`, and the event channel. Once the connection is established, the `ProxyPushSupplier` sends events to its associated consumer by invoking **push** on the consumer.

Parameters

`push_consumer`

A reference to an object supporting the `PushConsumer` interface defined within `CosEventComm`

Exceptions

AlreadyConnected	Raised if the proxy is already connected to a push consumer.
TypeError	An implementation of the <code>ProxyPushSupplier</code> interface may impose additional requirements on the interface supported by a push consumer (for example, it may be designed to invoke some operation other than <code>push</code> in order to transmit events). If the push consumer being connected does not meet those requirements, this operation raises the <code>TypeError</code> exception.

ProxyPushSupplier::suspend_connection()

```
void suspend_connection()
    raises([ConnectionAlreadyInactive](#cosnotifychanneladmin-exceptions));
```

Causes the `ProxyPushSupplier` to stop sending events to the `PushConsumer` instance connected to it. The `ProxyPushSupplier` does not forward events to its associated `PushConsumer` until `resume_connection()` is invoked. During this time, the `ProxyPushSupplier` continues to queue events destined for the `PushConsumer`; however, events that time out prior to resumption of the connection are discarded. Upon resumption of the connection, all queued events are forwarded to the `PushConsumer`.

Exceptions The `ConnectionAlreadyInactive` exception is raised if the connection is currently in a suspended state.

`ProxyPushSupplier::resume_connection()`

```
void resume_connection()
    raises([ConnectionAlreadyActive](#cosnotifychanneladmin-exceptions));
```

Causes the `ProxyPushSupplier` interface to resume sending events to the `PushConsumer` instance connected to it, including those events that have been queued while the connection was suspended and have not yet timed out.

Exceptions

```
[ConnectionAlreadyActive](#cosnotifychanneladmin-exceptions)
```

The connection is not in a suspended state.

CosNotifyChannelAdmin::ProxySupplier Interface

```
//IDL
interface ProxySupplier :
    CosNotification::QoSAdmin,
    CosNotifyFilter::FilterAdmin
{
    readonly attribute [ConsumerAdmin](../
cosnotifychanneladminconsumeradmin_interface/
cosnotifychanneladminconsumeradmin_interface.md) MyAdmin;
    readonly attribute [ProxyType](#cosnotifychanneladmin-data-types) MyType;
    attribute CosNotifyFilter::MappingFilter priority_filter;
    attribute CosNotifyFilter::MappingFilter lifetime_filter;
    CosNotification::EventTypeSeq obtain_offered_types(
        in [ObtainInfoMode](#cosnotifychanneladmin-
data-types) mode );
    void validate_event_qos (
        in CosNotification::QoSProperties required_qos,
        out CosNotification::NamedPropertyRangeSeq available_qos)
        raises (CosNotification::UnsupportedQoS);
};
```

The `ProxySupplier` interface is an abstract interface that is inherited by the different proxy suppliers that can be instantiated within an event channel. It encapsulates the behaviors common to all notification service proxy suppliers. In particular, the `ProxySupplier` interface inherits the `QoSAdmin` interface defined within the `CosNotification` module, and the `FilterAdmin` interface defined within the `CosNotifyFilter` module. The former inheritance enables proxy suppliers to administer a list of associated QoS properties. The latter inheritance enables proxy suppliers to administer a list of associated filter objects.

Locally, the `ProxySupplier` interface defines a read-only attribute that contains a reference to the [ConsumerAdmin](#) object that created it. In addition, the `ProxySupplier` interface defines attributes that associate two mapping filter objects with each proxy supplier, one for priority and one for lifetime. For more information on mapping filters refer to the *CORBA Notification Service Guide*.

Lastly, the `ProxySupplier` interface defines an operation to return the list of event types that a given proxy supplier can forward to its associated consumer, and an operation to determine which QoS properties can be set on a per-event basis.

ProxySupplier::priority_filter

```
attribute CosNotifyFilter::MappingFilter priority_filter;
```

Contains a reference to an object supporting the MappingFilter interface defined in the CosNotifyFilter module. Such an object encapsulates a list of constraint-value pairs, where each constraint is a boolean expression based on the type and contents of an event, and the value is a possible priority setting for the event.

Upon receipt of an event by a proxy supplier object whose `priority_filter` attribute contains a non-zero reference, the proxy supplier invokes the `match` operation supported by the mapping filter object. The mapping filter object then applies its encapsulated constraints to the event.

If the `match` operation returns `TRUE`, the proxy supplier changes the events priority to the value specified in the constraint-value pair that matched the event.

If the `match` operation returns `FALSE`, the proxy supplier checks if the events priority property is already set. If so, the filter does nothing. If the priority property is not set, the filter sets the priority property to its default value.

ProxySupplier::lifetime_filter

```
attribute CosNotifyFilter::MappingFilter lifetime_filter;
```

Contains a reference to an object supporting the MappingFilter interface defined in the CosNotifyFilter module. Such an object encapsulates a list of constraint-value pairs, where each constraint is a boolean expression based on the type and contents of an event, and the value is a possible lifetime setting for the event.

Upon receipt of each event by a proxy supplier object whose `lifetime_filter` attribute contains a non-zero reference, the proxy supplier invokes the `match` operation supported by the mapping filter object. The mapping filter object then proceeds to apply its encapsulated constraints to the event.

If the `match` operation returns `TRUE`, the proxy supplier changes the events lifetime to the value specified in the constraint-value pair that matched the event.

If the `match` operation returns `FALSE`, the proxy supplier checks if the events lifetime property is already set. If so, the filter does nothing. If the lifetime property is not set, the filter sets the lifetime property to its default value.

ProxySupplier::obtain_offered_types()

```
CosNotification::EventTypeSeq obtain_offered_types(
    in [ObtainInfoMode](#cosnotifychanneladmin-
data-types) mode );
```

Returns a list names of event types that the target proxy supplier can forward to its associated consumer.

This mechanism relies on event suppliers keeping the channel informed of the types of events they plan to supply by invoking the `offer_change` operation on their associated proxy consumer objects. The proxy consumers automatically share the information about supplied event types with the proxy suppliers associated with the channel. This enables consumers to discover the types of events that can be supplied to them by the channel by invoking the `obtain_offered_types` operation on their associated proxy supplier.

Parameters

`mode`

Specifies how to notify consumers of changes to the publication list.

`ProxySupplier::validate_event_qos()`

```
void validate_event_qos (
    in CosNotification::QoSProperties required_qos,
    out CosNotification::NamedPropertyRangeSeq available_qos)
    raises (CosNotification::UnsupportedQoS);
```

Checks whether the target proxy object will honor the setting of the specified QoS properties on a per-event basis. If all requested QoS property value settings can be satisfied by the target object, the operation returns successfully with an output parameter that contains a sequence of `NamedPropertyRange` data structures.

Parameters

<code>required_qos</code>	A sequence of QoS property name-value pairs that specify a set of QoS settings that a client is interested in setting on an event

!!! note

The QoS property settings contained in the optional header fields of a structured event may differ from those that are configured on a given proxy object.

<code>available_qos</code>	A sequence of NamedPropertyRange. Each element includes the name of a an additional QoS property whose setting is supported by the target object on a per-event basis. Each element also includes the range of values that are acceptable for each such property.

Exceptions

UnsupportedQoS

Raised if any of the requested settings cannot be honored by the target object. This exception contains as data a sequence of data structures, each of which identifies the name of a QoS property in the input list whose requested setting could not be satisfied, along with an error code and a range of settings for the property that could be satisfied.

CosNotifyChannelAdmin::SequenceProxyPullConsumer Interface

```
//IDL
interface SequenceProxyPullConsumer :
    [ProxyConsumer](../cosnotifychanneladminproxyconsumer_interface/
cosnotifychanneladminproxyconsumer_interface.md),
    CosNotifyComm::SequencePullConsumer
{
    void connect_sequence_pull_supplier (
        in CosNotifyComm::SequencePullSupplier pull_supplier)
        raises(CosEventChannelAdmin::AlreadyConnected,
            CosEventChannelAdmin::TypeError );
};
```

The **SequenceProxyPullConsumer** interface supports connections to the channel by suppliers who make sequences of structured events available to the channel using the pull model.

Through inheritance of [ProxyConsumer](#), the SequenceProxyPullConsumer interface supports administration of QoS properties, administration of a list of associated filter objects, and a read-only attribute containing a reference to the [SupplierAdmin](#) that created it. This inheritance also implies that a SequenceProxyPullConsumer supports an operation that returns the list of event types that consumers connected to the same channel are interested in receiving, and an operation that returns information about the instance's ability to accept a QoS request.

The SequenceProxyPullConsumer interface also inherits from the SequencePullConsumer interface defined in the CosNotifyComm module. This interface supports the operation to close the connection from the supplier to the SequenceProxyPullConsumer. Since the SequencePullConsumer interface inherits from NotifyPublish, a supplier can inform its associated SequenceProxyPullConsumer whenever the list of event types it plans to supply to the channel changes.

The SequenceProxyPullConsumer interface also defines a method to establish a connection between the supplier and an event channel.

SequenceProxyPullConsumer::connect_sequence_pull_supplier()

```
void connect_sequence_pull_supplier (
    in CosNotifyComm::SequencePullSupplier pull_supplier)
    raises(CosEventChannelAdmin::AlreadyConnected,
        CosEventChannelAdmin::TypeError );
```

Establishes a connection between a pull-style supplier of sequences of structured events and the event channel. Once the connection is established, the proxy can receive events from the supplier by invoking `pull_structured_events` or `try_pull_structured_events` on the supplier (whether the proxy invokes `pull_structured_events` or `try_pull_structured_events`, and the frequency with which it performs such invocations, is a detail specific to the implementation of the channel).

Parameters

`pull_supplier`

A reference to an object supporting the `SequencePullSupplier` interface defined within `CosNotifyComm`.

Exceptions

AlreadyConnected	Raised if the proxy is already connected to a pull supplier.
TypeError	An implementation of the <code>SequenceProxyPullConsumer</code> interface may impose additional requirements on the interface supported by a pull supplier (for example, it may be designed to invoke some operation other than <code>pull_structured_events</code> or <code>try_pull_structured_events</code> in order to receive events). If the pull supplier being connected does not meet those requirements, this operation raises the <code>TypeError</code> or exception.

CosNotifyChannelAdmin::SequenceProxyPushConsumer Interface

```
//IDL
interface SequenceProxyPushConsumer :
    [ProxyConsumer](../cosnotifychanneladminproxyconsumer_interface/
cosnotifychanneladminproxyconsumer_interface.md),
    CosNotifyComm::SequencePushConsumer
{
    void connect_sequence_push_supplier (
        in CosNotifyComm::SequencePushSupplier push_supplier)
        raises(CosEventChannelAdmin::AlreadyConnected);
};
```

The **SequenceProxyPushConsumer** interface supports connections to the channel by suppliers that push events to the channel as sequences of structured events.

Through inheritance of the [ProxyConsumer](#) interface, the interface supports administration of QoS properties, administration of a list of associated filter objects, and a read-only attribute containing a reference to the [SupplierAdmin](#) object that created it. In addition, this inheritance means that a **SequenceProxyPushConsumer** instance supports an operation that returns the list of event types that consumers connected to the same channel are interested in receiving, and an operation that returns information about the instance's ability to accept a QoS request.

The **SequenceProxyPushConsumer** interface also inherits from the **SequencePushConsumer** interface defined in the **CosNotifyComm** module. This interface supports the operation that enables a supplier of sequences of structured events to push them to a **SequenceProxyPushConsumer**, and also the operation to close down the connection from the supplier to the **SequenceProxyPushConsumer**. Since the **SequencePushConsumer** interface inherits from the **NotifyPublish** interface, a supplier can inform its associated **SequenceProxyPushConsumer** when the list of event types it supplies to the channel changes.

Lastly, the **SequenceProxyPushConsumer** interface defines a method to establish a connection between a supplier and an event channel.

SequenceProxyPushConsumer::connect_sequence_push_supplier()

```
void connect_sequence_push_supplier (  
    in CosNotifyComm::SequencePushSupplier push_supplier)  
    raises(CosEventChannelAdmin::AlreadyConnected);
```

Establishes a connection between a push-style supplier of sequences of structured events and an event channel. Once the connection is established, the supplier can send events to the channel by invoking `push_structured_events` on its associated `SequenceProxyPushConsumer`.

Parameters

`push_supplier`

A reference to an object supporting the `SequencePushSupplier` interface defined within the `CosNotifyComm` module.

Exceptions

`AlreadyConnected`

The proxy is already connected to a push supplier object.

CosNotifyChannelAdmin::SequenceProxyPullSupplier Interface

```
//IDL
interface SequenceProxyPullSupplier :
    [ProxySupplier](../cosnotifychanneladminproxysupplier_interface/
cosnotifychanneladminproxysupplier_interface.md),
    CosNotifyComm::SequencePullSupplier
{
    void connect_sequence_pull_consumer (
        in CosNotifyComm::SequencePullConsumer pull_consumer)
        raises(CosEventChannelAdmin::AlreadyConnected);
};
```

The **SequenceProxyPullSupplier** interface supports connections to the channel by consumers who pull sequences of structured events from an event channel.

Through inheritance of the [ProxySupplier](#) interface, the SequenceProxyPullSupplier interface supports administration of QoS properties, administration of a list of associated filter objects, and a read-only attribute containing a reference to the [ConsumerAdmin](#) object that created it. In addition, this inheritance implies that a SequenceProxyPullSupplier instance supports an operation that returns the list of event types that the proxy supplier can supply, and an operation that returns information about the instance's ability to accept a QoS request.

The SequenceProxyPullSupplier interface also inherits from the SequencePullSupplier interface defined in CosNotifyComm. This interface supports the operations enabling a consumer of sequences of structured events to pull them from the SequenceProxyPullSupplier, and also the operation to close the connection from the consumer to its associated SequenceProxyPullSupplier. Since the SequencePullSupplier interface inherits from the NotifySubscribe interface, a SequenceProxyPullSupplier can be notified whenever the list of event types that its associated consumer is interested in receiving changes.

The SequenceProxyPullSupplier interface also defines a method to establish a connection between the consumer and an event channel.

SequenceProxyPullSupplier:: connect_sequence_pull_consumer()

```
void connect_sequence_pull_consumer (  
    in CosNotifyComm::SequencePullConsumer pull_consumer)  
    raises(CosEventChannelAdmin::AlreadyConnected);
```

Establishes a connection between a pull-style consumer of sequences of structured events and the event channel. Once the connection is established, the consumer can proceed to receive events from the channel by invoking `pull_structured_events` or `try_pull_structured_events` on its associated `SequenceProxyPullSupplier`.

Parameters

`pull_consumer`

A reference to an object supporting the `SequencePullConsumer` interface defined in `CosNotifyComm`.

Exceptions

`AlreadyConnected`

The proxy is already connected to a pull consumer.

CosNotifyChannelAdmin::SequenceProxyPushSupplier Interface

```
//IDL
interface SequenceProxyPushSupplier :
    [ProxySupplier](../cosnotifychanneladminproxysupplier_interface/
cosnotifychanneladminproxysupplier_interface.md),
    CosNotifyComm::SequencePushSupplier
{
    void connect_sequence_push_consumer (
        in CosNotifyComm::SequencePushConsumer push_consumer)
        raises(CosEventChannelAdmin::AlreadyConnected,
            CosEventChannelAdmin::TypeError );
    void suspend_connection()
        raises([ConnectionAlreadyInactive](#cosnotifychanneladmin-
exceptions));
    void resume_connection()
        raises([ConnectionAlreadyActive](#cosnotifychanneladmin-exceptions));
};
```

The **SequenceProxyPushSupplier** interface supports connections to the channel by consumers that receive sequences of structured events from the channel.

Through inheritance of [ProxySupplier](#), the SequenceProxyPushSupplier interface supports administration of QoS properties, administration of a list of associated filter objects, and a read-only attribute containing a reference to the [ConsumerAdmin](#) that created it. This inheritance also implies that a SequenceProxyPushSupplier instance supports an operation that returns the list of event types that the proxy supplier can supply, and an operation that returns information about the instance's ability to accept a QoS request.

The SequenceProxyPushSupplier interface also inherits from the SequencePushSupplier interface defined in CosNotifyComm. This interface supports the operation to close the connection from the consumer to the SequenceProxyPushSupplier. Since the SequencePushSupplier interface inherits from the NotifySubscribe interface, a SequenceProxyPushSupplier can be notified whenever the list of event types that its associated consumer is interested in receiving changes.

Lastly, the `SequenceProxyPushSupplier` interface defines the operation to establish the connection over which the push consumer receives events from the channel. The `SequenceProxyPushSupplier` interface also defines a pair of operations to suspend and resume the connection between a `SequenceProxyPushSupplier` instance and its associated `SequencePushConsumer`. While a connection is suspended, the `SequenceProxyPushSupplier` accumulates events destined for the consumer but does not transmit them until the connection is resumed.

`SequenceProxyPushSupplier::connect_sequence_push_consumer()`

```
void connect_sequence_push_consumer (
    in CosNotifyComm::SequencePushConsumer push_consumer)
    raises(CosEventChannelAdmin::AlreadyConnected,
          CosEventChannelAdmin::TypeError );
```

Establishes a connection between a push-style consumer of sequences of structured events and the event channel. Once the connection is established, the **SequenceProxyPushSupplier** sends events to its associated consumer by invoking **push_structured_events**.

Parameters

`push_consumer`

A reference to a `SequencePushConsumer`.

Exceptions

AlreadyConnected	Raised if the proxy is already connected to a push consumer.
TypeError	An implementation of the <code>SequenceProxyPushSupplier</code> interface may impose additional requirements on the interface supported by a push consumer (for example, it may be designed to invoke some operation other than push_structured_events in order to transmit events). If the push consumer being connected does not meet those requirements, this operation raises the TypeError exception.

`SequenceProxyPushSupplier::suspend_connection()`

```
void suspend_connection()
    raises([ConnectionAlreadyInactive](#cosnotifychanneladmin-exceptions));
```

Causes the **Sequence** `ProxyPushSupplier` to stop sending events to the `PushConsumer` instance connected to it. The `StructuredProxyPushSupplier` does not forward events to its `SequencePushConsumer` until `resume_connection()` is invoked. During this time, the `SequenceProxyPushSupplier` continues to queue events destined for the `SequencePushConsumer`; however, events that time out prior to resumption of the connection are discarded. Upon resumption of the connection, all queued events are forwarded to the `SequencePushConsumer`.

Exceptions

```
[ConnectionAlreadyInactive](#cosnotifychanneladmin-exceptions)
```

The connection is already suspended.

`SequenceProxyPushSupplier::resume_connection()`

```
void resume_connection()
    raises([ConnectionAlreadyActive](#cosnotifychanneladmin-exceptions));
```

Causes the **Sequence** `ProxyPushSupplier` to resume sending events to the `SequencePushConsumer` instance connected to it, including those that have been queued while the connection was suspended and have not yet timed out.

Exceptions

```
[ConnectionAlreadyActive](#cosnotifychanneladmin-exceptions)
```

The connection is not suspended.

CosNotifyChannelAdmin::StructuredProxyPullConsumer Interface

```
//IDL
interface StructuredProxyPullConsumer :
    [ProxyConsumer](../cosnotifychanneladminproxyconsumer_interface/
cosnotifychanneladminproxyconsumer_interface.md),
    CosNotifyComm::StructuredPullConsumer
{
    void connect_structured_pull_supplier (
        in CosNotifyComm::StructuredPullSupplier pull_supplier)
        raises(CosEventChannelAdmin::AlreadyConnected,
            CosEventChannelAdmin::TypeError );
};
```

The **StructuredProxyPullConsumer** interface supports connections to the channel by suppliers that make structured events available to the channel using the pull model.

Through inheritance of [ProxyConsumer](#), the StructuredProxyPullConsumer interface supports administration of QoS properties, administration of a list of associated filter objects, and a read-only attribute containing a reference to the [SupplierAdmin](#) object that created it. This inheritance also implies that a StructuredProxyPullConsumer instance supports an operation that returns the list of event types that consumers connected to the same channel are interested in receiving, and an operation that returns information about the instance's ability to accept a QoS request.

The StructuredProxyPullConsumer interface also inherits from the StructuredPullConsumer interface defined in CosNotifyComm. This interface supports the operation to close the connection from the supplier to the StructuredProxyPullConsumer. Since the StructuredPullConsumer interface inherits from NotifyPublish, a supplier can inform the StructuredProxyPullConsumer to which it is connected whenever the list of event types it plans to supply to the channel changes.

Lastly, the StructuredProxyPullConsumer interface defines a method to establish a connection between the supplier and an event channel.

StructuredProxyPullConsumer::connect_structured_pull_supplier()

```
void connect_structured_pull_supplier (
    in CosNotifyComm::StructuredPullSupplier pull_supplier)
    raises(CosEventChannelAdmin::AlreadyConnected,
          CosEventChannelAdmin::TypeError );
```

Establishes a connection between a pull-style supplier of structured events and the event channel. Once the connection is established, the proxy can receive events from the supplier by invoking

`pull_structured_event` or `try_pull_structured_event` on the supplier (whether the proxy invokes `pull_structured_event` or `try_pull_structured_event`, and the frequency with which it performs such invocations, is a detail specific to the implementation of the channel).

Parameters

`pull_supplier`

A reference to an object supporting the `StructuredPullSupplier` interface defined within `CosNotifyComm`.

Exceptions

AlreadyConnected	Raised if the proxy is already connected to a pull supplier.
TypeError	An implementation of the <code>StructuredProxyPullConsumer</code> interface may impose additional requirements on the interface supported by a pull supplier (for example, it may be designed to invoke some operation other than <code>pull_structured_event</code> or <code>try_pull_structured_event</code> in order to receive events). If the pull supplier being connected does not meet those requirements, this operation raises the <code>TypeError</code> or exception.

CosNotifyChannelAdmin::StructuredProxyPullSupplier Interface

```
//IDL
interface StructuredProxyPullSupplier :
    [ProxySupplier](../cosnotifychanneladminproxysupplier_interface/
cosnotifychanneladminproxysupplier_interface.md),
    CosNotifyComm::StructuredPullSupplier
{
    void connect_structured_pull_consumer (
        in CosNotifyComm::StructuredPullConsumer pull_consumer)
        raises(CosEventChannelAdmin::AlreadyConnected);
};
```

The **StructuredProxyPullSupplier** interface supports connections to the channel by consumers that pull structured events from the channel.

Through inheritance of [ProxySupplier](#), the StructuredProxyPullSupplier interface supports administration of QoS properties, administration of a list of associated filter objects, and a read-only attribute containing a reference to the [ConsumerAdmin](#) object that created it. In addition, this inheritance means that a StructuredProxyPullSupplier instance supports an operation that returns the list of event types that the proxy supplier can supply, and an operation that returns information about the instance's ability to accept a QoS request.

The StructuredProxyPullSupplier interface also inherits from the StructuredPullSupplier interface defined in CosNotifyComm. This interface supports the operations enabling a consumer of structured events to pull them from a StructuredProxyPullSupplier, and the operation to close the connection from the consumer to the StructuredProxyPullSupplier. Since the StructuredPullSupplier interface inherits from NotifySubscribe, a StructuredProxyPullSupplier can be notified whenever the list of event types that its associated consumer is interested in receiving changes.

Lastly, the StructuredProxyPullSupplier interface defines a method to establish a connection between the consumer and an event channel.

StructuredProxyPullSupplier::connect_structured_pull_consumer()


```
void connect_structured_pull_consumer (  
    in CosNotifyComm::StructuredPullSupplier pull_consumer)  
    raises(CosEventChannelAdmin::AlreadyConnected);
```

Establishes a connection between a pull consumer of structured events and the event channel. Once established, the consumer can receive events from the channel by invoking `pull_structured_event` or `try_pull_structured_event` on its associated `StructuredProxyPullSupplier`.

Parameters

`pull_consumer`

A reference to an object supporting the `StructuredPullSupplier` interface defined in `CosNotifyComm`.

Exceptions

`AlreadyConnected`

The proxy is already connected to a pull consumer.

CosNotifyChannelAdmin::StructuredProxyPushConsumer Interface

```
//IDL
interface StructuredProxyPushConsumer :
    [ProxyConsumer](../cosnotifychanneladminproxyconsumer_interface/
cosnotifychanneladminproxyconsumer_interface.md),
    CosNotifyComm::StructuredPushConsumer
{
    void connect_structured_push_supplier (
        in CosNotifyComm::StructuredPushSupplier push_supplier)
        raises(CosEventChannelAdmin::AlreadyConnected);
};
```

The **StructuredProxyPushConsumer** interface supports connections to the channel by suppliers that push events to the channel as structured events.

Through inheritance of the [ProxyConsumer](#) interface, the interface supports administration of QoS properties, administration of a list of associated filter objects, and a read-only attribute containing a reference to the [SupplierAdmin](#) object that created it. In addition, this inheritance means that a StructuredProxyPushConsumer instance supports an operation that returns the list of event types that consumers connected to the same channel are interested in receiving, and an operation that returns information about the instance's ability to accept a QoS request.

The StructuredProxyPushConsumer interface also inherits from the StructuredPushConsumer interface defined in the CosNotifyComm module. This interface supports the operation that enables a supplier of structured events to push them to the StructuredProxyPushConsumer, and also an operation to close down the connection from the supplier to the StructuredProxyPushConsumer. Since the StructuredPushConsumer interface inherits from the NotifyPublish interface, a supplier can inform the StructuredProxyPushConsumer to which it is connected whenever the list of event types it plans to supply to the channel changes.

Lastly, the StructuredProxyPushConsumer interface defines a method to establish a connection between the supplier and an event channel.

StructuredProxyPushConsumer::connect_structured_push_supplier()

```
void connect_structured_push_supplier (  
    in CosNotifyComm::StructuredPushSupplier push_supplier)  
    raises(CosEventChannelAdmin::AlreadyConnected);
```

Establishes a connection between a push-style supplier of structured events and the event channel. Once the connection is established, the supplier can send events to the channel by invoking `push_structured_event` on its associated `StructuredProxyPushConsumer` instance.

Parameters

`push_supplier`

A reference to an object supporting the `StructuredPushSupplier` interface defined within the `CosNotifyComm` module.

Exceptions

`AlreadyConnected`

The proxy object is already connected to a push supplier object.

CosNotifyChannelAdmin::StructuredProxyPushSupplier Interface

```
//IDL
interface StructuredProxyPushSupplier :
    [ProxySupplier](../cosnotifychanneladminproxysupplier_interface/
cosnotifychanneladminproxysupplier_interface.md),
    CosNotifyComm::StructuredPushSupplier
{
    void connect_structured_push_consumer (
        in CosNotifyComm::StructuredPushConsumer push_consumer)
        raises(CosEventChannelAdmin::AlreadyConnected,
            CosEventChannelAdmin::TypeError );
    void suspend_connection()
        raises([ConnectionAlreadyInactive](#cosnotifychanneladmin-
exceptions));
    void resume_connection()
        raises([ConnectionAlreadyActive](#cosnotifychanneladmin-exceptions));
};
```

The **StructuredProxyPushSupplier** interface supports connections to the channel by consumers that receive structured events from the channel.

Through inheritance of [ProxySupplier](#), the StructuredProxyPushSupplier interface supports administration of QoS properties, administration of a list of associated filter objects, and a read-only attribute containing a reference to the [ConsumerAdmin](#) that created it. This inheritance also implies that a StructuredProxyPushSupplier instance supports an operation that returns the list of event types that the proxy supplier can supply, and an operation that returns information about the instance's ability to accept a QoS request.

The StructuredProxyPushSupplier interface also inherits from the StructuredPushSupplier interface defined in CosNotifyComm. This interface supports the operation that to close the connection from the consumer to the StructuredProxyPushSupplier. Since StructuredPushSupplier inherits from NotifySubscribe, a StructuredProxyPushSupplier can be notified whenever the list of event types that its associated consumer is interested in receiving changes.

Lastly, the `StructuredProxyPushSupplier` interface defines the operation to establish the connection over which the push consumer can receive events from the channel. The `StructuredProxyPushSupplier` interface also defines a pair of operations to suspend and resume the connection between a `StructuredProxyPushSupplier` and its associated `StructuredPushConsumer`. During the time such a connection is suspended, the `StructuredProxyPushSupplier` accumulates events destined for the consumer but does not transmit them until the connection is resumed.

`StructuredProxyPushSupplier::connect_structured_push_consumer()`

```
void connect_structured_push_consumer (
    in CosNotifyComm::StructuredPushConsumer push_consumer)
    raises(CosEventChannelAdmin::AlreadyConnected,
          CosEventChannelAdmin::TypeError );
```

Establishes a connection between a push-style consumer of structured events and the event channel. Once the connection is established, the **StructuredProxyPushSupplier** sends events to the consumer by invoking **push_structured_event**.

Parameters

`push_consumer`

A reference to an object supporting the `StructuredPushConsumer` interface defined within `CosNotifyComm`

Exceptions

<code>AlreadyConnected</code>	Raised if the proxy is already connected to a push consumer.
<code>TypeError</code>	An implementation of the <code>StructuredProxyPushSupplier</code> interface may impose additional requirements on the interface supported by a push consumer (for example, it may be designed to invoke some operation other than push_structured_event to transmit events). If the push consumer being connected does not meet those requirements, this operation raises the TypeError exception.

`StructuredProxyPushSupplier::suspend_connection()`

```
void suspend_connection()
    raises([ConnectionAlreadyInactive](#cosnotifychanneladmin-exceptions));
```

Causes the `StructuredProxyPushSupplier` to stop sending events to the `PushConsumer` connected to it. The `StructuredProxyPushSupplier` does not forward events to its `StructuredPushConsumer` until `resume_connection()` is invoked. During this time, the `StructuredProxyPushSupplier` queues events destined for the `StructuredPushConsumer`; however, events that time out prior to resumption of the connection are discarded. Upon resumption of the connection, all queued events are forwarded to the `StructuredPushConsumer`.

Exceptions

```
[ConnectionAlreadyInactive](#cosnotifychanneladmin-exceptions)
```

The connection is already suspended.

`StructuredProxyPushSupplier::resume_connection()`

```
void resume_connection()
    raises([ConnectionAlreadyActive](#cosnotifychanneladmin-exceptions));
```

Causes causes the `Structured ProxyPushSupplier` to resume sending events to the **Structured** `PushConsumer` connected to it, including those that have been queued while the connection was suspended and have not yet timed out.

Exceptions

```
[ConnectionAlreadyActive](#cosnotifychanneladmin-exceptions)
```

The connection is not currently suspended.

CosNotifyChannelAdmin::SupplierAdmin Interface

```
//IDL
interface SupplierAdmin :
    CosNotification::QoSAdmin,
    CosNotifyComm::NotifyPublish,
    CosNotifyFilter::FilterAdmin,
    CosEventChannelAdmin::SupplierAdmin
{
    readonly attribute [AdminID](#cosnotifychanneladmin-data-types) MyID;
    readonly attribute EventChannel MyChannel;
    readonly attribute [InterFilterGroupOperator](#cosnotifychanneladmin-
data-types) MyOperator;
    readonly attribute [ProxyIDSeq](#cosnotifychanneladmin-data-types)
pull_consumers;
    readonly attribute [ProxyIDSeq](#cosnotifychanneladmin-data-types)
push_consumers;
    [ProxyConsumer](../cosnotifychanneladminproxyconsumer_interface/
cosnotifychanneladminproxyconsumer_interface.md) [get_proxy_consumer]
(#cosnotifychanneladminsupplieradmin-interface)(in [ProxyID]
(#cosnotifychanneladmin-data-types) proxy_id )
        raises ( [ProxyNotFound](#cosnotifychanneladmin-exceptions) );
    [ProxyConsumer](../cosnotifychanneladminproxyconsumer_interface/
cosnotifychanneladminproxyconsumer_interface.md)
[obtain_notification_pull_consumer](#cosnotifychanneladminsupplieradmin-
interface) (
        in [ClientType](#cosnotifychanneladmin-data-types) ctype,
        out [ProxyID](#cosnotifychanneladmin-data-types) proxy_id)
        raises ( [AdminLimitExceeded](#cosnotifychanneladmin-exceptions) );
    [ProxyConsumer](../cosnotifychanneladminproxyconsumer_interface/
cosnotifychanneladminproxyconsumer_interface.md)
[obtain_notification_push_consumer](#cosnotifychanneladminsupplieradmin-
interface) (
        in [ClientType](#cosnotifychanneladmin-data-types) ctype,
        out [ProxyID](#cosnotifychanneladmin-data-types) proxy_id)
        raises ( [AdminLimitExceeded](#cosnotifychanneladmin-exceptions) );
    [ProxyConsumer](../cosnotifychanneladminproxyconsumer_interface/
cosnotifychanneladminproxyconsumer_interface.md)
obtain_txn_notification_push_consumer (
        in [ClientType](#cosnotifychanneladmin-data-types) ctype,
        out [ProxyID](#cosnotifychanneladmin-data-types) proxy_id)
        raises ( [AdminLimitExceeded](#cosnotifychanneladmin-exceptions) );
    void destroy();
};
```


The **SupplierAdmin** interface defines the behavior of objects that create and manage lists of proxy consumers within an event channel. A event channel can have any number of **SupplierAdmin** instances associated with it. Each instance is responsible for creating and managing a list of proxy consumers that share a common set of QoS property settings, and a common set of filters. This feature enables clients to group proxy consumer objects within a channel into groupings that each support a set of suppliers with a common set of QoS requirements, and that make event forwarding decisions using a common set of filters.

The SupplierAdmin interface inherits QoSAdmin. This enables each SupplierAdmin to manage a set of QoS property settings. These QoS property settings are assigned as the default QoS property settings for any proxy consumer created by a SupplierAdmin.

The SupplierAdmin interface inherits from the FilterAdmin interface defined in CosNotifyFilter, enabling each SupplierAdmin to maintain a list of filters. These filters encapsulate subscriptions that apply to all proxy consumer objects that have been created by a given SupplierAdmin instance.

The SupplierAdmin interface also inherits from the NotifyPublish interface defined in CosNotifyComm. This inheritance enables a SupplierAdmin to be the target of an offer_change request made by a supplier, and for the change in event types being offered to be shared by all proxy consumer that were created by the target SupplierAdmin. This optimizes the notification of a group of proxy consumers that have been created by the same SupplierAdmin of changes to the types of events being offered by suppliers.

The SupplierAdmin interface also inherits from `CosEventChannelAdmin::SupplierAdmin`. This inheritance enables clients to use the SupplierAdmin interface to create pure OMG event service style proxy consumer objects. Proxy consumer objects created in this manner do not support configuration of QoS properties, and do not have associated filters. Proxy consumer objects created through the inherited `CosEventChannelAdmin::SupplierAdmin` interface do not have unique identifiers associated with them, whereas proxy consumers created by invoking the operations supported by the SupplierAdmin interface do.

The SupplierAdmin interface supports a read-only attribute that maintains a reference to the EventChannel that created a given SupplierAdmin. The SupplierAdmin interface also supports a read-only attribute that contains a numeric identifier that is assigned to a `SupplierAdmin` the event channel that creates it. This identifier is unique among all SupplierAdmins created by a given channel.

A SupplierAdmin maintains a list of filters that are applied to all proxy consumers it creates. Each proxy consumer also supports a list of filters that apply only that proxy. When combining these two lists during the evaluation of an event, either `AND` or `OR` semantics can be applied. The choice is determined by an input flag upon creation of the SupplierAdmin, and the operator that is used for this purpose by a given SupplierAdmin is maintained in a read-only attribute.

Each `SupplierAdmin` assigns a unique numeric identifier to each proxy consumer it maintains. The `SupplierAdmin` interface supports attributes that maintain the list of these unique identifiers associated with the proxy pull and the proxy push consumers created by a given `SupplierAdmin`. The `SupplierAdmin` interface also supports an operation which, when provided with the unique identifier of a proxy consumer, returns the object reference of that proxy consumer object. Finally, the `SupplierAdmin` interface supports operations that can create the various styles of proxy consumers supported by the event channel.

`SupplierAdmin::MyID`

```
readonly attribute [AdminID](#cosnotifychanneladmin-data-types) MyID;
```

Maintains the unique identifier of the target `SupplierAdmin`. This ID is assigned to it upon creation by the event channel.

`SupplierAdmin::MyChannel`

```
readonly attribute EventChannel MyChannel;
```

Maintains an object reference to the event channel that created the `SupplierAdmin`.

`SupplierAdmin::MyOperator`

```
readonly attribute [InterFilterGroupOperator](#cosnotifychanneladmin-data-types) MyOperator;;
```

Maintains the information regarding whether `AND` or `OR` semantics are used during the evaluation of events when combining the filters associated with the target **`SupplierAdmin`** and those defined on a given proxy consumer.

`SupplierAdmin::pull_consumers`

```
readonly attribute [ProxyIDSeq](#cosnotifychanneladmin-data-types) pull_consumers;
```

Contains the list of unique identifiers assigned by a `SupplierAdmin` to each pull-style proxy consumer it has created.

`SupplierAdmin::push_consumers`

```
readonly attribute [ProxyIDSeq](#cosnotifychanneladmin-data-types)
push_consumers;
```

Contains the list of unique identifiers assigned by a `SupplierAdmin` to each push-style proxy consumer it has created.

`SupplierAdmin::get_proxy_consumer()`

```
[ProxyConsumer](../cosnotifychanneladminproxyconsumer_interface/
cosnotifychanneladminproxyconsumer_interface.md) get_proxy_consumer ( in
[ProxyID](#cosnotifychanneladmin-data-types) proxy_id )
raises ( [ProxyNotFound](#cosnotifychanneladmin-exceptions) );
```

Returns an object reference to the proxy consumer whose unique identifier was specified.

Parameters

```
proxy_id
```

The numeric identifier associated with one of the proxy consumers created by the target `SupplierAdmin`.

Exceptions

```
[ProxyNotFound](#cosnotifychanneladmin-exceptions)
```

The input parameter does not correspond to the unique identifier of a proxy consumer created by the target `SupplierAdmin`.

`SupplierAdmin::obtain_notification_pull_consumer()`

```
[ProxyConsumer](../cosnotifychanneladminproxyconsumer_interface/
cosnotifychanneladminproxyconsumer_interface.md)
obtain_notification_pull_consumer (
    in [ClientType](#cosnotifychanneladmin-data-types) ctype,
    out [ProxyID](#cosnotifychanneladmin-data-types) proxy_id)
raises ( [AdminLimitExceeded](#cosnotifychanneladmin-exceptions) );
```

Creates an instances of a pull-style proxy consumers and returns an object reference to the new proxy.

Three varieties of pull-style proxy consumers are defined:

- The [ProxyPullConsumer](#) interface supports connections to pull suppliers that send events as `Anys`.
- The [StructuredProxyPullConsumer](#) interface supports connections to pull suppliers that send structured events.
- The [SequenceProxyPullConsumer](#) interface supports connections to pull suppliers that send sequences of structured events.

The input parameter flag indicates which type of pull style proxy to create.

The target `SupplierAdmin` creates the new pull-style proxy consumer and assigns it a numeric identifier that is unique among all proxy consumers it has created.

Parameters

<code>ctype</code>	A flag indicating which style of pull-style proxy consumer to create.
<code>proxy_id</code>	The unique identifier of the new proxy consumer.

Exceptions

`[AdminLimitExceeded](#cosnotifychanneladmin-exceptions)`

The number of consumers currently connected to the channel that the target `SupplierAdmin` is associated with exceeds the value of the `MaxSuppliers` administrative property.

`SupplierAdmin::obtain_notification_push_consumer()`

```
[ProxyConsumer](../cosnotifychanneladminproxyconsumer_interface/
cosnotifychanneladminproxyconsumer_interface.md)
obtain_notification_push_consumer (
    in [ClientType](#cosnotifychanneladmin-data-types) ctype,
    out [ProxyID](#cosnotifychanneladmin-data-types) proxy_id)
    raises ( [AdminLimitExceeded](#cosnotifychanneladmin-exceptions) );
```

Creates an instance of a push-style proxy supplier and returns an object reference to the new proxy.

Three varieties of push-style proxy consumer are defined:

- The [ProxyPushConsumer](#) interface supports connections to push consumers that receive events as `Anys`.
- The [StructuredProxyPushConsumer](#) interface supports connections to push consumers that receive structured events.

- The [SequenceProxyPushConsumer](#) interface supports connections to push consumers that receive sequences of structured events.

The input parameter flag indicates which type of push-style proxy to create.

The target SupplierAdmin creates the new push-style proxy consumer and assigns it a numeric identifier that is unique among all proxy suppliers it has created.

Parameters

<code>ctype</code>	A flag that indicates the type of push-style proxy consumer to create.
<code>proxy_id</code>	The unique identifier of the new proxy consumer.

Exceptions

```
[AdminLimitExceeded] (#cosnotifychanneladmin-exceptions)
```

The number of consumers currently connected to the channel that the target `SupplierAdmin` is associated with exceeds the value of the `MaxSuppliers` administrative property.

`SupplierAdmin::destroy()`

```
void destroy();
```

Iteratively destroys each proxy under the administration of the target object, and finally destroys the target object itself. When destroying each object, it frees any storage associated with the object, and then invalidates the object's IOR.

CosNotifyComm Module

`CosNotifyComm` specifies the following interfaces to instantiate notification service clients:

<code>[PushConsumer](../ cosnotifycommpushconsumer_interface/ cosnotifycommpushconsumer_interface. md)</code>	<code>[PushSupplier](../ cosnotifycommpushsupplier_interface/ cosnotifycommpushsupplier_interface. md)</code>
<code>[PullConsumer](../ cosnotifycommpullconsumer_interface/ cosnotifycommpullconsumer_interface. md)</code>	<code>[PullSupplier](../ cosnotifycommpullsupplier_interface/ cosnotifycommpullsupplier_interface. md)</code>
<code>[StructuredPushConsumer](../ cosnotifycommstructuredpushconsumer_ interface/ cosnotifycommstructuredpushconsumer_ interface.md)</code>	<code>[StructuredPushSupplier](../ cosnotifycommstructuredpushsupplier_ interface/ cosnotifycommstructuredpushsupplier_ interface.md)</code>
<code>[StructuredPullConsumer](../ cosnotifycommstructuredpullconsumer_ interface/ cosnotifycommstructuredpullconsumer_ interface.md)</code>	<code>[StructuredPullSupplier](../ cosnotifycommstructuredpullsupplier_ interface/ cosnotifycommstructuredpullsupplier_ interface.md)</code>
<code>[SequencePushConsumer](../ cosnotifycommsequencepushconsumer_i nterface/ cosnotifycommsequencepushconsumer_i nterface.md)</code>	<code>[SequencePushSupplier](../ cosnotifycommsequencepushsupplier_i nterface/ cosnotifycommsequencepushsupplier_i nterface.md)</code>
<code>[SequencePullConsumer](../ cosnotifycommsequencepullconsumer_i nterface/ cosnotifycommsequencepullconsumer_i nterface.md)</code>	<code>[SequencePullSupplier](../ cosnotifycommsequencepullsupplier_i nterface/ cosnotifycommsequencepullsupplier_i nterface.md)</code>

The module also specifies the [NotifyPublish](#) and [NotifySubscribe](#) interfaces to facilitate informing notification clients about subscription and publication changes.

CosNotifyComm Exceptions

CosNotifyComm::InvalidEventType Exception

```
exception InvalidEventType{ CosNotification::EventType type };
```

Raised when the specified EventType is not syntactically correct. It returns the name of the invalid event type.

Note

The Orbix notification service does not throw this exception.

CosNotifyComm::NotifyPublish Interface

```
interface NotifyPublish {
    void [offer_change](#cosnotifycommnotifypublish-interface) (
        in CosNotification::EventTypeSeq added,
        in CosNotification::EventTypeSeq removed )
        raises ( [InvalidEventType](#cosnotifycomm-exceptions) );
};
```

The `NotifyPublish` interface supports an operation that allows a supplier to announce, or publish, the names of the event types it supplies. It is an abstract interface which is inherited by all notification service consumer interfaces, and it enables suppliers to inform consumers supporting this interface of the types of events they intend to supply.

`NotifyPublish::offer_change()`

```
void offer_change (
    in CosNotification::EventTypeSeq added,
    in CosNotification::EventTypeSeq removed )
    raises ( [InvalidEvent](#cosnotifycomm-exceptions)Type );
```

Allows a supplier of notifications to announce, or publish, the names of the types of events it supplies.

Note

Each event type name consists of two components: the name of the domain in which the event type has meaning, and the name of the actual event type. Either component of a type name may specify a complete domain/event type name, a domain/event type name containing the wildcard “*” character, or the special event type name “%ALL”.

Parameters

<code>added</code>	A sequence of event type names specifying those event types which the event supplier plans to supply.

<code>removed</code>	Sequence of event type names specifying those event types which the client no longer plans to supply.

Exceptions

`[InvalidEventType] (#cosnotifycomm-exceptions)`

One of the event type names supplied in either input parameter is syntactically invalid. In this case, the invalid name is returned in the type field of the exception.

CosNotifyComm::NotifySubscribe Interface

```
interface NotifySubscribe {
    void [subscription_change](#cosnotifycommnotifysubscribe-interface)(
        in CosNotification::EventTypeSeq added,
        in CosNotification::EventTypeSeq removed )
        raises ( [InvalidEventType](#cosnotifycomm-exceptions) );
};
```

The `NotifySubscribe` interface supports an operation allowing a consumer to inform suppliers of the event types it wishes to receive. It is an abstract interface that is inherited by all notification service supplier interfaces. Its main purpose is to enable consumers to inform suppliers of the event types they are interested in, ultimately enabling the suppliers to avoid supplying events that are not of interest to any consumer.

`NotifySubscribe::subscription_change()`

```
void subscription_change(
    in CosNotification::EventTypeSeq added,
    in CosNotification::EventTypeSeq removed )
    raises ( [InvalidEventType](#cosnotifycomm-exceptions) );
```

Allows a consumer to inform suppliers of the event types it wishes to receive.

Note

Each event type name is comprised of two components: the name of the domain in which the event type has meaning, and the name of the actual event type. Also note that either component of a type name may specify a complete domain/event type name, a domain/event type name containing the wildcard '*' character, or the special event type name "%ALL".

Parameters

added	A sequence of event type names specifying the event types the consumer wants to add to its subscription list.

removed

A sequence of event type names specifying the event types the consumer wants to remove from its subscription list.

Exceptions

[InvalidEventType] (#cosnotifycomm-exceptions)

One of the event type names supplied in either input parameter is syntactically invalid. The invalid name is returned in the type field of the exception.

CosNotifyComm::PullConsumer Interface

```
interface PullConsumer :
    [NotifyPublish](../cosnotifycommnotifypublish_interface/
cosnotifycommnotifypublish_interface.md),
    CosEventComm::PullConsumer
{
};
```

The `PullConsumer` interface inherits all the operations of `CosEventComm::PullConsumer`. In addition, the `PullConsumer` interface inherits the [NotifyPublish](#) interface described above, which enables a supplier to inform an instance supporting this interface whenever there is a change to the types of events it intends to produce.

Note

An object supporting `PullConsumer` can receive all events that were supplied to its associated channel. How events supplied to the channel in other forms are internally mapped for delivery to a `PullConsumer` is summarized in the *CORBA Notification Service Guide*.

CosNotifyComm::PullSupplier Interface

```
interface PullSupplier :  
    [NotifySubscribe](../cosnotifycommnotifysubscribe_interface/  
cosnotifycommnotifysubscribe_interface.md),  
    CosEventComm::PullSupplier  
{  
};
```

The `PullSupplier` interface inherits all the operations of `CosEventComm::PullSupplier`. In addition, the `PullSupplier` interface inherits the [NotifySubscribe](#) interface described above, which enables a consumer to inform an instance supporting this interface whenever there is a change to the types of events it wishes to receive.

Note

An object supporting the `PullSupplier` interface can transmit events that can potentially be received by any consumer connected to the channel. How events supplied to the channel in other forms are translated is summarized in the *CORBA Notification Service Guide*

CosNotifyComm::PushConsumer Interface

```
interface PushConsumer :  
    [NotifyPublish](../cosnotifycommnotifypublish_interface/  
cosnotifycommnotifypublish_interface.md),  
    CosEventComm::PushConsumer  
{  
};
```

The `PushConsumer` interface inherits all the operations of `CosEventComm::PushConsumer`. In addition, the `PushConsumer` interface inherits the [NotifyPublish](#) interface described above, which enables a supplier to inform an instance supporting this interface whenever there is a change to the types of events it intends to produce.

Note

An object supporting `PushConsumer` can receive all events that were supplied to its associated channel. How events supplied to the channel in other forms are internally mapped for delivery to a `PushConsumer` is summarized in the *CORBA Notification Service Guide*.

CosNotifyComm::PushSupplier Interface

```
interface PushSupplier :  
    [NotifySubscribe](../cosnotifycommnotifysubscribe_interface/  
cosnotifycommnotifysubscribe_interface.md),  
    CosEventComm::PushSupplier  
{  
};
```

The `PushSupplier` interface inherits all the operations of `CosEventComm::PushSupplier`. In addition, the `PushSupplier` interface inherits the `NotifySubscribe` interface described above, which enables a consumer to inform an instance supporting this interface whenever there is a change to the types of events it wishes to receive.

Note

An object supporting the `PushSupplier` interface can transmit events that can potentially be received by any consumer connected to the channel. How events supplied to the channel in other forms are translated is summarized in the *CORBA Notification Service Guide*

CosNotifyComm::SequencePullConsumer Interface

```
interface SequencePullConsumer : [NotifyPublish](../
cosnotifycommnotifypublish_interface/cosnotifycommnotifypublish_interface.md)
{
    void [disconnect_sequence_pull_consumer()]
    (#cosnotifycommsequencepullconsumer-interface);
};
```

The `SequencePullConsumer` interface defines an operation to disconnect the pull consumer from its associated supplier. The `SequencePullConsumer` interface inherits [NotifyPublish](#), which enables a supplier to inform an instance supporting this interface whenever there is a change to the types of events it intends to produce.

Note

An object supporting the `SequencePullConsumer` interface can receive all events that were supplied to its associated channel, including events supplied in a form other than a sequence of structured events. How events supplied to the channel in other forms are internally mapped into a sequence of structured events for delivery to a `SequencePullConsumer` is summarized in the *CORBA Notification Service Guide*.

`SequencePullConsumer::disconnect_sequence_pull_consumer()`

```
void disconnect_sequence_pull_consumer();
```

Terminates a connection between the target `SequencePullConsumer` and its associated supplier. The target `SequencePullConsumer` releases all resources allocated to support the connection, and disposes of its own object reference.

CosNotifyComm::SequencePullSupplier Interface

```
interface SequencePullSupplier : [NotifySubscribe](../
cosnotifycommnotifysubscribe_interface/
cosnotifycommnotifysubscribe_interface.md)
{
    CosNotification::EventBatch [pull_structured_events]
    (#cosnotifycommsequencepullsupplier-interface)(
        in long max_number )
        raises(CosEventComm::Disconnected);
    CosNotification::StructuredEvent [try_pull_structured_events]
    (#cosnotifycommsequencepullsupplier-interface)(
        in long max_number,
        out boolean has_event)
        raises(CosEventComm::Disconnected);
    void [disconnect_sequence_pull_supplier()]
    (#cosnotifycommsequencepullsupplier-interface);
};
```

The `SequencePullSupplier` interface supports operations that enable suppliers to transmit sequences of structured events using the pull model. It also defines an operation to disconnect the pull supplier from its associated consumer. The `SequencePullSupplier` interface inherits [NotifySubscribe](#), which enables a consumer to inform an instance supporting this interface whenever there is a change to the types of events it is interested in receiving.

Note

An object supporting the `SequencePullSupplier` interface can transmit events that can be received by any consumer connected to the channel, including those which consume events in a form other than a sequence of structured events. How events supplied to the channel in the form of a sequence of structured events are internally mapped into different forms for delivery to consumers that receive events in a form other than the a sequence of structured events is summarized in the *CORBA Notification Service Guide*.

`SequencePullSupplier::pull_structured_events()`

```
CosNotification::EventBatch pull_structured_events(
    in long max_number )
    raises(CosEventComm::Disconnected);
```

Blocks until a sequence of structured events is available for transmission, at which time it returns the sequence containing events to be delivered to its connected consumer proxy.

The amount of time the supplier packs events into the sequence before transmitting it, along with the maximum size of any sequence it transmits (regardless of the input parameter), are controlled by QoS property settings as described in the *CORBA Notification Service Guide*.

Parameters

max_number

The maximum length of the sequence returned.

Exceptions

Disconnected

The operation was invoked on a `SequencePullSupplier` that is not currently connected to a consumer proxy.

`SequencePullSupplier::try_pull_structured_events()`

```
CosNotification::StructuredEvent try_pull_structured_events(
    in long max_number,
    out boolean has_event)
    raises(CosEventComm::Disconnected);
```

Returns a sequence of a structured events that contains events being delivered to its connected consumer, if such a sequence is available for delivery at the time the operation was invoked:

- If an event sequence is available for delivery and is returned as the result, the output parameter `has_event` is set to `TRUE`.
- If no event sequence is available to return upon invocation, the operation returns immediately with the value of the output parameter set to `FALSE`. In this case, the return value does not contain a valid event sequence.

Parameters

<code>max_number</code>	The maximum length of the sequence returned.
<code>has_event</code>	An output parameter of type boolean that indicates whether or not the return value actually contains a sequence of events.

Exceptions

Disconnected

This operation was invoked on a `SequencePullSupplier` that is not currently connected to a consumer proxy.

`SequencePullSupplier::disconnect_sequence_pull_supplier()`

```
void disconnect_sequence_pull_supplier();
```

Terminates a connection between the target `SequencePullSupplier` and its associated consumer. The target `SequencePullSupplier` releases all resources allocated to support the connection, and disposes of its own object reference.

CosNotifyComm::SequencePushConsumer Interface

```
interface SequencePushConsumer : [NotifyPublish](../
cosnotifycommnotifypublish_interface/cosnotifycommnotifypublish_interface.md)
{
    void [push_structured_events](#it_notifycommgroupsequencepushconsumer-
interface)(
        in CosNotification::EventBatch notifications)
        raises(CosEventComm::Disconnected);
    void [disconnect_sequence_push_consumer()]
    (#it_notifycommgroupsequencepushconsumer-interface);
};
```

The `SequencePushConsumer` interface supports an operation that enables consumers to receive sequences of structured events using the push model. It also defines an operation to disconnect the push consumer from its associated supplier. The `SequencePushConsumer` interface inherits `NotifyPublish`, which enables a supplier to inform an instance supporting this interface whenever there is a change to the types of events it intends to produce.

Note

An object supporting the `SequencePushConsumer` interface can receive all events which are supplied to its associated channel, including events supplied in a form other than a sequence of structured events. How events supplied to the channel in other forms are internally mapped into a sequence of structured events for delivery to a `SequencePushConsumer` is summarized in the *CORBA Notification Service Guide*.

`SequencePushConsumer::push_structured_events()`

```
void push_structured_events(
    in CosNotification::EventBatch notifications)
    raises(CosEventComm::Disconnected);
```

Enables consumers to receive sequences of structured events by the push model.

The maximum number of events that are transmitted within a single invocation of this operation, along with the amount of time a supplier of sequences of structured events packs individual events into the sequence before invoking this operation, are controlled by QoS property settings as described in the *CORBA Notification Service Guide*.

Parameters

`notifications`

A parameter of type `EventBatch` as defined in the `CosNotification` module. Upon invocation, this parameter contains a sequence of structured events being delivered to the consumer by its associated supplier proxy.

Exceptions

`Disconnected`

The operation was invoked on a `SequencePushConsumer` instance that is not currently connected to a supplier proxy.

`SequencePushConsumer::disconnect_sequence_push_consumer()`

```
void disconnect_sequence_push_consumer();
```

Terminates a connection between the target `SequencePushConsumer` and its associated supplier proxy. The target `SequencePushConsumer` releases all resources allocated to support the connection, and disposes of its own object reference.

CosNotifyComm::SequencePushSupplier Interface

```
interface SequencePushSupplier : [NotifySubscribe](../
cosnotifycommnotifysubscribe_interface/
cosnotifycommnotifysubscribe_interface.md)
{
    void [disconnect_sequence_push_supplier()]
    (#cosnotifycommsequencepushsupplier-interface);
};
```

The `SequencePushSupplier` interface defines an operation that to disconnect the push supplier from its associated consumer proxy. In addition, the `SequencePushSupplier` interface inherits [NotifySubscribe](#), which enables a consumer to inform an instance supporting this interface whenever there is a change to the types of events it is interested in receiving.

Note

An object supporting the `SequencePushSupplier` interface can transmit events that can be received by any consumer connected to the channel, including those which consume events in a form other than a sequence of structured events. How events supplied to the channel in the form of a sequence of structured events are internally mapped into different forms for delivery to consumers which receive events in a form other than a sequence of structured events is summarized in the *CORBA Notification Service Guide*.

`SequencePushSupplier::disconnect_sequence_push_supplier()`

```
void disconnect_sequence_push_supplier();
```

Terminates a connection between the target `SequencePushSupplier` and its associated consumer. The target `SequencePushSupplier` releases all resources allocated to support the connection, and disposes of its own object reference.

CosNotifyComm::StructuredPullConsumer Interface

```
interface StructuredPullConsumer : [NotifyPublish](../
cosnotifycommnotifypublish_interface/cosnotifycommnotifypublish_interface.md)
{
    void [disconnect_structured_pull_consumer()]
    (#cosnotifycommstructuredpullconsumer-interface);
};
```

The `StructuredPullConsumer` defines an operation that can be invoked to disconnect the pull consumer from its associated supplier. In addition, the `StructuredPullConsumer` interface inherits the `NotifyPublish` interface, which enables a supplier to inform an instance supporting this interface whenever there is a change to the types of events it intends to produce.

Note

An object supporting the `StructuredPullConsumer` interface can receive all events that were supplied to its associated channel, including events supplied in a form other than a structured event. How events supplied to the channel in other forms are internally mapped into a structured event for delivery to a `StructuredPullConsumer` is summarized in the *CORBA Notification Service Guide*.

`StructuredPullConsumer::disconnect_structured_pull_consumer()`

```
void disconnect_structured_pull_consumer();
```

Terminates a connection between the target `StructuredPullConsumer`, and its associated supplier proxy. The target `StructuredPullConsumer` releases all resources allocated to support the connection, and disposes of its own object reference.

CosNotifyComm::StructuredPullSupplier Interface

```
interface StructuredPullSupplier : [NotifySubscribe](../
cosnotifycommnotifysubscribe_interface/
cosnotifycommnotifysubscribe_interface.md)
{
    CosNotification::StructuredEvent [pull_structured_event()]
    (#cosnotifycommstructuredpullsupplier-interface)
    raises(CosEventComm::Disconnected);
    CosNotification::StructuredEvent [try_pull_structured_event]
    (#cosnotifycommstructuredpullsupplier-interface)(
        out boolean has_event)
    raises(CosEventComm::Disconnected);
    void [disconnect_structured_pull_supplier()]
    (#cosnotifycommstructuredpullsupplier-interface);
};
```

The `StructuredPullSupplier` interface supports operations that enable suppliers to transmit structured events by the pull model. It also defines an operation to disconnect the pull supplier from its associated consumer proxy. In addition, the `StructuredPullSupplier` interface inherits the [NotifySubscribe](#) interface, which enables a consumer to inform an instance supporting this interface whenever there is a change to the types of events it is interested in receiving.

Note

An object supporting the `StructuredPullSupplier` interface can transmit events that can potentially be received by any consumer connected to the channel, including those which consume events in a form other than a structured event. How events supplied to the channel in other forms are translated is summarized in the *CORBA Notification Service Guide*

`StructuredPullSupplier::pull_structured_event()`


```
CosNotification::StructuredEvent pull_structured_event()
    raises(CosEventComm::Disconnected);
```

Blocks until an event is available for transmission, at which time it returns an instance of a structured event containing the event being delivered to its connected consumer proxy.

Exceptions

Disconnected

The operation was invoked on a `StructuredPullSupplier` that is not currently connected to a consumer proxy.

`StructuredPullSupplier::try_pull_structured_event()`

```
CosNotification::StructuredEvent try_pull_structured_event(
    out boolean has_event)
    raises(CosEventComm::Disconnected);
```

If an event is available for delivery at the time the operation was invoked, the method returns a structured event that contains the event being delivered to its connected consumer and the output parameter of the operation is set to `TRUE`. If no event is available to return upon invocation, the operation returns immediately with the value of the output parameter set to `FALSE`. In this case, the return value does not contain a valid event.

Parameters

`has_event`

An output parameter of type `boolean` that indicates whether or not the return value actually contains an event.

Exceptions

Disconnected

The operation was invoked on a `StructuredPullSupplier` that is not currently connected to a consumer proxy.

`StructuredPullSupplier::disconnect_structured_pull_supplier()`

```
void disconnect_structured_pull_supplier();
```

Terminates a connection between the target `StructuredPullSupplier` and its associated consumer. The target `StructuredPullSupplier` releases all resources allocated to support the connection, and disposes of its own object reference.

CosNotifyComm::StructuredPushConsumer Interface

```
interface StructuredPushConsumer : [NotifyPublish](../
cosnotifycommnotifypublish_interface/cosnotifycommnotifypublish_interface.md)
{
    void [push_structured_event](#cosnotifycommstructuredpushconsumer-
interface)(
        in CosNotification::StructuredEvent notification)
        raises(CosEventComm::Disconnected);
    void [disconnect_structured_push_consumer()]
    (#cosnotifycommstructuredpushconsumer-interface);
};
```

The `StructuredPushConsumer` interface supports an operation enabling consumers to receive structured events by the push model. It also defines an operation to disconnect the push consumer from its associated proxy supplier. In addition, the `StructuredPushConsumer` interface inherits the [NotifyPublish](#) interface described above, which enables a supplier to inform an instance supporting this interface whenever there is a change to the types of events it intends to produce.

Note

An object supporting the `StructuredPushConsumer` interface can receive all events that were supplied to its associated channel, including events supplied in a form other than a structured event. How events supplied to the channel in other forms are internally mapped into a structured event for delivery to a `StructuredPushConsumer` is summarized in the *CORBA Notification Service Guide*.

`StructuredPushConsumer::push_structured_event()`

```
void push_structured_event(
    in CosNotification::StructuredEvent notification)
    raises(CosEventComm::Disconnected);
```

Enables consumers to receive structured events by the push model.

Parameters

`notification`

A parameter of type `StructuredEvent` as defined in the `CosNotificationmodule`. When the method returns this parameter contains a structured event being delivered to the consumer by its proxy supplier.

Exceptions

Disconnected

This operation was invoked on a `StructuredPushConsumer` instance that is not currently connected to a proxy supplier.

`StructuredPushConsumer::disconnect_structured_push_consumer()`

```
void disconnect_structured_push_consumer();
```

Terminates a connection between the target `StructuredPushConsumer` and its associated proxy supplier. That the target `StructuredPushConsumer` releases all resources allocated to support the connection, and disposes of its own object reference.

CosNotifyComm::StructuredPushSupplier Interface

```
interface StructuredPushSupplier : [NotifySubscribe](../
cosnotifycommnotifysubscribe_interface/
cosnotifycommnotifysubscribe_interface.md) {
    void [disconnect_structured_push_supplier()]
    (#cosnotifycommstructuredpushsupplier-interface);
};
```

The `StructuredPushSupplier` interface supports the behavior of objects that transmit structured events using push-style communication. It defines an operation that can be invoked to disconnect the push supplier from its associated consumer proxy. In addition, the `StructuredPushSupplier` interface inherits `NotifySubscribe`, which enables a consumer to inform an instance supporting this interface whenever there is a change to the types of events it is interested in receiving.

Note

An object supporting the `StructuredPushSupplier` interface can transmit events which can potentially be received by any consumer connected to the channel, including those which consume events in a form other than a structured event. How events supplied to the channel are translated is summarized in the *CORBA Notification Service Guide*.

`StructuredPushSupplier::disconnect_structured_push_supplier()`

```
void disconnect_structured_push_supplier();
```

Terminates a connection between the target `StructuredPushSupplier`, and its associated consumer. The target `StructuredPushSupplier` releases all resources allocated to support the connection, and disposes of its own object reference.

CosNotifyFilter Module

The `CosNotifyFilterModule` specifies the following interfaces to support event filtering:

```
[Filter](../cosnotifyfilterfilter_interface/
cosnotifyfilterfilter_interface.md)
[FilterFactory](../cosnotifyfilterfilterfactory_interface/
cosnotifyfilterfilterfactory_interface.md)
[MappingFilter](../cosnotifyfiltermappingfilter_interface/
cosnotifyfiltermappingfilter_interface.md)
[FilterAdmin](../cosnotifyfilterfilteradmin_interface/
cosnotifyfilterfilteradmin_interface.md)
```

In addition to these interfaces the module specifies several data types and exceptions related to event filtering.

CosNotifyFilter Data Types

CosNotifyFilter::ConstraintID Data Type

```
typedef long ConstraintID;
```

Identifies a constraint.

CosNotifyFilter::ConstraintExp Data Structure

```
struct ConstraintExp
{
    CosNotification::EventTypeSeq event_types;
    string                        constraint_expr;
};
```

Contains a constraint expression and a list of events to check against. The `constraint_expr` member is a string that conforms to the Trader constraint grammar. For more information on the constraint grammar, see the *CORBA Notification Service Guide*.

CosNotifyFilter::ConstraintIDSeq Data Type

```
typedef <[ConstraintID](#cosnotifyfilter-data-types)> ConstraintIDSeq;
```

Contains a list of constraint ID.

CosNotifyFilter::ConstraintExpSeq Data Type

```
typedef sequence<[ConstraintExp](#cosnotifyfilter-data-types)>
ConstraintExpSeq;
```

Contains a list of constraint expressions.

CosNotifyFilter::ConstraintInfo Data Structure

```
struct ConstraintInfo
{
    [ConstraintExp](#cosnotifyfilter-data-types) constraint_expression;
    [ConstraintID](#cosnotifyfilter-data-types) constraint_id;
}
```

Specifies an instantiated constraint.

CosNotifyFilter::ConstraintInfoSeq Data Type

```
typedef sequence<[ConstraintInfo](#cosnotifyfilter-data-types)>
ConstraintInfoSeq;
```

Contains a list of instantiated constraints.

CosNotifyFilter::FilterID Data Type

```
typedef long FilterID;
```

Identifies an instantiated filter. It is unique to the object to which it is attached.

CosNotifyFilter::FilterIDSeq Data Type

```
typedef sequence<FilterID> FilterIDSeq;
```

Contains a list of FilterIds.

CosNotifyFilter::MappingConstraintPair Data Structure

```
struct MappingConstraintPair
{
    ConstraintExp constraint_expression;
    any          result_to_set;
}
```

Specifies a constraint expression and the value to set if the event matches the constraint expression.

CosNotifyFilter::MappingConstraintPairSeq Data Type

```
typedef sequence<[MappingConstraintPair](#cosnotifyfilter-data-types)>
MappingConstraintPairSeq
```

Contains a list of mapping filter constraint/value pairs.

CosNotifyFilter::MappingConstraintInfo Data Structure

```
struct MappingConstraintInfo
{
    [ConstraintExp](#cosnotifyfilter-data-types) constraint_expression;
    [ConstraintID](#cosnotifyfilter-data-types)  constraint_id;
    any          value;
}
```

Specifies a mapping constraint that has been instantiated.

CosNotifyFilter::MappingConstraintInfoSeq Data Types

```
typedef sequence<[MappingConstraintInfo](#cosnotifyfilter-data-types)>
MappingConstraintInfoSeq;
```

Contains a list of instantiated mapping filter constraint/value pairs.

CosNotifyFilter::CallbackID Data Type


```
typedef long CallbackID;
```

Holds an identifier for a callback registered with `attach_callback`.

CosNotifyFilter::CallbackIDSeq Data Type

```
typedef sequence<> CallbackIDSeq;
```

Contains a list of callback IDs.

CosNotifyFilter Exceptions

CosNotifyFilter::UnsupportedFilterableData Exception

```
exception UnsupportedFilterableData {};
```

Raised if the input parameter contains data that the `match` operation is not designed to handle. For example, the filterable data contains a field whose name corresponds to a standard event field that has a numeric value, but the actual value associated with this field name within the event is a string.

CosNotifyFilter::InvalidGrammar Exception

```
exception InvalidGrammar {};
```

Raised when creating a filter. If the string passed to the filter factory specifies a grammar that is not supported, the factory will throw `InvalidGrammar`.

Note

Orbix notification service supports the `EXTENDED_TCL` grammar.

CosNotifyFilter::InvalidConstraint Exception

```
exception InvalidConstraint {[ConstraintExp](#cosnotifyfilter-data-types)
  constr};
```

Raised during the creation of constraints. If the string specifying the constraint is syntactically incorrect, `InvalidConstraint` is thrown. It returns the invalid constraint.

CosNotifyFilter::ConstraintNotFound Exception

```
exception ConstraintNotFound {ConstraintID id};
```

Raised when a specified constraint ID cannot be resolved to a constraint attached to the target filter object. It returns the ID that cannot be resolved.

CosNotifyFilterFilter::CallbackNotFound Exception

```
exception CallbackNotFound {};
```

Raised when the specified callback ID cannot be resolved to a callback object attached to the target filter object.

CosNotifyFilter::InvalidValue Exception

```
exception InvalidValue {[ConstraintExp](#cosnotifyfilter-data-types) constr;
  any value};
```

Raised when the `type_code` of the value associated with the mapping filter constraint does not match the `value_type` of the target mapping filter object.

CosNotifyFilter::FilterNotFound Exception

```
exception FilterNotFound {};
```

Raised if the specified filter ID cannot be resolved to a filter associated with the target object.

CosNotifyFilter::Filter Interface

```

interface Filter
{
    readonly attribute string constraint_grammar;
    [ConstraintInfoSeq](#cosnotifyfilter-data-types) [add_constraints]
    (#cosnotifyfilterfilter-interface)(
        in [ConstraintExpSeq](#cosnotifyfilter-data-types) constraint_list)
    raises ([InvalidConstraint](#cosnotifyfilter-exceptions));
    void (
        in [ConstraintIDSeq](#cosnotifyfilter-data-types) del_list,
        in [ConstraintInfoSeq](#cosnotifyfilter-data-types) modify_list)
    raises ([InvalidConstraint](#cosnotifyfilter-exceptions),
    [ConstraintNotFound](#cosnotifyfilter-exceptions));
    [ConstraintInfoSeq](#cosnotifyfilter-data-types) (
        in [ConstraintIDSeq](#cosnotifyfilter-data-types) id_list)
    raises ([ConstraintNotFound](#cosnotifyfilter-exceptions));
    [ConstraintInfoSeq](#cosnotifyfilter-data-types) ();
    void ();
    void [destroy()](#cosnamingbindingiterator-interface);
    boolean ( in any filterable_data )
    raises ([UnsupportedFilterableData](#cosnotifyfilter-exceptions));
    boolean (
        in CosNotification::StructuredEvent filterable_data )
    raises ([UnsupportedFilterableData](#cosnotifyfilter-exceptions));
    boolean match_typed (
        in CosTrading::PropertySeq filterable_data )
    raises ([UnsupportedFilterableData](#cosnotifyfilter-exceptions));
    (
        in CosNotifyComm::NotifySubscribe callback);
    void ( in CallbackID callback)
    raises ([CallbackNotFound](#cosnotifyfilter-exceptions));
    [CallbackIDSeq](#cosnotifyfilter-data-types) ;
}; // Filter

```

The `Filter` interface defines the behaviors supported by filter objects. These objects encapsulate constraints that are used by the proxies and admins associated with an event channel. The proxies and admins use the constraint definitions to determine which events are forwarded, and which are discarded.

For more information on filters and the constraint language, see the *CORBA Notification Service Guide*.

The `Filter` interface supports operations to manage the constraints associated with a `Filter` instance, along with a read-only attribute to identify the constraint grammar used to evaluate the constraints associated with the instance. In addition, the `Filter` interface supports three variants of the `match` operation which are invoked by a proxy object upon receipt of an event—the specific variant selected depends upon whether the event is received as an `Any` or a structured event—to evaluate the object using the constraints associated with the filter object.

The `Filter` interface also supports operations enabling a client to associate any number of callbacks with the target filter object. The callbacks are notified each time there is a change to the list of event types the filter forwards through the event channel. Operations are also defined to support administration of this callback list by unique identifier.

`Filter::constraint_grammar`

```
readonly attribute string constraint_grammar;
```

`constraint_grammar` is a readonly attribute specifying the particular grammar used to parse the constraint expressions encapsulated by the target filter. The value of this attribute is set upon creation of a filter object.

A filter's constraints must be expressed using a particular constraint grammar because its member `match` operations must be able to parse the constraints to determine whether or not a particular event satisfies one of them.

Orbix supports an implementation of the `Filter` interface which supports the default constraint grammar described in the *CORBA Notification Service Guide*. The `constraint_grammar` attribute is set to the value `EXTENDED_TCL` when the target filter object supports this default grammar.

Other implementations can provide additional implementations of the `Filter` interface that support different constraint grammars, and thus the `constraint_grammar` attribute must be set to a different value upon creation of such a filter object.

`Filter::add_constraints()`

```
[ConstraintInfoSeq](#cosnotifyfilter-data-types) add_constraints(
    in [ConstraintExpSeq](#cosnotifyfilter-data-types)
    constraint_list)
    raises ([InvalidConstraint](#cosnotifyfilter-exceptions));
```

Associates one or more new constraints with the target filter object. Upon successful processing of all input constraint expressions, `add_constraints()` returns a [ConstraintInfoSeq](#) containing all of the constraints and the identifiers assigned to them by the filter.

If one or more of the constraints passed into `add_constraints()` is invalid, none of the constraints are added to the target filter.

Note

Once `add_constraints()` is invoked by a client, the target filter is temporarily disabled from usage by any proxy or admin it may be associated with. Upon completion of the operation, the target filter is re-enabled and can once again be used by associated proxies and admins to make event forwarding decisions.

Parameters

`constraint_list`

A sequence of constraint data structures using the constraint grammar supported by the target object.

Exceptions If any of the constraints in the input sequence is not a valid expression within the supported constraint grammar, the [InvalidConstraint](#) exception is raised. This exception contains as data the specific constraint expression that was determined to be invalid.

Filter::modify_constraints()

```
void modify_constraints (
    in [ConstraintIDSeq](#cosnotifyfilter-data-types) del_list,
    in [ConstraintInfoSeq](#cosnotifyfilter-data-types) modify_list)
    raises ([InvalidConstraint](#cosnotifyfilter-exceptions),
[ConstraintNotFound](#cosnotifyfilter-exceptions));
```

Modifies the constraints associated with the target filter object. This operation can be used both to remove constraints currently associated with the target filter, and to modify the constraint expressions of constraints currently associated with the filter.

If an exception is raised during the operation, no changes are made to the filter's constraints.

Note

Once `modify_constraints` is invoked by a client, the target filter is temporarily disabled from use by any proxy or admin. Upon completion of the operation, the target filter is re-enabled and can once again be used by associated proxies and admins to make event forwarding decisions.

Parameters

<code>del_list</code>	A sequence of numeric identifiers each of which should be associated with one of the constraints currently encapsulated by the target filter object.
<code>modify_list</code>	A sequence containing constraint structures and an associated numeric value. The numeric value in each element of the sequence is the unique identifier of one of the constraints encapsulated by the target filter.

Exceptions

<code>ConstraintNotFound</code>	Raised if any of the numeric values in either input sequences does not correspond to the unique identifier associated with any constraint encapsulated by the target filter. This exception contains the specific identifier that did not correspond to the identifier of some constraint encapsulated by the target filter.
<code>[InvalidConstraint] (#cosnotifyfilter-exceptions)</code>	Raised if any of the constraint expressions supplied in the second input sequence is not a valid expression in terms of the constraint grammar supported by the target object. This exception contains the specific constraint that was determined to be invalid.

Filter::get_constraints()

```
[ConstraintInfoSeq] (#cosnotifyfilter-data-types) get_constraints(in
[ConstraintIDSeq] (#cosnotifyfilter-data-types) id_list)
  raises ([ConstraintNotFound] (#cosnotifyfilter-exceptions));
```

Returns a sequence of data structures containing the input identifiers along with their associated constraint.

Parameters

`id_list`

A sequence of numeric values corresponding to the unique identifiers of constraints encapsulated by the target object.

Exceptions

```
[ConstraintNotFound] (#cosnotifyfilter-exceptions)
```

One of the input values does not correspond to the identifier of some encapsulated constraint. The exception contains that input value.

Filter::get_all_constraints()

```
[ConstraintInfoSeq] (#cosnotifyfilter-data-types) get_all_constraints();
```

Returns all of the constraints currently encapsulated by the target filter object.

Filter::remove_all_constraints()

```
void remove_all_constraints();
```

Removes all of the constraints currently encapsulated by the target filter. Upon completion, the target filter still exists but no constraints are associated with it.

Filter::destroy()

```
void destroy();
```

Destroys the target filter and invalidates its object reference.

Filter::match()

```
boolean match (in any filterable_data)
    raises ([UnsupportedFilterableData] (#cosnotifyfilter-exceptions));
```

Evaluates the filter constraints associated with the target filter against an event supplied to the channel in the form of a `CORBA::Any`. The operation returns `TRUE` if the input event satisfies one of the filter constraints, and `FALSE` otherwise.

The act of determining whether or not a given event passes a given filter constraint is specific to the type of grammar in which the filter constraint is specified.

Parameters

```
filterable_data
```

A `CORBA::Any` which contains an event to be evaluated.

Exceptions

```
[UnsupportedFilterableData] (#cosnotifyfilter-exceptions)
```

The input parameter contains data that the `match` operation is not designed to handle.

Filter::match_structured()

```
boolean match_structured(
    in CosNotification::StructuredEvent filterable_data )
    raises ( [UnsupportedFilterableData] (#cosnotifyfilter-exceptions) );
```

Evaluates the filter constraints associated with the target filter against a structured event. The operation returns `TRUE` if the input event satisfies one of the filter constraints, and `FALSE` otherwise.

The act of determining whether or not a given event passes a given filter constraint is specific to the type of grammar in which the filter constraint is specified.

Parameters

```
filterable_data
```

A `CosNotification::StructuredEvent` containing an event to be evaluated,

Exceptions

```
[UnsupportedFilterableData] (#cosnotifyfilter-exceptions)
```

The input parameter contains data that the `match` operation is not designed to handle.

Filter::attach_callback()


```
attach_callback (
    in CosNotifyComm::NotifySubscribe callback);
```

Associates an object supporting the CosNotifyComm::NotifySubscribe interface with the target filter. This operation returns a numeric value assigned to this callback that is unique to all such callbacks currently associated with the target filter.

After this operation has been successfully invoked on a filter, the filter invokes the subscription_change() method of all its associated callbacks each time the set of constraints associated with the filter is modified. This process informs suppliers in the filter's callback list of the change in the set of event types to which the filter's clients subscribe. With this information, suppliers can make intelligent decisions about which event types to produce.

Parameters

callback

The reference to an object supporting the CosNotifyComm::NotifySubscribe interface.

Filter::detach_callback()

```
void detach_callback(in callback)
raises ([CallbackNotFound](#cosnotifyfilter-exceptions));
```

Removes a callback object from the filter's callback list. Subsequent changes to the event type subscription list encapsulated by the target filter are no longer propagated to that callback object.

Parameters

callback

A unique identifiers associated with one of the callback objects attached to the target filter.

Exceptions

```
[CallbackNotFound](#cosnotifyfilter-exceptions)
```

The input value does not correspond to the unique identifier of a callback object currently attached to the target filter object.

Filter::get_callbacks()

```
[CallbackIDSeq] (#cosnotifyfilter-data-types) get_callbacks();
```

Returns all the unique identifiers for the callback objects attached to the target filter.

CosNotifyFilter::FilterAdmin Interface

```
interface FilterAdmin {
    [FilterID](#cosnotifyfilter-data-types) add_filter ( in [Filter](../
cosnotifyfilterfilter_interface/cosnotifyfilterfilter_interface.md)
new_filter );
    void remove_filter ( in [FilterID](#cosnotifyfilter-data-types) filter )
        raises ( [FilterNotFound](#cosnotifyfilter-exceptions) );
    [Filter](../cosnotifyfilterfilter_interface/
cosnotifyfilterfilter_interface.md) get_filter ( in [FilterID]
(#cosnotifyfilter-data-types) filter )
        raises ( [FilterNotFound](#cosnotifyfilter-exceptions) );
    [FilterIDSeq](#cosnotifyfilter-data-types) get_all_filters();
    void remove_all_filters();
};
```

The `FilterAdmin` interface defines operations enabling an object supporting this interface to manage a list of filters, each of which supports the [Filter](#) interface. This interface is an abstract interface which is inherited by all of the proxy and admin interfaces defined by the notification service.

`FilterAdmin::add_filter()`

```
[FilterID](#cosnotifyfilter-data-types) add_filter(in [Filter](../
cosnotifyfilterfilter_interface/cosnotifyfilterfilter_interface.md)
new_filter);
```

Appends a filter to the list of filters associated with the target object upon which the operation was invoked and returns an identifier for the filter.

Parameters

`new_filter`

A reference to an object supporting the [Filter](#) interface.

`FilterAdmin::remove_filter()`

```
void remove_filter(in [FilterID](#cosnotifyfilter-data-types) filter)
    raises ( [FilterNotFound](#cosnotifyfilter-exceptions) );
```

Removes the specified filter from the target object's list of filters.

Parameters

filter

A numeric value identifying a filter associated with the target object

Exceptions

[FilterNotFound](#cosnotifyfilter-exceptions)

The identifier does not correspond to a filter associated with the target object.

FilterAdmin::get_filter()

```
[Filter](../cosnotifyfilterfilter_interface/
cosnotifyfilterfilter_interface.md) get_filter (in [FilterID]
(#cosnotifyfilter-data-types) filter)
    raises ( [FilterNotFound](#cosnotifyfilter-exceptions) );
```

Returns the object reference to the specified filter.

Parameters

filter

A numeric value identifying a filter associated with the target object

Exceptions

[FilterNotFound](#cosnotifyfilter-exceptions)

The identifier does not correspond to a filter associated with the target object.

FilterAdmin::get_all_filters()

```
[FilterIDSeq] (#cosnotifyfilter-data-types) get_all_filters();
```

Returns the list of unique identifiers corresponding to all of the filters associated with the target object.

FilterAdmin::remove_all_filters()

```
void remove_all_filters();
```

Removes all filters from the filter list of the target object.

CosNotifyFilter::FilterFactory Interface

```
interface FilterFactory {
    [Filter](../cosnotifyfilterfilter_interface/
cosnotifyfilterfilter_interface.md) create_filter (
        in string constraint_grammar)
        raises ([InvalidGrammar](#cosnotifyfilter-exceptions));
    [MappingFilter](../cosnotifyfiltermappingfilter_interface/
cosnotifyfiltermappingfilter_interface.md) create_mapping_filter (
        in string constraint_grammar,
        in any default_value)
        raises([InvalidGrammar](#cosnotifyfilter-exceptions));
};
```

The `FilterFactory` interface defines operations for creating filter.

`FilterFactory::create_filter()`

```
[Filter](../cosnotifyfilterfilter_interface/
cosnotifyfilterfilter_interface.md) create_filter (in string
constraint_grammar)
    raises ([InvalidGrammar](#cosnotifyfilter-exceptions));
```

Creates a forwarding filter object and returns a reference to the new filter.

Parameters

`constraint_grammar`

A string identifying the grammar used to parse constraints associated with this filter.

Exceptions

`[InvalidGrammar](#cosnotifyfilter-exceptions)`

The client invoking this operation supplied the name of a grammar that is not supported by any forwarding filter implementation this factory is capable of creating.

FilterFactory::create_mapping_filter()

```
[MappingFilter](../cosnotifyfiltermappingfilter_interface/  
cosnotifyfiltermappingfilter_interface.md) create_mapping_filter (  
    in string constraint_grammar,  
    in any default_value)  
    raises([InvalidGrammar](#cosnotifyfilter-exceptions));
```

Creates a mapping filter object and returns a reference to the new mapping filter.

Parameters

<code>constraint_grammar</code>	A string parameter identifying the grammar used to parse constraints associated with this filter.
<code>default_value</code>	An <code>Any</code> specifying the <code>default_value</code> of the new mapping filter.

Exceptions

```
[InvalidGrammar](#cosnotifyfilter-exceptions)
```

The client invoking this operation supplied the name of a grammar that is not supported by any mapping filter implementation this factory is capable of creating.

CosNotifyFilter::MappingFilter Interface

```

interface MappingFilter
{
    readonly attribute string constraint_grammar;
    readonly attribute CORBA::TypeCode value_type;
    readonly attribute any default_value;
    [MappingConstraintInfoSeq](#cosnotifyfilter-data-types)
add_mapping_constraints (
    in [MappingConstraintPairSeq](#cosnotifyfilter-data-types)
pair_list)
    raises ([InvalidConstraint](#cosnotifyfilter-exceptions), [InvalidValue]
(#cosnotifyfilter-exceptions));
    void modify_mapping_constraints (
    in [ConstraintIDSeq](#cosnotifyfilter-data-types) del_list,
    in [MappingConstraintInfoSeq](#cosnotifyfilter-data-types)
modify_list)
    raises ([InvalidConstraint](#cosnotifyfilter-exceptions), [InvalidValue]
(#cosnotifyfilter-exceptions), [ConstraintNotFound](#cosnotifyfilter-
exceptions));
    [MappingConstraintInfoSeq](#cosnotifyfilter-data-types)
get_mapping_constraints (
    in [ConstraintIDSeq](#cosnotifyfilter-data-types) id_list)
    raises ([ConstraintNotFound](#cosnotifyfilter-exceptions));
    MappingConstraintInfoSeq get_all_mapping_constraints();
    void remove_all_mapping_constraints();
    void destroy();
    boolean match ( in any filterable_data, out any result_to_set )
    raises ([UnsupportedFilterableData]);
    boolean match_structured (
    in CosNotification::StructuredEvent filterable_data,
    out any result_to_set)
    raises ([UnsupportedFilterableData](#cosnotifyfilter-exceptions));
    boolean match_typed (
    in CosTrading::PropertySeq filterable_data,
    out any result_to_set)
    raises ([UnsupportedFilterableData](#cosnotifyfilter-exceptions));
}; // MappingFilter

```


The `MappingFilter` interface defines the behaviors of objects that encapsulate a sequence of constraint-value pairs (see the description of the Default Filter Constraint Language in the *CORBA Notification Service Guide*). These constraint-value pairs are used to evaluate events and adjust their lifetime/priority values according to the result. An object supporting the `MappingFilter` interface can effect either an events lifetime property or its priority property, but not both.

The `MappingFilter` interface supports the operations required to manage the constraint-value pairs associated with an object instance supporting the interface. In addition, the `MappingFilter` interface supports a read-only attribute that identifies the constraint grammar used to parse the constraints encapsulated by this object. The `MappingFilter` interface supports a read-only attribute that identifies the typecode associated with the datatype of the specific property value it is intended to affect. It also supports another read-only attribute which holds the default value which is returned as the result of a match operation in cases when the event in question is found to satisfy none of the constraints encapsulated by the mapping filter. Lastly, the `MappingFilter` interface supports three variants of the operation which are invoked by an associated proxy object upon receipt of an event, to determine how the property of the event which the target mapping filter object was designed to affect should be modified.

`MappingFilter::constraint_grammar`

```
readonly attribute string constraint_grammar;
```

Identifies the grammar used to parse the constraint expressions encapsulated by the target mapping filter. The value of this attribute is set upon creation of a mapping filter.

A filter object's constraints must be expressed using a particular constraint grammar because its member `match` operations must be able to parse the constraints to determine whether or not a particular event satisfies one of them.

Orbix supports an implementation of the `MappingFilter` object which supports the default constraint grammar described in the *CORBA Notification Service Guide*. `constraint_grammar` is set to the value `EXTENDED_TCL` when the target mapping filter supports this default grammar.

Users may provide additional implementations of the `MappingFilter` interface which support different constraint grammars, and thus set the `constraint_grammar` attribute to a different value when creating such a mapping filter.

`MappingFilter::value_type`

```
readonly attribute CORBA::TypeCode value_type;
```

Identifies the datatype of the property value that the target mapping filter is designed to affect. Note that the factory creation operation for mapping filters accepts as an input parameter the `default_value` to associate with the mapping filter instance. This `default_value` is a `CORBA::Any`. Upon creation of a mapping filter, the `typecode` associated with the `default_value` is abstracted from the `CORBA::Any`, and its value is assigned to this attribute.

MappingFilter::default_value

```
readonly attribute any default_value;
```

The value returned as the result of any `match` operation during which the input event does not satisfy any of the constraints encapsulated by the mapping filter. The value of this attribute is set upon creation of a mapping filter object instance.

MappingFilter::add_mapping_constraints()

```
[MappingConstraintInfoSeq](#cosnotifyfilter-data-types)
add_mapping_constraints (
    in [MappingConstraintPairSeq](#cosnotifyfilter-data-types) pair_list)
    raises ([InvalidConstraint](#cosnotifyfilter-exceptions), [InvalidValue]
    (#cosnotifyfilter-exceptions));
```

Returns a sequence of structures which contain one of the input constraint expressions, its corresponding value, and the unique identifier assigned to this constraint-value pair by the target filter.

If one or more of the constraints passed into `add_mapping_constraints()` is invalid, none of the constraints are added to the target mapping filter.

Note

Once `add_mapping_constraints` is invoked by a client, the target filter is temporarily disabled from use by any proxy it may be associated with. Upon completion of the operation, the target filter is re-enabled and can once again be used by associated proxies to make event property mapping decisions.

Parameters

`pair_list`

A sequence of constraint-value pairs. Each constraint in this sequence must be expressed in the constraint grammar supported by the target object, and each associated value must be of the data type indicated by the `value_type` attribute of the target object.

Exceptions

<code>[InvalidConstraint]</code> <code>(#cosnotifyfilter-exceptions)</code>	Raised if any of the constraint expressions in the input sequence is not a valid expression. This exception contains the constraint that was determined to be invalid.
<code>[InvalidValue]</code> <code>(#cosnotifyfilter-exceptions)</code>	Raised if any of the values supplied in the input sequence are not of the same datatype as that indicated by the target object's <code>value_type</code> attribute. This exception contains the invalid value and its corresponding constraint.

`MappingFilter::modify_mapping_constraints()`

```
void modify_mapping_constraints (
    in [ConstraintIDSeq](#cosnotifyfilter-data-types) del_list,
    in [MappingConstraintInfoSeq](#cosnotifyfilter-data-types)
    modify_list)
    raises([InvalidConstraint](#cosnotifyfilter-exceptions),
          [InvalidValue](#cosnotifyfilter-exceptions),
          [ConstraintNotFound](#cosnotifyfilter-exceptions));
```

Modifies the constraint-value pairs associated with the target mapping filter. This operation can remove constraint-value pairs currently associated with the target mapping filter, and to modify the constraints and/or values of constraint-value pairs currently associated with the target mapping filter.

If an exception is raised during the operation, no changes are made to the filter's constraints.

Note

Once `modify_mapping_constraints()` is invoked by a client, the target mapping filter is temporarily disabled from use by any proxy it may be associated with. Upon completion of the operation, the target mapping filter is re-enabled and can be used by associated proxies to make event property mapping decisions.

Parameters

<code>del_list</code>	A sequence of unique identifiers associated with one of the constraint-value pairs currently encapsulated by the target mapping filter. If all input values are valid, the specific constraint-value pairs identified by the values contained in this parameter are deleted from the mapping filter's list of constraint-value-pairs.
<code>modify_list</code>	A sequence of structures containing a constraint structure, an <code>Any</code> value, and a numeric identifier. The numeric identifier of each element is the unique identifier associated with one of the constraint-value pairs currently encapsulated by the target filter object. The constraint-value pairs identified are modified to the values specified in the input list.

Exceptions

<code>[ConstraintNotFound]</code> (#cosnotifyfilter-exceptions)	Raised if any of the identifiers in either of the input sequences does not correspond to the unique identifier associated with a constraint-value pair encapsulated by the target mapping filter. This exception contains the identifier which did not correspond to a constraint-value pair encapsulated by the target object.
<code>[InvalidConstraint]</code> (#cosnotifyfilter-exceptions)	Raised if any of the constraint expressions supplied in an element of the second input sequence is not valid. This exception contains the constraint that was determined to be invalid.
<code>[InvalidValue]</code> (#cosnotifyfilter-exceptions)	Raised if any of the values in the second input sequence is not of the same datatype as that indicated by the mapping filter's <code>value_type</code> attribute. This exception contains the invalid value and its corresponding constraint expression.

MappingFilter::get_mapping_constraints()

```
[MappingConstraintInfoSeq] (#cosnotifyfilter-data-types)
get_mapping_constraints (
    in [ConstraintIDSeq] (#cosnotifyfilter-data-types) id_list)
    raises ([ConstraintNotFound] (#cosnotifyfilter-exceptions));
```

Returns a sequence of constraint-value pairs associated with the target mapping filter.

Parameters

`id_list`

A sequence of unique identifiers for constraint-value pairs encapsulated by the target object.

Exceptions

`[ConstraintNotFound] (#cosnotifyfilter-exceptions)`

One of the input values does not correspond to the identifier of an encapsulated constraint-value pair. The exception contains the identifier that did not correspond to a constraint-value pair.

`MappingFilter::get_all_mapping_constraints()`

```
[MappingConstraintInfoSeq] (#cosnotifyfilter-data-types)
get_all_mapping_constraints();
```

Returns all of the constraint-value pairs encapsulated by the target mapping filter.

`MappingFilter::remove_all_mapping_constraints`

```
void remove_all_mapping_constraints();
```

Removes all of the constraint-value pairs currently encapsulated by the target mapping filter. Upon completion, the target mapping filter still exists but has no constraint-value pairs associated with it.

`MappingFilter::destroy()`

```
void destroy();
```

Destroys the target mapping filter, and invalidates its object reference.

`MappingFilter::match()`

```
boolean match(in any filterable_data, out any result_to_set)
    raises ([UnsupportedFilterableData](#cosnotifyfilter-exceptions));
```

Determines how to modify some property value of an event in the form of a `CORBA::Any`.

The target mapping filter begins applying the its constraints according to each constraint's associated value, starting with the constraint with the best associated value for the specific property the mapping filter is designed to affect (for example, the highest priority, the longest lifetime, and so on), and ending with the constraint with the worst associated value.

Upon encountering a constraint which the event matches, the operation sets `result_to_set` to the value associated with the matched constraint, and returns with a value of `TRUE`. If the event does not satisfy any of the target mapping filter's constraints, the operation sets `result_to_set` to the value of the target mapping filter's `default_valueattribute` and returns with a value of `FALSE`.

The act of determining whether or not a given event passes a given filter constraint is specific to the grammar used to parse the filter constraints.

Parameters

<code>filterable_data</code>	An <code>Any</code> containing the event being evaluated
<code>result_to_set</code>	An <code>Any</code> containing the value and the property name to set when an event evaluates to <code>TRUE</code> .

Exceptions

```
[UnsupportedFilterableData](#cosnotifyfilter-exceptions)
```

The input parameter contains data that the `match` operation is not designed to handle.

MappingFilter::match_structured()

```
boolean match_structured (
    in CosNotification::StructuredEvent filterable_data,
    out any result_to_set)
    raises ([UnsupportedFilterableData](#cosnotifyfilter-exceptions));
```

Determines how to modify some property value of a structured event.

The target mapping filter begins applying the its constraints according to each constraints associated value, starting with the constraint with the best associated value for the specific property the mapping filter is designed to affect (for example, the highest priority, the longest lifetime, and so on), and ending with the constraint with the worst associated value.

Upon encountering a constraint which the event matches, the operation sets `result_to_set` to the value associated with the matched constraint, and returns with a value of `TRUE`. If the event does not satisfy any of the target mapping filter's constraints, the operation sets `result_to_set` to the value of the target mapping filter's `default_valueattribute` and returns with a value of `FALSE`.

The act of determining whether or not a given event passes a given filter constraint is specific to the grammar used to parse the filter constraints.

Parameters

<code>filterable_data</code>	A <code>CosNotification::StructuredEvent</code> containing the event being evaluated.
<code>result_to_set</code>	An <code>Any</code> containing the value and the property name to set when an event evaluates to <code>TRUE</code> .

Exceptions

```
[UnsupportedFilterableData] (#cosnotifyfilter-exceptions)
```

The input parameter contains data that `match_structured()` is not designed to handle.

CosTrading Module

Contains the major functional interfaces of a trading service.

CosTrading Data Types

CosTrading::Constraint Data Type

```
typedef [Istring](#cosnaming-overview) Constraint;
```

A query constraint expression. The constraint is used to filter offers during a query, and must evaluate to a boolean expression.

The constraint language consists of the following elements:

- comparative functions: ==, !=, >, >=,
- boolean connectives: and, or, not
- property existence: exist
- property names
- numeric, boolean and string constants
- mathematical operators: +, -, *, /
- grouping operators: (,)

The following property value types can be manipulated using the constraint language:

- boolean, short, unsigned short, long, unsigned long, float, double, char, Ichar, string, Istring
- sequences of the above types

Only the `exist` operator can be used on properties of other types.

Note

The constraint language keywords are case-sensitive

Literal strings should be enclosed in single quotes

The boolean literals are `TRUE` and `FALSE`

CosTrading::Istring Data Type

```
typedef string Istring;
```

When internationalized strings are widely supported, this definition will be changed.

CosTrading::LinkName Data Type

```
typedef [Istring](#cosnaming-overview) LinkName;
```

The name of a unidirectional link from one trader to another. The only restriction on the format of a link name is it cannot be an empty string.

CosTrading::LinkNameSeq Data Type

```
typedef sequence<[LinkName](#costrading-data-types)> LinkNameSeq;
```

CosTrading::OfferId Data Type

```
typedef string OfferId;
```

An offer identifier is an opaque string whose format is determined entirely by the trading service from which the offer identifier was obtained, and can only be used with that trading service.

CosTrading::OfferIdSeq Data Type

```
typedef sequence<[OfferId](#costrading-data-types)> OfferIdSeq;
```

CosTrading::OfferSeq Data Type

```
typedef sequence<Offer> OfferSeq;
```

CosTrading::PolicyName Data Type

```
typedef string PolicyName;
```

The name of a policy used to control the trader's behavior. The only restriction on the format of a policy name is it cannot be an empty string.

CosTrading::PolicyNameSeq Data Type

```
typedef sequence<[PolicyName](#costrading-data-types)> PolicyNameSeq;
```

CosTrading::PolicySeq Data Type

```
typedef sequence<Policy> PolicySeq;
```

CosTrading::PolicyValue Data Type

```
typedef any PolicyValue;
```

CosTrading::PropertyName Data Type

```
typedef [Istring](#cosnaming-overview) PropertyName;
```

Although not explicitly defined in the specification, a property name should start with a letter, may contain digits and underscores, and should not contain spaces.

CosTrading::PropertyNameSeq DataType

```
typedef sequence<[PropertyName](#costrading-data-types)> PropertyNameSeq;
```

CosTrading::PropertySeq Data Type

```
typedef sequence<Property> PropertySeq;
```

CosTrading::PropertyValue Data Type

```
typedef any PropertyValue;
```

A `CORBA::Any` containing the value of the property. Orbix Trader allows arbitrarily complex user-defined types to be used as property values.

CosTrading::ServiceTypeName Data Type

```
typedef [Istring](#cosnaming-overview) ServiceTypeName;
```

A service type name can have one of two formats, both representing formats that appear in the Interface Repository.

- **Scoped Name** - A scoped name has the form `::One::Two`. Other supported variations are `Three::Four` and `Five`.
- **Interface Repository Identifier** - An interface repository identifier has the form `IDL:[prefix/][module/]name:X.Y`. For example, `IDL:omg.org/CosTrading/Lookup:1.0` is a valid interface repository identifier, and you can use the same format for your service type names.

Note

Although a service type name can appear similar to names used in the interface repository, the trading service never uses servicetype names to look up information in the interface repository.

CosTrader::TraderName Data Type

```
typedef LinkNameSeq TraderName;
```

A `TraderName` represents a path from one trader to the desired trader by following a sequence of links. The `starting_trader` importer policy, if specified for a query operation, should contain a value of this type.

CosTrading::TypeRepository Data Type

```
typedef Object TypeRepository;
```

`TypeRepository` represents an object reference for a `CosTradingRepos::ServiceTypeRepository` object. You will need to narrow this reference before you can interact with the service type repository.

CosTrading::FollowOption Enum

```
enum FollowOption
{
    local_only,
    if_no_local,
    always
};
```

Determines the follow behavior for linked traders.

The member values are defined as follows:

<code>local_only</code>	The trader will not follow a link.
<code>if_no_local</code>	The trader will only follow a link if no offers were found locally.
<code>always</code>	The trader will always follow a link.

CosTrading::Offer Struct

```
struct Offer
{
    Object reference;
    [PropertySeq](#costrading-data-types) properties;
};
```

The description of a service offer. The data members contains the following data:

<code>reference</code>	The object reference associated with this offer. Depending on the configuration of the server, this reference may be <code>nil</code> .
<code>properties</code>	A sequence of properties associated with this offer.

CosTrading::Policy Struct

```
struct Policy
{
    [PolicyName](#costrading-data-types) name;
    [PolicyValue](#costrading-data-types) value;
};
```

CosTrading::Property Struct

```
struct Property
{
    [PropertyName](#costrading-data-types) name;
    PropertyValue value;
};
```

A name-value pair associated with a service offer or proxy offer. If the property name matches the name of a property in the offer's service type, then the `TypeCode` of the value must match the property definition in the service type.

Note

Orbix Trader allows properties to be associated with an offer even if the property name does not match any property in the service type. These properties can also be used in query constraint and preference expressions.

CosTrading Exceptions

CosTrading::DuplicatePolicyName

```
exception DuplicatePolicyName {[PolicyName](#costrading-data-types) name};
```

More than one value was supplied for a policy. The policy name that caused the exception is returned.

CosTrading::DuplicatePropertyName

```
exception DuplicatePropertyName {[PropertyName](#costrading-data-types)
name};
```

The property name has already appeared once. The duplicated property name is returned.

CosTrading::IllegalConstraint

```
exception IllegalConstraint{[Constraint](#costrading-data-types) constr};
```

An error occurred while parsing the constraint expression. The invalid constraint is passed back.

CosTrading::IllegalOfferId

```
exception IllegalOfferId {[OfferId](#costrading-data-types) id};
```

The offer identifier is empty or malformed. The invalid id is returned.

CosTrading::IllegalPropertyName

```
exception IllegalPropertyName {[PropertyName](#costrading-data-types) name};
```

The property name is empty or does not conform the format supported by the trader. The property name that caused the exception is returned.

CosTrading::IllegalServiceType

```
exception IllegalServiceType {[ServiceTypeName](#costrading-data-types) type};
```

A service type name does not conform to the formats supported by the trader. The name that caused the exception is returned.

CosTrading::InvalidLookupRef

```
exception InvalidLookupRef {Lookup target};
```

The Lookup object reference cannot be `nil`.

CosTrading::MissingMandatoryProperty

```
exception MissingMandatoryProperty
{
    [ServiceTypeName](#costrading-data-types) type;
    [PropertyName](#costrading-data-types) name;
};
```

No value was supplied for a property defined as mandatory by the service type.

CosTrading::NotImplemented

```
exception NotImplemented {};
```

The requested operation is not supported by this trading service.

CosTrading::PropertyTypeMismatch

```
exception PropertyTypeMismatch
{
    [ServiceTypeName](#costrading-data-types) type;
    [Property](#costrading-data-types) prop;
};
```

The property value type conflicts with the property's definition in the service type.

CosTrading::ReadOnlyDynamicProperty

```
exception ReadOnlyDynamicProperty
{
    [ServiceTypeName](#costrading-data-types) type;
    [PropertyName](#costrading-data-types) name;
};
```

A property that is defined as read-only by the service type cannot have a dynamic value.

CosTrading::UnknownMaxLeft

```
exception UnknownMaxLeft {};
```

The iterator does not know how many items are left.

CosTrading::UnknownOfferId

```
exception UnknownOfferId {[OfferId](#costrading-data-types) id};
```

The trader does not contain an offer with the given identifier. The unresolved ID is returned.

CosTrading::UnknownServiceType

```
exception UnknownServiceType {[ServiceTypeName] (#costrading-data-types)  
type};
```

The service type repository used by the trader does not have the requested service type. The unresolved name is returned.

CosTrading::Admin Interface

```

// IDL in CosTrading
interface Admin :
    TraderComponents, SupportAttributes,
    ImportAttributes, LinkAttributes
{
    typedef sequence OctetSeq;
    readonly attribute OctetSeq [request_id_stem](#costradingadmin-interface);
    unsigned long [set_def_search_card](#costradingadmin-interface) (in
unsigned long value);
    unsigned long [set_max_search_card](#costradingadmin-interface) (in
unsigned long value);
    unsigned long [set_def_match_card](#costradingadmin-interface) (in unsigned
long value);
    unsigned long [set_max_match_card](#costradingadmin-interface) (in unsigned
long value);
    unsigned long [set_def_return_card](#costradingadmin-interface) (in
unsigned long value);
    unsigned long [set_max_return_card](#costradingadmin-interface) (in
unsigned long value);
    unsigned long [set_max_list](#costradingadmin-interface) (in unsigned long
value);
    boolean [set_supports_modifiable_properties](#costradingadmin-interface)
(in boolean value);
    boolean [set_supports_dynamic_properties](#costradingadmin-interface) (in
boolean value);
    boolean [set_supports_proxy_offers](#costradingadmin-interface) (in boolean
value);
    unsigned long [set_def_hop_count](#costradingadmin-interface) (in unsigned
long value);
    unsigned long [set_max_hop_count](#costradingadmin-interface) (in unsigned
long value);
    FollowOption [set_def_follow_policy](#costradingadmin-interface) (in
FollowOption policy);
    FollowOption [set_max_follow_policy](#costradingadmin-interface) (in
FollowOption policy);
    FollowOption [set_max_link_follow_policy](#costradingadmin-interface) (
        in FollowOption policy);
    TypeRepository [set_type_repos](#costradingadmin-interface) (in
TypeRepository repository);
    OctetSeq [set_request_id_stem](#costradingadmin-interface) (in OctetSeq
stem);
    void [list_offers](#costradingadmin-interface)( in unsigned long how_many,
        out OfferIdSeq ids,
        out OfferIdIterator id_itr )
    raises ( NotImplemented );
    void [list_proxies](#costradingadmin-interface)( in unsigned long how_many,

```

```

        out OfferIdSeq ids,
        out OfferIdIterator id_itr )
    raises ( NotImplemented );
};

```

Interface `Admin` provides attributes and operations for administrative control of the trading service.

`Admin::request_id_stem` Attribute

```
readonly attribute OctetSeq request_id_stem;
```

The request identifier “stem” is a sequence of octets that comprise the prefix for a request identifier. The trader will append additional octets to ensure the uniqueness of each request identifier it generates.

`Admin::list_offers()`

```

void list_offers(in unsigned long how_many,
                 out OfferIdSeq ids,
                 out OfferIdIterator id_itr)
raises(NotImplemented);

```

Obtains the identifiers for the service offers in this trader.

Parameters

Parameter	Description
<code>how_namy</code>	Indicates how many identifiers to return in <code>ids</code> .
<code>ids</code>	Contains at most <code>how_many</code> identifiers. If the number of identifiers exceeds <code>how_many</code> , the <code>id_itr</code> parameter will hold a reference to an iterator object through which the remaining identifiers can be obtained.
<code>id_itr</code>	Will hold nil if no identifiers were found or if all of the identifiers were returned in <code>ids</code> . Otherwise, holds a reference to an iterator object through which the remaining identifiers can be obtained.

`Admin::list_proxies()`

```
void list_proxies(in unsigned long how_many,
                 out OfferIdSeq ids,
                 out OfferIdIterator id_itr)
raises(NotImplemented);
```

Obtains the identifiers for the proxy offers in this trader.

Parameters

<code>how_many</code>	Indicates how many identifiers to return in <code>ids</code> .
<code>ids</code>	Contains at most <code>how_many</code> identifiers. If the number of identifiers exceeds <code>how_many</code> , the <code>id_itr</code> parameter will hold a reference to an iterator object through which the remaining identifiers can be obtained.
<code>id_itr</code>	Will hold nil if no identifiers were found or if all of the identifiers were returned in <code>ids</code> . Otherwise, holds a reference to an iterator object through which the remaining identifiers can be obtained.

Admin::set_def_follow_policy()

```
FollowOption set_def_follow_policy(in FollowOption policy);
```

Changes the value of the default link follow attribute and returns the previous value.

Parameters

`policy`

The new value

Admin::set_def_hop_count()

```
unsigned long set_def_hop_count(in unsigned long value);
```

Changes the value of the default hop count attribute and returns the previous value.

Parameters

value

The new value

Admin::set_def_match_card()

```
unsigned long set_def_match_card(in unsigned long value);
```

Changes the value of the default match cardinality attribute and returns the previous value.

Parameters

value

The new value

Admin::set_def_return_card()

```
unsigned long set_def_return_card(in unsigned long value);
```

Changes the value of the default return cardinality attribute and returns the previous value.

Parameters

value

The new value

Admin::set_def_search_card()

```
unsigned long set_def_search_card(in unsigned long value);
```

Changes the value of the default search cardinality attribute and returns the previous value.

Parameters

value

The new value

See Also CosTrading::ImportAttributes

Admin::set_max_follow_policy()

```
FollowOption set_max_follow_policy(in FollowOption policy);
```

Changes the value of the maximum link follow attribute and returns the previous value.

Parameters

policy

The new value

Admin::set_max_hop_count()

```
unsigned long set_max_hop_count(in unsigned long value);
```

Changes the value of the maximum hop count attribute and returns the previous value.

Parameters

value

The new value

Admin::set_max_link_follow_policy()

```
FollowOption set_max_link_follow_policy(in FollowOption policy);
```

Changes the value of the maximum link follow policy and returns the previous value.

Parameters

policy

The new value

Admin::set_max_list()

```
unsigned long set_max_list(in unsigned long value);
```

Changes the value of the maximum list attributes and returns the previous value.

Parameters

value

The new value

Admin::set_max_match_card()

```
unsigned long set_max_match_card(in unsigned long value);
```

Changes the value of the maximum match cardinality attribute and returns the previous value.

Parameters

value

The new value

Admin::set_max_return_card()

```
unsigned long set_max_return_card(in unsigned long value);
```

Changes the value of the maximum return cardinality attribute and returns the previous value.

Parameters

```
value
```

The new value

Admin::set_max_search_card()

```
unsigned long set_max_search_card(in unsigned long value);
```

Changes the value of the maximum search cardinality attribute and returns the previous value.

Parameters

```
value
```

The new value

Admin::set_request_id_stem()

```
OctetSeq set_request_id_stem(in OctetSeq stem);
```

Changes the value of the request identifier stem and returns the previous value.

Parameters

```
stem
```

The new value

Admin::set_supports_dynamic_properties()

```
boolean set_supports_dynamic_properties(in boolean value);
```

Establishes whether the trader considers offers with dynamic properties during a query and returns the previous setting.

Parameters

value

The new value

Admin::set_supports_modifiable_properties()

```
boolean set_supports_modifiable_properties(in boolean value);
```

Establishes whether the trader supports property modification and returns the previous setting.

Parameters

value

- **TRUE** activates property modification support.
- **FALSE** deactivates property modification support.

Admin::set_supports_proxy_offers()

```
boolean set_supports_proxy_offers(in boolean value);
```

Establishes whether the trader supports proxy offers and returns the previous setting.

Parameters

value

- **TRUE** turns on proxy support.
- **FALSE** turns off proxy support.

Admin::set_type_repos()

```
TypeRepository set_type_repos(in TypeRepository repository);
```

Establishes the service type repository to be used by the trader and returns a reference to the previous type repository.

Parameters

repository

A reference to a type repository.

CosTrading::ImportAttributes Interface

The read-only attributes of this interface provide the default and maximum values for policies that govern query operations.

Note

Performing a query is also known as *importing service offers*, therefore these attributes are called *import attributes*.

ImportAttributes::def_follow_policy Attribute

```
readonly attribute FollowOption def_follow_policy;
```

The default value for the `follow_policy` policy if it is not supplied.

ImportAttributes::def_hop_count Attribute

```
readonly attribute unsigned long def_hop_count;
```

The default value for the `hop_count` policy if it is not supplied.

ImportAttributes::def_match_card Attribute

```
readonly attribute unsigned long def_match_card;
```

The default value for the `match_card` policy if it is not supplied.

ImportAttributes::def_return_card Attribute

```
readonly attribute unsigned long def_return_card;
```

The default value for the `return_card` policy if it is not supplied.

ImportAttributes::def_search_card Attribute

```
readonly attribute unsigned long def_search_card;
```

The default value for the `search_card` policy if it is not supplied.

ImportAttributes::max_follow_policy Attribute

```
readonly attribute FollowOption max_follow_policy;
```

The maximum value for the `follow_policy` policy, which may override the value supplied by an importer.

ImportAttributes::max_hop_count Attribute

```
readonly attribute unsigned long max_hop_count;
```

The maximum value for the `hop_count` policy, which may override the value supplied by an importer.

ImportAttributes::max_list Attribute

```
readonly attribute unsigned long max_list;
```

The maximum size of any list returned by the trader. This may override the value supplied by a client to operations such as `query` and `next_n`.

ImportAttributes::max_match_card Attribute

```
readonly attribute unsigned long max_match_card;
```

The maximum value for the `match_card` policy, which may override the value supplied by an importer.

ImportAttributes::max_return_card Attribute

```
readonly attribute unsigned long max_return_card;
```

The maximum value for the `return_card` policy, which may override the value supplied by an importer.

ImportAttributes::max_search_card Attribute

```
readonly attribute unsigned long max_search_card;
```

The maximum value for the `search_card` policy, which may override the value supplied by an importer.

CosTrading::Link Interface

```

interface Link :
    TraderComponents, SupportAttributes, LinkAttributes
{
    struct [LinkInfo](#costradinglink-interface)
    {
        Lookup target;
        Register target_reg;
        FollowOption def_pass_on_follow_rule;
        FollowOption limiting_follow_rule;
    };
    exception [IllegalLinkName](#costradinglink-exceptions) { LinkName name; };
    exception [UnknownLinkName](#costradinglink-exceptions) { LinkName name; };
    exception [DuplicateLinkName](#costradinglink-exceptions) { LinkName
name; };
    exception [DefaultFollowTooPermissive](#costradinglink-exceptions) {
        FollowOption default_follow_rule;
        FollowOption limiting_follow_rule; };
    exception [LimitingFollowTooPermissive](#costradinglink-exceptions) {
        FollowOption limiting_follow_rule;
        FollowOption max_link_follow_policy; };
    void [add_link](#costradinglink-exceptions)( in LinkName name, in Lookup
target,
        in FollowOption default_follow_rule,
        in FollowOption[ limiting_follow_rule ])(#costrading-data-
types)
    raises ( [IllegalLinkName](#costradinglink-exceptions), [DuplicateLinkName]
(#costradinglink-exceptions), InvalidLookupRef,
        [DefaultFollowTooPermissive](#costradinglink-exceptions),
        [LimitingFollowTooPermissive](#costradinglink-exceptions) );
    void [remove_link](#costradinglink-exceptions)( in LinkName name )
    raises ( [IllegalLinkName](#costradinglink-exceptions), [UnknownLinkName]
(#costradinglink-exceptions) );
    LinkInfo [describe_link](#costradinglink-exceptions)( in LinkName name )
    raises ( [IllegalLinkName](#costradinglink-exceptions), [UnknownLinkName]
(#costradinglink-exceptions) );
    LinkNameSeq [list_links](#costradinglink-exceptions)();
    void [modify_link](#costradinglink-exceptions)( in LinkName name,
        in FollowOption default_follow_rule,
        in FollowOption limiting_follow_rule )
    raises ( [IllegalLinkName](#costradinglink-exceptions), [UnknownLinkName]
(#costradinglink-exceptions),
        [DefaultFollowTooPermissive](#costradinglink-exceptions),
        [LimitingFollowTooPermissive](#costradinglink-exceptions) );
};

```

Provides structures, exceptions, and operations for managing links between traders.

Link::LinkInfo Data Structure

```
struct LinkInfo
{
    Lookup target;
    Register target_reg;
    FollowOption def_pass_on_follow_rule;
    FollowOption limiting_follow_rule;
};
```

A complete description of a link. The members hold the following information:

<code>target</code>	Lookup interface if link target
<code>target_reg</code>	<code>Register</code> interface of link
<code>def_pass_on_follow_rule</code>	Default link behavior for the link if no link-follow policy is specified by an importer during a query
<code>limiting_follow_rule</code>	Most permissive link-follow behavior that the link is willing to tolerate

CosTrading::Link Exceptions

Link::DefaultFollowTooPermissive Exception

```
exception DefaultFollowTooPermissive
{
    FollowOption def_pass_on_follow_rule;
    FollowOption limiting_follow_rule;
};
```

Raised when the value for `def_pass_on_follow_rule` exceeds the value for `limiting_follow_rule`. Both values are passed back to the caller.

Link::DuplicateLinkName Exception


```
exception DuplicateLinkName {LinkName name};
```

Raised when a link already exists with the given name. The duplicated link name is passed back to the caller.

Link::IllegalLinkName Exception

```
exception IllegalLinkName {LinkName name};
```

Raised when the link name is empty or does not conform the format supported by the trader. The invalid link name is passed back to the caller.

Link::LimitingFollowTooPermissive Exception

```
exception LimitingFollowTooPermissive
{
    FollowOption limiting_follow_rule;
    FollowOption max_link_follow_policy;
};
```

The value for `limiting_follow_rule` exceeds the trader's `max_link_follow_policy` attribute.

Link::UnknownLinkName Exception

```
exception UnknownLinkName {LinkName name};
```

Raised when trader does not have a link with the given name. The invalid name is returned.

Link::add_link()

```
void add_link(in LinkName name, in Lookup target,
             in FollowOption def_pass_on_follow_rule,
             in FollowOption limiting_follow_rule)
raises([IllegalLinkName](#costradinglink-exceptions),
       [DuplicateLinkName](#costradinglink-exceptions),
       InvalidLookupRef,
       [DefaultFollowTooPermissive](#costradinglink-exceptions),
       [LimitingFollowTooPermissive](#costradinglink-exceptions));
```

Adds a new, unidirectional link from this trader to another trader.

Parameters

<code>name</code>	Specifies the name of the new link.
<code>target</code>	Holds a reference to the <code>Lookup</code> interface of the target trader
<code>def_pass_on_follow_rule</code>	Specifies the default link behavior for the link if not link-follow policy is specified by an importer during a query.
<code>limiting_follow_rule</code>	Specifies the most permissive link-follow behavior the the link is willing to follow.

Exceptions

<code>IllegalLinkName</code>	Link name is empty of has an invalid format.
<code>DuplicateLinkName</code>	Another link exists with the same name.
<code>InvalidLookupRef</code>	Target object reference is <code>nil</code> .
<code>DefaultFollowTooPermissive</code>	The value for <code>def_pass_on_follow_rule</code> exceeds the value for <code>limiting_follow_rule</code> .
<code>LimitingFollowTooPermissive</code>	The value for <code>limiting_follow_rule</code> exceeds the trader's <code>max_link_follow_policy</code> .

`Link::describe_link()`

```
[LinkInfo](#costradinglink-interface) describe_link(in LinkName name)
raises([IllegalLinkName](#costradinglink-exceptions), [UnknownLinkName]
(#costradinglink-exceptions));
```

Obtains a description of a link and returns it in a [LinkInfo](#) object.

Parameters

name

Name of the link of interest

Exceptions

<code>IllegalLinkName</code>	The link name is empty or has an invalid format.
<code>UnknownLinkName</code>	No link with the specified name exists.

`Link::list_links()`

```
LinkNameSeq list_links();
```

Returns the names of all trading links within the trader.

`Link::modify_link()`

```
void modify_link(in LinkName name,
                 in FollowOption def_pass_on_follow_rule,
                 in FollowOption limiting_follow_rule)
raises([IllegalLinkName](#costradinglink-exceptions),
       [UnknownLinkName](#costradinglink-exceptions),
       [DefaultFollowTooPermissive](#costradinglink-exceptions),
       [LimitingFollowTooPermissive](#costradinglink-exceptions));
```

Modifies the follow behavior of an existing link.

Parameters

<code>name</code>	Specifies the name of the link to be modified.

<code>def_pass_on_follow_rule</code>	Specifies the default link behavior for the link if no link-follow policy is specified by an importer during a query.
<code>limiting_follow_rule</code>	Describes the most permissive link-follow behavior that the link is willing to follow.

Exceptions

<code>IllegalLinkName</code>	Link name is empty or has an invalid format.
<code>UnknownLinkName</code>	The specified link name does not exist.
<code>DefaultFollowTooPermissive</code>	The value for <code>def_pass_on_follow_rule</code> exceeds the value for <code>limiting_follow_rule</code> .
<code>LimitingFollowTooPermissive</code>	The value for <code>limiting_follow_rule</code> exceeds the trader's <code>max_link_follow_policy</code> .

Link::remove_link()

```
void remove_link(in LinkName name)
    raises([IllegalLinkName](#costradinglink-exceptions), [UnknownLinkName]
           (#costradinglink-exceptions));
```

Removes an existing link.

Parameters

`name`

Name of the link to be removed

Exceptions

<code>IllegalLinkName</code>	The link name is empty or has an invalid format.
<code>UnknownLinkName</code>	No link exists with the specified name.

CosTrading::LinkAttributes Interface

LinkAttributes::max_link_follow_policy Attribute

```
readonly attribute FollowOption max_link_follow_policy;
```

Determines the most permissive behavior that will be allowed for any link.

CosTrading::Lookup Interface

```

interface Lookup :
    TraderComponents, SupportAttributes, ImportAttributes
{
    typedef Istring [Preference](#costradinglookup-interface);
    enum [HowManyProps](#costradinglookup-interface)
    {
        none,
        some,
        all
    };
    union [SpecifiedProps](#costradinglookup-interface) switch ([HowManyProps]
(#costradinglookup-interface))
    {
        case some: PropertyNameSeq prop_names;
    };
    exception IllegalPreference {[Preference](#costradinglookup-interface)
pref};
    exception IllegalPolicyName {PolicyName name};
    exception PolicyTypeMismatch {Policy the_policy};
    exception InvalidPolicyValue {Policy the_policy};
    void query(in ServiceTypeName type,
                in Constraint constr,
                in [Preference](#costradinglookup-interface) pref,
                in PolicySeq policies,
                in [SpecifiedProps](#costradinglookup-interface) desired_props,
                in unsigned long how_many,
                out OfferSeq offers,
                out OfferIterator offer_itr,
                out PolicyNameSeq limits_applied)
    raises (IllegalServiceType, UnknownServiceType,
            IllegalConstraint, IllegalPreference,
            IllegalPolicyName, PolicyTypeMismatch,
            InvalidPolicyValue, IllegalPropertyName,
            DuplicatePropertyName, DuplicatePolicyName);
};

```

Provides a single operation, `query`, for use by importers.

Lookup::Preference DataType

```
typedef Istring Preference;
```

A query preference expression. The preference is used to order the offers found by a query. The valid forms of a preference expression are:

min numeric-expression

orders the offers in ascending order based on the numeric expression. Offers for which the expression cannot be evaluated (for example, if the offer does not contain a property that is used in the expression) are placed at the end of the sequence.

max numeric-expression

orders the offers in descending order based on the numeric expression. Offers for which the expression cannot be evaluated (for example, if the offer does not contain a property that is used in the expression) are placed at the end of the sequence.

with boolean-expression

orders the offers such that those for which the boolean expression are `TRUE` are included before any of those for which the expression is false, which are placed before any of those that cannot be evaluated.

random

orders the offers in random order.

first

orders the offers as they are encountered by the server.

If an empty preference expression is supplied, it is equivalent to a preference of `first`.

Lookup::HowManyProps Enum

```
enum HowManyProps
{
    none,
    some,
    all
};
```

The choices for indicating how many properties are returned with each offer. The members are defined as follows:

<code>none</code>	No properties should be returned.
<code>some</code>	Some properties should be returned.
<code>all</code>	All properties should be returned.

Lookup::SpecifiedProps Union

```
union SpecifiedProps switch([HowManyProps](#costradinglookup-interface))
{
case some: PropertyNameSeq prop_names;
};
```

Determines which properties are to be returned for each matching offer found by the [query](#) operation. The union's discriminator can meaningfully be set to the other enumerated values `none` and `all`. If set to `none`, you are indicating that no properties should be returned. If set to `all`, then all properties will be returned. Set the value for `some` with a sequence of property names indicating which properties should be returned

Lookup::IllegalPolicyName Exception

```
exception IllegalPolicyName {PolicyName name};
```

The policy name is empty or does not conform the format supported by the trader. The invalid name is returned.

Lookup::IllegalPreference Exception

```
exception IllegalPreference {[Preference](#costradinglookup-interface) pref};
```

An error occurred while parsing the preference expression. The invalid preference is returned.

Lookup::InvalidPolicyValue Exception

```
exception InvalidPolicyValue {Policy the_policy};
```

The policy has an invalid value.

Lookup::PolicyTypeMismatch Exception


```
exception PolicyTypeMismatch {Policy the_policy};
```

The policy value type specified does not match the type expected by the trader. The type expected by the trader is returned.

Lookup::query()

```
void query(in ServiceTypeName type,
          in Constraint constr,
          in [Preference](#costradinglookup-interface) pref,
          in PolicySeq policies,
          in [SpecifiedProps](#costradinglookup-interface) desired_props,
          in unsigned long how_many,
          out OfferSeq offers,
          out OfferIterator offer_itr,
          out PolicyNameSeq limits_applied)
raises(IllegalServiceType,
       UnknownServiceType,
       IllegalConstraint,
       [IllegalPreference](#costradinglookup-interface),
       [IllegalPolicyName](#costradinglookup-interface),
       [PolicyTypeMismatch](#costradinglookup-interface),
       [InvalidPolicyValue](#costradinglookup-interface),
       IllegalPropertyName,
       DuplicatePropertyName,
       DuplicatePolicyName);
```

Allows an *importer* to obtain references to objects that provide services meeting its requirements.

The importer can control the behavior of the search by supplying values for certain policies. The trader may override some or all of the values supplied by the importer. The following policies are known by the trader:

exact_type_match (boolean)

if `TRUE`, only offers of exactly the service type specified by the importer are considered; if `FALSE`, offers of any service type that conforms to the importer's service type are considered

hop_count (unsigned long)

indicates maximum number of hops across federation links that should be tolerated in the resolution of this query

link_follow_rule (FollowOption)

indicates how the client wishes links to be followed in the resolution of this query

match_card (unsigned long)

indicates the maximum number of matching offers to which the preference specification should be applied

return_card (unsigned long)

indicates the maximum number of matching offers to return as a result of this query

search_card (unsigned long)

indicates the maximum number of offers to be considered when looking for type conformance and constraint expression match

starting_trader (TraderName)

specifies the remote trader at which the query starts

use_dynamic_properties (boolean)

specifies whether to consider offers with dynamic properties

use_modifiable_properties (boolean)

specifies whether to consider offers with modifiable properties

use_proxy_offers (boolean)

specifies whether to consider proxy offers

Parameters

type	Specifies the service type that interests the importer. The service type limits the scope of the search to only those offers exported for this type, and optionally any subtype of this type.
constr	Limits the search to only those offers for which this expression is <code>TRUE</code> . The simplest constraint expression is "TRUE", which matches any offer.
pref	Specifies how the matched offers are to be ordered.
policies	Specifies the policies that govern the behavior of the query.

<code>desired_properties</code>	Determines the properties that are to be included with each offer returned by the query. This parameter does not affect whether or not a service offer is returned. To exclude an offer that does not contain a desired property, include "exist <code>property-name</code> " in the constraint.
<code>how_many</code>	Indicates how many offers are to be returned in the <code>offers</code> parameter.
<code>offers</code>	Holds at most <code>how_many</code> offers. If the number of matching offers exceeds <code>how_many</code> , the <code>offer_itr</code> parameter will hold a reference to an iterator object through which the remaining offers can be obtained.
<code>offer_itr</code>	Will hold <code>nil</code> if no matching offers were found or if all of the matching offers were returned in <code>offers</code> ; otherwise, holds a reference to an iterator. The object's destroy operation should be invoked when the object is no longer needed.
<code>limits_applied</code>	Holds the names of any policies that were overridden by the trader's maximum allowable settings.

Exceptions

<code>IllegalServiceType</code>	Service type name is empty or has an invalid format
<code>UnknownServiceType</code>	Service type was not found in service type repository
<code>IllegalConstraint</code>	An error occurred while parsing the constraint expression
<code>IllegalPreference</code>	An error occurred while parsing the preference expression
<code>IllegalPolicyName</code>	A policy name is empty or has an invalid format
<code>PolicyTypeMismatch</code>	A policy value type did not match the type expected by the trader
<code>InvalidPolicyValue</code>	A policy has an invalid value
<code>IllegalPropertyName</code>	A property name is empty or has an invalid format
<code>DuplicatePropertyName</code>	A property name appeared more than once in the list of desired properties
<code>DuplicatePolicyName</code>	A policy name appeared more than once in the list of policies

CosTrading::OfferIdIterator Interface

```
interface OfferIdIterator
{
    unsigned long [max_left()](#costradingofferiditerator-interface)
    raises (UnknownMaxLeft);
    boolean [next_n](#cosnamingbindingiterator-interface)(in unsigned long n,
out OfferIdSeq ids);
    void [destroy()](#cosnamingbindingiterator-interface);
};
```

Specifies methods to iterate through a list of offer identifiers.

OfferIdIterator::destroy()

```
void destroy();
```

Destroys the iterator object.

OfferIdIterator::max_left()

```
unsigned long max_left()
raises(UnknownMaxLeft);
```

Returns the number of offer identifiers remaining in the iterator.

Exceptions

```
UnknownMaxLeft
```

Cannot determine the number of remaining offer identifiers

OfferIdIterator::next_n()

```
boolean next_n(in unsigned long n,  
              out OfferIdSeq ids);
```

Returns `TRUE` if `ids` contains more offer identifiers, and returns `FALSE` if `ids` is `nil`.

Parameters

<code>n</code>	Number of offer identifiers to return
<code>ids</code>	List of offer identifiers containing at most <code>n</code> elements

CosTrading::OfferIterator Interface

```
interface OfferIterator
{
    unsigned long [max_left](#costradingofferiditerator-interface)()
    raises (UnknownMaxLeft);
    boolean [next_n](#cosnamingbindingiterator-interface)( in unsigned long n,
out OfferSeq offers );
    void [destroy](#cosnamingbindingiterator-interface)();
};
```

Specifies methods to iterate through a list of offers.

OfferIterator::destroy()

```
void destroy();
```

Destroys the iterator object.

OfferIterator::max_left()

```
unsigned long max_left()
raises(UnknownMaxLeft);
```

Returns the number of offers remaining in the iterator.

Exceptions

```
UnknownMaxLeft
```

cannot determine the number of remaining offers

OfferIterator::next_n()

```
boolean next_n(in unsigned long n,  
              out OfferSeq offers);
```

Returns `TRUE` if `offers` contains more offer identifiers, and returns `FALSE` if `offers` is `nil`.

Parameters

<code>n</code>	Number of offers to return
<code>ids</code>	List of offers containing at most <code>n</code> elements

CosTrading::Proxy Interface

```

interface Proxy :
    TraderComponents,
    SupportAttributes
{
    typedef Istring [ConstraintRecipe](#costradingproxy-interface);
    struct [ProxyInfo](#costradingproxy-interface)
    {
        ServiceTypeName type;
        Lookup target;
        PropertySeq properties;
        boolean if_match_all;
        [ConstraintRecipe](#costradingproxy-interface) recipe;
        PolicySeq policies_to_pass_on;
    };
    exception [IllegalRecipe](#costradingproxy-interface) {[ConstraintRecipe]
(#costradingproxy-interface) recipe};
    exception [NotProxyOfferId](#costradingproxy-interface) {OfferId id};
    OfferId [export_proxy](#costradingproxy-interface)(in Lookup target, in
ServiceTypeName type,
                                in PropertySeq properties,
                                in boolean if_match_all,
                                in [ConstraintRecipe](#costradingproxy-interface)
recipe,
                                in PolicySeq policies_to_pass_on)
    raises (IllegalServiceType, UnknownServiceType,
            InvalidLookupRef, IllegalPropertyName,
            PropertyTypeMismatch, ReadonlyDynamicProperty,
            MissingMandatoryProperty, [IllegalRecipe](#costradingproxy-
interface),
            DuplicatePropertyName, DuplicatePolicyName);
    void [withdraw_proxy](#costradingproxy-interface)( in OfferId id )
    raises (IllegalOfferId, UnknownOfferId, [NotProxyOfferId](#costradingproxy-
interface));
    ProxyInfo [describe_proxy](#costradingproxy-interface)( in OfferId id )
    raises (IllegalOfferId, UnknownOfferId, [NotProxyOfferId](#costradingproxy-
interface));
};

```

Provides datatypes, exceptions and methods for managing proxy offers.

Proxy::ConstraintRecipe Data Type

```
typedef Istring ConstraintRecipe;
```

A constraint recipe specifies how the trader should rewrite a constraint before invoking the **query** operation of the proxy offer's Lookup interface. Using a constraint recipe, the exporter can have the trader rewrite a constraint into a completely different constraint language (one that is understood by the proxy offer's Lookup target).

The constraint recipe can include the value of properties using the expression "`$(property-name)`". The recipe can also include the entire text of the original constraint using the special syntax "`$*`".

For example, assume the property `name` has the value "Joe", and the property `age` has the value 33. The constraint recipe "Name == \$(name) and Age" would be rewritten as "Name == 'Joe' and Age".

Proxy::ProxyInfo Data Structure

```
struct ProxyInfo
{
    ServiceTypeName type;
    Lookup target;
    PropertySeq properties;
    boolean if_match_all;
    [ConstraintRecipe](#costradingproxy-interface) recipe;
    PolicySeq policies_to_pass_on;
};
```

A complete description of a proxy offer which contains the following members:

<code>type</code>	The service type for which tis offer was exported.
<code>target</code>	The target Lookup object.
<code>properties</code>	A sequence of properties associated with this offer.
<code>if_match_all</code>	If <code>TRUE</code> , type conformance is all that is necessary for this offer to match. If <code>FALSE</code> , the offer must also match the constraint expression.
<code>recipe</code>	The recipe for rewriting the constraint

<code>policies_to_p ass_on</code>	Policies to be appended to the importer's policies and passed along to the target.

Proxy::IllegalRecipe Exception

```
exception IllegalRecipe{[ConstraintRecipe](#costradingproxy-interface)
recipe};
```

An error occurred while parsing the recipe.

Proxy::NotProxyOfferId Exception

```
exception NotProxyOfferId{OfferId id};
```

The offer identifier does not refer to a proxy offer.

Proxy::describe_proxy()

```
[ProxyInfo](#costradingproxy-interface) describe_proxy(in OfferId id)
raises(IllegalOfferId,
       UnknownOfferId,
       [NotProxyOfferId](#costradingproxy-interface));
```

Obtains the description of a proxy offer.

Parameters

<code>id</code>

Identifier of the proxy offer of interest

Exceptions

<code>IllegalOfferId</code>	Offer Identifier is empty or has an invalid format.
<code>UnknownOfferId</code>	No offer was found with the given identifier

<code>NotProxyOfferId</code>	Offer identifier does not refer to a proxy offer

Proxy::export_proxy()

```
OfferId export_proxy(in Lookup target,
                    in ServiceTypeName type,
                    in PropertySeq properties,
                    in boolean if_match_all,
                    in [ConstraintRecipe](#costradingproxy-interface)
recipe,
                    in PolicySeq policies_to_pass_on)
raises(IllegalServiceType,
      UnknownServiceType,
      InvalidLookupRef,
      IllegalPropertyName,
      PropertyTypeMismatch,
      ReadonlyDynamicProperty,
      MissingMandatoryProperty,
      [IllegalRecipe](#costradingproxy-interface),
      DuplicatePropertyName,
      DuplicatePolicyName);
```

Creates a new proxy offer.

Parameters

<code>target</code>	The target Lookup interface
<code>type</code>	The service type for which this offer was exported
<code>properties</code>	A sequence of properties associated with this offer.
<code>if_match_all</code>	If <code>TRUE</code> , type conformance is all that is necessary for this offer to match. If <code>FALSE</code> , the offer must also match the constraint expression.
<code>recipe</code>	The recipe for rewriting the constraint.
<code>policies_to_pass_on</code>	Policies to be appended to the importer's policies and passed along to the target.

Exceptions

<code>IllegalServiceType</code>	Service type name is empty or has invalid format.
<code>UnknownServiceType</code>	Service type was not found in the service type repository.
<code>InvalidLookupRef</code>	Target object reference is <code>nil</code> .
<code>IllegalPropertyName</code>	Property name is empty or has an invalid format.
<code>PropertyTypeMismatch</code>	Property value type does not match the property definition of the service type.
<code>ReadonlyDynamicProperty</code>	Read-only properties cannot have dynamic values.
<code>MissingMandatoryProperty</code>	No value was given for a mandatory property.
<code>IllegalRecipe</code>	An error occurred while parsing the constraint recipe.
<code>DuplicatePropertyname</code>	A property name appeared more than once in the list of properties.
<code>DuplicatePolicyName</code>	A policy name appeared more than once in the list of policies to pass on.

`Proxy::withdraw_proxy()`

```
void withdraw_proxy(in OfferId id)
    raises(IllegalOfferId,
           UnknownOfferId,
           [NotProxyOfferId] (#costradingproxy-interface));
```

Removes a proxy offer.

Parameters

`id`

Identifier of the proxy offer to be withdrawn

Exceptions

IllegalOfferId	Offer identifier is empty or has an invalid format
UnknownOfferId	No offer was found with the given identifier.
NotProxyOfferId	Offer identifier does not refer to a proxy offer

CosTrading::Register Interface

```
interface Register
inherits from CosTrading::TraderComponents, CosTrading::SupportAttributes
```

Provides operations for managing service offers.

Register::OfferInfo Structure

```
struct OfferInfo
{
    Object reference;
    ServiceTypeName type;
    PropertySeq properties;
};
```

A complete description of a service offer.

reference	The object reference associated with this offer. Depending on the configuration of the server, this reference may be nil .
type	The service type for which this offer was exported
properties	A sequence of properties associated with this offer.

Register::IllegalTraderName Exception

```
exception IllegalTraderName
{
    TraderName name;
};
```

The trader name was empty, or a component of the name was not a valid link name.

Register::InterfaceTypeMismatch Exception

```
exception InterfaceTypeMismatch
{
    ServiceTypeName type;
    Object reference;
};
```

If the trader is configured to use the interface repository, then it will attempt to confirm that the interface of the object reference conforms to the interface of the service type. If the trader is able to determine that there is a mismatch, this exception is thrown.

Register::InvalidObjectRef Exception

```
exception InvalidObjectRef
{
    Object ref;
};
```

The object reference is `nil`, and the trader is configured to reject offers with `nil` references.

Register::MandatoryProperty Exception

```
exception MandatoryProperty
{
    ServiceTypeName type;
    PropertyName name;
};
```

A mandatory property cannot be removed.

Register::NoMatchingOffers Exception

```
exception NoMatchingOffers
{
    Constraint constr;
};
```

No matching offers were found matching the constraint expression.

Register::ProxyOfferId Exception

```
exception ProxyOfferId
{
    OfferId id;
};
```

The offer identifier actually refers to a proxy offer.

Register::ReadOnlyProperty Exception

```
exception ReadOnlyProperty
{
    ServiceTypeName type;
    PropertyName name;
};
```

A read-only property cannot be modified.

Register::RegisterNotSupported Exception

```
exception RegisterNotSupported
{
    TraderName name;
};
```

The resolve operation is not supported by this trader.

Register::UnknownPropertyName Exception

```
exception UnknownPropertyName
{
    PropertyName name;
};
```

A property was identified for removal that does not exist in the offer.

Register::UnknownTraderName Exception


```
exception UnknownTraderName
{
    TraderName name;
};
```

The trader name could not be correctly resolved to a trader.

Register::describe()

```
[OfferInfo](#costradingregister-interface) describe(in OfferId id)
    raises(IllegalOfferId,
           UnknownOfferId,
           [ProxyOfferId](#costradingregister-interface));
```

Obtains the description of a service offer and returns it in an [OfferInfo](#) structure.

Parameters

id

Identifier of the offer of interest

Exceptions

IllegalOfferId	Offer identifier is empty or has an invalid format
UnknownOfferId	No offer was found with the given identifier
ProxyOfferId	Offer identifier refers to a proxy offer. Proxy offers must be described using the Proxy interface.

Register::export()

```

OfferId export(in Object reference,
               in ServiceTypeName type,
               in PropertySeq properties)
  raises(InvalidObjectRef,
         IllegalServiceType,
         UnknownServiceType,
         [InterfaceTypeMismatch](#costradingregister-interface),
         IllegalPropertyName,
         PropertyTypeMismatch,
         ReadonlyDynamicProperty,
         MissingMandatoryProperty,
         DuplicatePropertyName);

```

Creates a new service offer and returns an identifier object for the new service. A client wishing to advertise a new offer is called an *exporter*.

Parameters

<code>reference</code>	Reference to an object that enables a client to interact with a remote server.
<code>type</code>	Identifies the service type for which this offer is advertised.
<code>properties</code>	List of named values that describe the service being offered.

Exceptions

<code>InvalidObjectRef</code>	Object reference is <code>nil</code> and the trader has been configured to reject <code>nil</code> references
<code>IllegalServiceType</code>	Service type name is empty or has an invalid format
<code>UnknownServiceType</code>	Service type was not found in service type repository
<code>InterfaceTypeMismatch</code>	Trader was able to determine that the interface of the object reference does not conform to the the interface of the service type
<code>IllegalPropertyName</code>	Property name is empty or has an invalid format
<code>PropertyTypeMismatch</code>	Property value type does not match the property definition of the service type

<code>ReadonlyDynamicProperty</code>	Read-only properties cannot have dynamic values
<code>MissingMandatoryProperty</code>	No value was supplied for a mandatory property
<code>DuplicateProperty</code>	Property name appeared more than once in list of properties

Register::modify()

```
void modify(in OfferId id,
            in PropertyNameSeq del_list,
            in PropertySeq modify_list)
    raises(NotImplemented,
           IllegalOfferId,
           UnknownOfferId,
           [ProxyOfferId] (#costradingregister-interface),
           IllegalPropertyName,
           [UnknownPropertyName] (#costradingregister-interface),
           PropertyTypeMismatch,
           ReadonlyDynamicProperty,
           [MandatoryProperty] (#costradingregister-interface),
           [ReadonlyProperty] (#costradingregister-interface),
           DuplicatePropertyName);
```

Modifies an existing service offer to add new properties, and change or delete existing properties.

Parameters

<code>id</code>	Identifier of the offer to be modified
<code>del_list</code>	Names of properties to be removed
<code>modify_list</code>	Properties to be added or modified

Exceptions

<code>NotImplemented</code>	Trader does not support modification of properties
<code>IllegalOfferId</code>	Offer identifier is empty or has an invalid format

<code>UnknownOfferId</code>	No offer was found with the given identifier
<code>ProxyOfferId</code>	Offer identifier refers to a proxy offer. Proxy offers must be described using the <code>Proxy</code> interface.
<code>IllegalPropertyName</code>	Property name is empty or has an invalid format
<code>UnknownPropertyName</code>	Property to be removed does not exist in offer
<code>PropertyTypeMismatch</code>	Property value type does not match the property definition of the service type
<code>ReadOnlyDynamicProperty</code>	Read-only properties cannot have dynamic values
<code>MandatoryProperty</code>	Mandatory properties cannot be removed
<code>ReadOnlyProperty</code>	Read-only properties cannot be modified
<code>DuplicatePropertyName</code>	Property name appeared more than once in list of properties

Register::resolve()

```
[Register](#costradingregister-interface) resolve(in TraderName name)
    raises([IllegalTraderName](#costradingregister-interface),
          [UnknownTraderName](#costradingregister-interface),
          [RegisterNotSupported](#costradingregister-interface));
```

Resolves a context-relative name for another trader and returns a `Register` object for the resolved trader.

Parameters

`name`

Identifies the trader to be resolved

Exceptions

<code>IllegalTraderName</code>	Trader name was empty, or a component of the name was not a valid link name
<code>UnknownTraderName</code>	Trader name could not be correctly resolved to a trader
<code>RegisterNotSupported</code>	Trader does not support this operation

Register::withdraw()

```
void withdraw(in OfferId id)
    raises(IllegalOfferId,
           UnknownOfferId,
           [ProxyOfferId] (#costradingregister-interface));
```

Removes a service offer.

Parameters

`id`

Identifier of the offer to be withdrawn

Exceptions

<code>IllegalOfferId</code>	Offer identifier is empty or has an invalid format
<code>UnknownOfferId</code>	No offer was found with the given identifier
<code>ProxyOfferId</code>	Offer identifier refers to a proxy offer. Proxy offers must be removed using the <code>Proxy</code> interface.

Register::withdraw_using_constraint()

```
void withdraw_using_constraint(in ServiceTypeName type,
                             in Constraint constr)
    raises(IllegalServiceType,
           UnknownServiceType,
           IllegalConstraint,
           [NoMatchingOffers](#costradingregister-interface));
```

Withdraws all offers for a particular service type that match a constraint expression. Only offers that exactly match the given service type are considered. Proxy offers are not considered, and links are not followed.

Parameters

<code>type</code>	Identifies the service type for which offers are to be removed.
<code>constr</code>	Limits the search to only those offers for which this expression is true. The simplest constraint expression is <code>TRUE</code> , which matches any offer and is an efficient way to withdraw all offers for a service type.

Exceptions

<code>IllegalServiceType</code>	Service type name is empty or has an invalid format
<code>UnknownServiceType</code>	Service type was not found in service type repository
<code>IllegalConstraint</code>	An error occurred while parsing the constraint expression
<code>NoMatchingOffers</code>	No matching offers were found

CosTrading::SupportAttributes Interface

```
interface SupportAttributes
```

The read-only attributes in this interface determine what additional functionality a trader supports, and also provide access to the service type repository used by the trader.

SupportAttributes::supports_dynamic_properties Attribute

```
readonly attribute boolean supports_dynamic_properties;
```

If `FALSE`, offers with dynamic properties will not be considered during a query.

SupportAttributes::supports_modifiable_properties Attribute

```
readonly attribute boolean supports_modifiable_properties;
```

If `FALSE`, the **modify** operation of the `Register` interface will raise `NotImplemented`.

SupportAttributes::supports_proxy_offers Attribute

```
readonly attribute boolean supports_proxy_offers;
```

If `FALSE`, the `proxy_if` attribute of the `TraderComponents` interface will return `nil`, and proxy offers will not be considered during a query.

SupportAttributes::type_repos Attribute

```
readonly attribute TypeRepository type_repos;
```

Returns the object reference of the service type repository used by the trader.

CosTrading::TraderComponents Interface

```
interface TraderComponents
```

Each of the five major interfaces of the `CosTrading` module inherit from this interface. By doing so, any of the *trader components* can be obtained using a reference to any of the other components.

A `nil` value will be returned by an attribute if the trader does not support that interface.

TraderComponents::admin_if Attribute

```
readonly attribute Admin admin_if;
```

TraderComponents::link_if Attribute

```
readonly attribute Link link_if;
```

TraderComponents::lookup_if Attribute

```
readonly attribute Lookup lookup_if;
```

TraderComponents::proxy_if Attribute

```
readonly attribute Proxy proxy_if;
```

TraderComponents::register_if Attribute

```
readonly attribute Register register_if;
```


CosTrading::Dynamic Module

Defines interfaces and types necessary to support dynamic properties. Dynamic properties allow an exporter to delegate a property's value to a third party. For example, rather than exporting an offer with a value of 54 for the property `weight`, you can provide a reference to an object that will dynamically compute the value for `weight`.

Naturally, there are performance issues when using dynamic properties, and therefore an importer may elect to exclude any offers containing dynamic properties.

To export an offer (or a proxy offer) with a dynamic property, you need to do the following:

- Define an object that implements the `DynamicPropEval` interface.
- Create an instance of the `DynamicProp` struct and insert that into the property's `CORBA::Any` value.
- Ensure that the lifetime of the `DynamicPropEval` object is such that it will be available whenever dynamic property evaluation is necessary.

CosTradingDynamic::DynamicProp Struct

```
struct DynamicProp
{
    DynamicPropEval eval_if;
    TypeCode returned_type;
    any extra_info;
};
```

Describes a dynamic property. This struct is inserted into a property's `CORBA::Any` value and provides all of the information necessary for the trader to accomplish dynamic property evaluation.

<code>eval_if</code>	Object reference for evaluation interface
<code>returned_type</code>	Value type expected for the property. The value of <code>returned_type</code> must match the value type of the property as defined by the service type.
<code>extra_info</code>	Additional information used for property evaluation. Orbix Trader supports primitive and user-defined types as values for <code>extra_info</code> .

CosTradingDynamic::DPEvalFailure Exception

```
exception DPEvalFailure
{
    CosTrading::PropertyName name;
    TypeCode returned_type;
    any extra_info;
};
```

Evaluation of a dynamic property failed.

name	Name of the property to be evaluated
returned_type	Value type expected for the property
extra_info	Additional information used for property evaluation

CosTradingDynamic::DynamicPropEval Interface

```
interface DynamicPropEval
```

Defines a single operation for evaluating a dynamic property.

DynamicPropEval::evalDP()

```
any evalDP(in CosTrading::PropertyName name,  
           in TypeCode returned_type,  
           in any extra_info)  
    raises(DPEvalFailure);
```

Evaluates a dynamic property and returns the objects properties.

Parameters

<code>name</code>	Name of the property to be evaluated
<code>returned_type</code>	Value type expected for the property
<code>extra_info</code>	Additional information used for property evaluation

Exceptions

```
DPEvalFailure
```

Evaluation of the property failed

CosTradingRepos Module

Contains the `ServiceTypeRepository` interface, which manages information about service types for the trading service.

A service type represents the information needed to describe a service, including an interface type defining the computational signature of the service, and zero or more properties that augment the interface. Each traded service, or service offer, is associated with a service type.

There are several components of a service type:

Interface:

The interface repository identifier for an interface determines the computational signature of a service. If the trading service is configured to use the interface repository, and this identifier resolves to an `InterfaceDef` object in the interface repository, then the trading service will ensure that an object in an exported offer conforms to this interface.

Properties:

Any number of properties can be defined for a service type. Properties typically represent behavioral, non-functional and non-computational aspects of the service.

Super types:

Service types can be related in a hierarchy that reflects interface type inheritance and property type aggregation. This hierarchy provides the basis for deciding if a service of one type may be substituted for a service of another type.

When a new service type is added that has one or more super types, the service type repository performs a number of consistency checks. First, the repository ensures (if possible) that the interface of the new type conforms to the interface of the super type. Second, the repository checks for any property that has been redefined in the new service type to ensure that it has the same type as that of the super type, and that its mode is at least as strong as its mode in the super type.

CosTradingRepos::ServiceTypeRepository Interface

```
interface ServiceTypeRepository
```

Contains types and operations for managing the repository.

ServiceTypeRepository::Identifier Alias

```
typedef CosTrading::Istring Identifier;
```

The interface repository identifier of an interface. For example, the identifier of this interface is

```
IDL:omg.org/CosTradingRepos/ServiceTypeRepository:1.0.
```

ServiceTypeRepository::PropStructSeq Sequence

```
typedef sequence<PropStruct> PropStructSeq;
```

ServiceTypeRepository::ServiceTypeNameSeq Sequence

```
typedef sequence<CosTrading::ServiceTypeName> ServiceTypeNameSeq;
```

ServiceTypeRepository::ListOption Enum

```
enum ListOption
{
    all,
    since
};
```

Indicates which service types are of interest.

all	All service types

since	All service types since a particular incarnation

ServiceTypeRepository::PropertyMode Enum

```
enum PropertyMode
{
    PROP_NORMAL,
    PROP_READONLY,
    PROP_MANDATORY,
    PROP_MANDATORY_READONLY
};
```

Each property has a mode associated with it. The property mode places restrictions on an exporter when exporting and modifying service offers.

PROP_NORMAL	Property is optional
PROP_READONLY	Property is optional, but once a value has been supplied, it cannot be changed
PROP_MANDATORY	A value for this property must be supplied when the offer is exported, but can also be changed at some later time
PROP_MANDATORY_READONLY	A value for this property must be supplied when the offer is exported, and cannot be changed

ServiceTypeRepository::IncarnationNumber Structure

```
struct IncarnationNumber
{
    unsigned long high;
    unsigned long low;
};
```

Represents a unique, 64-bit identifier that is assigned to each service type. This will be replaced by long long when that type is widely supported.

ServiceTypeRepository::PropStruct Structure

```
struct PropStruct
{
    CosTrading::PropertyName name;
    TypeCode value_type;
    PropertyMode mode;
};
```

A complete description of a property.

<code>name</code>	Name of the property
<code>value_type</code>	<code>CORBA::TypeCode</code> describing the type of values allowed for the property
<code>mode</code>	Determines whether a property is mandatory, and whether the property can be modified

ServiceTypeRepository::TypeStruct Structure

```
struct TypeStruct
{
    [Identifier](../corbaabstractinterfacedef_interface/
corbaabstractinterfacedef_interface.md#common-corba-data-types) if_name;
    [PropStructSeq](#costradingreposservicetyperepository-interface) props;
    [ServiceTypeNameSeq](#costradingreposservicetyperepository-interface)
super_types;
    boolean masked;
    [IncarnationNumber](#costradingreposservicetyperepository-interface)
incarnation;
};
```

A complete description of a service type.

<code>if_name</code>	Interface repository identifier for an interface
<code>props</code>	Defines the properties associated with this type
<code>super_types</code>	Service types from which this type inherits property definitions
<code>masked</code>	If <code>TRUE</code> , no new offers can be exported for this type

<code>incarnation</code>	Unique, 64-bit identifier for this type

ServiceTypeRepository::SpecifiedServiceTypes Union

```
union SpecifiedServiceTypes switch(ListOption)
{
case since: [IncarnationNumber](#costradingreposservicetyperepository-
interface) incarnation;
};
```

Provides two ways of retrieving the names of the service types managed by the repository. The union's discriminator can be set to `all` if you want to obtain all of the service type names.

<code>since</code>	Set this value with an incarnation number; only the names of those types whose incarnation numbers are greater than or equal to this value will be returned

ServiceTypeRepository::AlreadyMasked Exception

```
exception AlreadyMasked {CosTrading::ServiceTypeName name};
```

The service type cannot be masked if it is already masked.

ServiceTypeRepository::DuplicateServiceTypeName Exception

```
exception DuplicateServiceTypeName
{
CosTrading::ServiceTypeName name;
};
```

The same service type appeared more than once in the list of super types.

ServiceTypeRepository::HasSubTypes Exception


```
exception HasSubTypes
{
    CosTrading::ServiceTypeName the_type;
    CosTrading::ServiceTypeName sub_type;
};
```

A service type cannot be removed if it is the super type of any other type.

ServiceTypeRepository::InterfaceTypeMismatch Exception

```
exception InterfaceTypeMismatch
{
    CosTrading::ServiceTypeName base_service;
    [Identifier](../corbaabstractinterfacedef_interface/
corbaabstractinterfacedef_interface.md#common-corba-data-types) base_if;
    CosTrading::ServiceTypeName derived_service;
    [Identifier](../corbaabstractinterfacedef_interface/
corbaabstractinterfacedef_interface.md#common-corba-data-types) derived_if;
};
```

The interface of the new (*derived*) service type does not conform to the interface of a super type (*base service*).

ServiceTypeRepository::NotMasked Exception

```
exception NotMasked {CosTrading::ServiceTypeName name};
```

The service type cannot be unmasked if it is not currently masked.

ServiceTypeRepository::ServiceTypeExists Exception

```
exception ServiceTypeExists {CosTrading::ServiceTypeName name};
```

Another service type exists with the given name.

ServiceTypeRepository::ValueTypeRedefinition Exception

```
exception ValueTypeRedefinition
{
    CosTrading::ServiceTypeName type_1;
    [PropStruct](#costradingreposservicetyperepository-interface)
definition_1;
    CosTrading::ServiceTypeName type_2;
    [PropStruct](#costradingreposservicetyperepository-interface)
definition_2;
};
```

The definition of a property in the new service type (*type_1*) conflicts with the definition in a super type (*type_2*). This error can result if the `value_type` members do not match, or if the mode of the property is weaker than in the super type.

ServiceTypeRepository::incarnation Attribute

```
readonly attribute [IncarnationNumber](#costradingreposservicetyperepository-
interface) incarnation;
```

Determines the next incarnation number that will be assigned to a new service type. This could be used to synchronize two or more service type repositories, for example.

ServiceTypeRepository::add_type()

```
[IncarnationNumber](#costradingreposservicetyperepository-interface)
add_type(in CosTrading::ServiceTypeName name,
          in [Identifier](../
corbaabstractinterfacedef_interface/
corbaabstractinterfacedef_interface.md#common-corba-data-types) if_name,
          in [PropStructSeq]
(#costradingreposservicetyperepository-interface) props,
          in [ServiceTypeNameSeq]
(#costradingreposservicetyperepository-interface) super_types)
raises(CosTrading::IllegalServiceType,
       [ServiceTypeExists](#costradingreposservicetyperepository-interface),
       [InterfaceTypeMismatch](#costradingregister-interface),
       CosTrading::IllegalPropertyName,
       CosTrading::DuplicatePropertyName,
       [ValueTypeRedefinition](#costradingreposservicetyperepository-
interface),
       CosTrading::UnknownServiceType,
       [DuplicateServiceTypeName](#costradingreposservicetyperepository-
interface));
```

Adds a new service type and returns a unique identifier for the new type.

Parameters

<code>name</code>	Name to be used for the new type
<code>if_name</code>	Interface repository identifier for an interface
<code>props</code>	Properties defined for this interface interface
<code>super_types</code>	Zero or more super types from which this type will inherit interface and property definitions

Exceptions

<code>CosTrading::IllegalServiceType</code>	Service type name is empty or has an invalid format
<code>ServiceTypeExists</code>	Service type already exists with the same name
<code>InterfaceTypeMismatch</code>	Interface of the new type does not conform to the interface of a super type

<code>CosTrading::IllegalPropertyName</code>	Property name is empty or has an invalid format
<code>CosTrading::DuplicatePropertyName</code>	Same property name appears more than once in <code>props</code>
<code>ValueTypeRedefinition</code>	Property definition in props conflicts with a definition in a super type
<code>CosTrading::UnknownServiceType</code>	Super type does not exist
<code>DuplicateServiceTypeNames</code>	Same super type name appears more than once in <code>super_types</code>

ServiceTypeRepository::describe_type()

```
[TypeStruct] (#costradingreposservicetyperepository-interface)
describe_type(in CosTrading::ServiceTypeName name)
raises(CosTrading::IllegalServiceType,
       CosTrading::UnknownServiceType);
```

Gets the description of a service type and returns a `TypeStruct` with the description.

Parameters

name

Name of the type of interest

Exceptions

<code>CosTrading::IllegalServiceType</code>	Service type name is empty or has an invalid format
<code>CosTrading::UnknownServiceType</code>	Service type does not exist

ServiceTypeRepository::fully_describe_type()

```
[TypeStruct](#costradingreposservicetyperepository-interface)
fully_describe_type(in CosTrading::ServiceTypeName
                    name)
raises(CosTrading::IllegalServiceType,
       CosTrading::UnknownServiceType);
```

Obtains the *full* description of a service type. The `super_types` member of a full description contains the names of the types in the transitive closure of the super type relation. The `props` member includes all properties inherited from the transitive closure of the super types. A [TypeStruct](#) containing the full description is returned.

Parameters

name

Name of the type of interest

Exceptions

<code>CosTrading::IllegalServiceType</code>	Service type name is empty or has an invalid format
<code>CosTrading::UnknownServiceType</code>	Service type does not exist

ServiceTypeRepository::list_types()

```
[ServiceTypeNameSeq](#costradingreposservicetyperepository-interface)
list_types(in [SpecifiedServiceTypes](#costradingreposservicetyperepository-
interface)
          which_types);
```

Lists the names of some or all of the service types in the repository.

Parameters

which_types

Specifies which types are of interest

ServiceTypeRepository::mask_type()

```
void mask_type(in CosTrading::ServiceTypeName name)
raises(CosTrading::IllegalServiceType,
       CosTrading::UnknownServiceType,
       [AlreadyMasked] (#costradingreposservicetyperepository-interface));
```

Masks a service type so that offers can no longer be exported for it. Masking a service type is useful when the type is considered deprecated; in other words, no new offers should be allowed, but existing offers are still supported.

Parameters

name

Name of the type to be masked

Exceptions

CosTrading:: IllegalServiceType	Service type name is empty or has an invalid format
CosTrading:: UnknownServiceType	Service type does not exist
AlreadyMasked	Service type is already masked

ServiceTypeRepository::remove_type()

```
void remove_type(in CosTrading::ServiceTypeName name)
raises(CosTrading::IllegalServiceType,
       CosTrading::UnknownServiceType,
       [HasSubTypes] (#costradingreposservicetyperepository-interface));
```

Removes an existing service type.

Parameters

name

Name of the type to be removed

Exceptions

CosTrading::IllegalServiceType	Service type name is empty or has an invalid format
CosTrading::UnknownServiceType	Service type does not exist
HasSubTypes	Service type cannot be removed if it is the super type of any other type

ServiceTypeRepository::unmask_type()

```
void unmask_type(in CosTrading::ServiceTypeName name)
raises(CosTrading::IllegalServiceType,
       CosTrading::UnknownServiceType,
       [NotMasked] (#costradingreposservicetyperepository-interface));
```

Unmasks a masked service type so that offers can be exported for it.

Parameters

name

Name of the type to be unmasked

Exceptions

CosTrading::IllegalServiceType	Service type name is empty or has an invalid format
CosTrading::UnknownServiceType	Service type does not exist
NotMasked	Service type is not currently masked

CosTransactions Overview

The Object Management Group's (OMG) object transaction service (OTS) defines interfaces that integrate transactions into the distributed object paradigm. The OTS interface enables developers to manage transactions under two different models of transaction propagation, implicit and explicit:

- In the implicit model, the transaction context is associated with the client thread; when client requests are made on transactional objects, the transaction context associated with the thread is propagated to the object implicitly.
- In the explicit model, the transaction context must be passed explicitly when client requests are made on transactional objects in order to propagate the transaction context to the object.

Keep the following in mind:

- Applications must include the header file `CosTransactions.hh`.
- All of the OTS classes are nested within the `CosTransactions` namespace. Therefore, you must prefix `CosTransactions` to the OTS class and function names when using them in your application.
- All of the OTS class methods can throw the `CORBA::SystemException` exception if an object request broker (ORB) error occurs.

Overview of Classes

The OTS classes provide the following functionality:

- Managing transactions under the implicit model:

```
Current
```

- Managing transactions under the explicit model:

```
TransactionFactory  
Control  
Coordinator  
Terminator
```

- Managing resources in the CORBA environment:


```
RecoveryCoordinator
Resource
SubtransactionAwareResource
Synchronization
```

- Defining transactional interfaces in the CORBA environment:

```
TransactionalObject
```

- Reporting system errors:

```
HeuristicCommit
HeuristicHazard
HeuristicMixed
HeuristicRollback
Inactive
InvalidControl
INVALID_TRANSACTION
NoTransaction
NotPrepared
NotSubtransaction
SubtransactionsUnavailable
TRANSACTION_MODE
TRANSACTION_REQUIRED
TRANSACTION_ROLLEDBACK
TRANSACTION_UNAVAILABLE
Unavailable
```

General Exceptions

Errors are handled in OTS by using exceptions. Exceptions provide a way of returning error information back through multiple levels of procedure or method calls, propagating this information until a method or procedure is reached that can respond appropriately to the error.

Each of the following exceptions are implemented as classes. The exceptions are shown here in two tables: one for the OTS exceptions and another for the system exceptions.

Table 9: OTS Exceptions

Exception	Description
<code>HeuristicCommit</code>	This exception is thrown to report that a heuristic decision was made by one or more participants in a transaction and that all updates have been committed. See Also: <code>Resource class</code>
<code>HeuristicHazard</code>	This exception is thrown to report that a heuristic decision has possibly been made by one or more participants in a transaction and the outcome of all participants in the transaction is unknown. See Also: <code>Current::commit()</code> <code>Resource class</code> <code>Terminator::commit()</code>
<code>HeuristicMixed</code>	This exception is thrown to report that a heuristic decision was made by one or more participants in a transaction and that some updates have been committed and others rolled back. See Also: <code>Current::commit()</code> <code>Resource class</code> <code>Terminator::commit()</code>
<code>HeuristicRollback</code>	This exception is thrown to report that a heuristic decision was made by one or more participants in a transaction and that all updates have been rolled back. See Also: <code>Resource class</code>
<code>Inactive</code>	This exception is thrown when a transactional operation is requested for a transaction, but that transaction is already prepared. See Also: <code>Coordinator::create_subtransaction()</code> <code>Coordinator::register_resource()</code> <code>Coordinator::register_subtran_aware()</code> <code>Coordinator::rollback_only()</code>
<code>InvalidControl</code>	This exception is thrown when an invalid Control object is used in an attempt to resume a suspended transaction. See Also: <code>Control class</code> <code>Current::resume()</code>

Exception	Description
<code>NotPrepared</code>	This exception is thrown when an operation (such as a <code>commit()</code>) is requested for a resource, but that resource is not prepared. See Also: <code>RecoveryCoordinator::replay_completion()</code> <code>Resource class</code>
<code>NoTransaction</code>	This exception is thrown when an operation is requested for the current transaction, but no transaction is associated with the client thread. See Also: <code>Current::commit()</code> <code>Current::rollback()</code> <code>Current::rollback_only()</code>
<code>NotSubtransaction</code>	This exception is thrown when an operation that requires a subtransaction is requested for a transaction that is not a subtransaction. See Also: <code>Coordinator::register_subtran_aware()</code>
<code>SubtransactionsUnavailable</code>	This exception is thrown when an attempt is made to create a subtransaction. See Also: <code>Coordinator::create_subtransaction()</code> <code>Current::begin()</code>
<code>Unavailable</code>	This exception is thrown when a Terminator or Coordinator object cannot be provided by a Control object due to environment restrictions. See Also: <code>Control::get_coordinator()</code> <code>Control::get_terminator()</code>

The following table shows the system exceptions that can be thrown:

Table 10: System Exceptions

Exception	Description
<code>INVALID_TRANSACTION</code>	This exception is raised when the transaction context is invalid for a request.

Exception	Description
<code>TRANSACTION_MODE</code>	This exception is raised when there is a mismatch between the transaction policy in the target object's IOR and the current transaction mode (see Table 1).
<code>TRANSACTION_REQUIRED</code>	This exception is raised when an invocation on an object expecting a transaction is performed with no transaction (see Table 1).
<code>TRANSACTION_ROLLEDBACK</code>	This exception is raised when a transactional operation (such as <code>commit()</code>) is requested for a transaction that has been rolled back or marked for rollback. See Also: <code>Current::commit()</code> <code>Terminator::commit()</code>
<code>TRANSACTION_UNAVAILABLE</code>	This exception is raised when a transaction invocation is requested but the transaction service is not available.

General Data Types

OTS defines enumerated data types to represent the status of a transaction object during its lifetime and to indicate a participant's vote on the outcome of a transaction.

Status Enumeration Type

```
enum Status{
    StatusActive,
    StatusMarkedRollback,
    StatusPrepared,
    StatusCommitted,
    StatusRolledBack,
    StatusUnknown,
    StatusNoTransaction,
    StatusPreparing,
    StatusCommitting,
    StatusRollingBack
};
```

The `Status` enumerated type defines values that are used to indicate the status of a transaction. Status values are used in both the implicit and explicit models of transaction demarcation defined by OTS. The `Current::get_status()` operation can be called to return the transaction status if the implicit model is used. The `Coordinator::get_status()` operation can be called to return the transaction status if the explicit model is used.

The `Status` values indicate the following:

StatusActive	Processing of a transaction is still in progress.
StatusMarkedRollback	A transaction is marked to be rolled back.
StatusPrepared	A transaction has been prepared but not completed.
StatusCommitted	A transaction has been committed and the effects of the transaction have been made permanent.
StatusRolledBack	A transaction has been rolled back.
StatusUnknown	The status of a transaction is unknown.
StatusNoTransaction	A transaction does not exist in the current transaction context.
StatusPreparing	A transaction is preparing to commit.
StatusCommitting	A transaction is in the process of committing.
StatusRollingBack	A transaction is in the process of rolling back.

See Also `CosTransactions::Coordinator::get_status()`

```
CosTransactions::Current::get_status()
```

Vote Enumeration Type

```
enum Vote{
    VoteCommit,
    VoteRollback,
    VoteReadOnly
};
```

The `Vote` enumerated type defines values for the voting status of transaction participants. The participants in a transaction each vote on the outcome of a transaction during the two-phase commit process. In the prepare phase, a `Resource` object can vote whether to commit or abort a transaction. If a `Resource` has not modified any data as part of the transaction, it can vote `VoteReadOnly` to indicate that its participation does not affect the outcome of the transaction. The `Vote` values specify the following:

<code>VoteCommit</code>	The value used to indicate a vote to commit a transaction.
<code>VoteRollback</code>	The value used to indicate a vote to abort (rollback) a transaction.
<code>VoteReadOnly</code>	The value used to indicate no vote on the outcome of a transaction.

See Also `CosTransactions::Resource`

OTSPolicyValue Data Type

```
typedef unsigned short OTSPolicyValue;
const OTSPolicyValue REQUIRES = 1;
const OTSPolicyValue FORBIDS = 2;
const OTSPolicyValue ADAPTS = 3;
const CORBA::PolicyType OTS_POLICY_TYPE = 56;
```

The `OTSPolicyValue` data type is used to create POA policy objects that define behavior of objects during invocations, both with and without a current transaction.

The `CORBA::ORB::create_policy()` operation is used to create the policy objects (passing in the appropriate `OTSPolicyValue` value). The policy object is passed in the list of policy objects passed to `PortableServer::POA::create_POA()`.

The `OTSPolicyValue` values indicate the following:

REQUIRES	The target object depends on the presence of a transaction. If there is no current transaction, a TRANSACTION_REQUIRED system exception is raised.
FORBIDS	The target object depends on the absence of a transaction. If there is a current transaction, the INVALID_TRANSACTION system exception is raised. When there is no current transaction, the behavior of the FORBIDS policy is also affected by the NonTxTargetPolicy .
ADAPTS	The target object is invoked within the current transaction, whether there is one or not.

You cannot create a POA that mixes the **OTSPolicyValue** **FORBIDS** or **ADAPTS** values with the **InvocationPolicyValue** **EITHER** or **UNSHARED** values. Attempting to do so raises **PortableServer::InvalidPolicy** exception.

Examples The following example shows the **ADAPTS** value:

```
//C++
CORBA::ORB_var orb = ...
CORBA::Any policy_val;
policy_val <=< CosTransactions::ADAPTS;
CORBA::Policy_var policy =
    orb->create_policy(CosTransactions::OTS_POLICY_TYPE,
                     policy_val);
```

See Also `[CosTransactions](#general-data-types) :: No nTxTargetPolicyValue`

`CosTransactions::TransactionalObject`

InvocationPolicyValue Data Type

```
typedef unsigned short InvocationPolicyValue;
const InvocationPolicyValue EITHER = 0;
const InvocationPolicyValue SHARED = 1;
const InvocationPolicyValue UNSHARED = 2;
const CORBA::PolicyType INVOCATION_POLICY_TYPE = 55;
```

The **InvocationPolicyValue** data type is used to create POA policy objects that define the behavior of objects with respect to the *shared* and *unshared* transaction models.

The shared transaction model represents a standard end-to-end transaction that is shared between the client and the target object. The unshared transaction model uses asynchronous messaging where separate transactions are used along the invocation path. Hence, the client and the target object do not share the same transaction.

The `CORBA::ORB::create_policy()` operation is used to create the policy objects (passing in the appropriate `InvocationPolicyValue`). The policy object is passed in the list of policy objects passed to `PortableServer::POA::create_POA()`.

The `InvocationPolicyValue` data type values indicate the following:

<code>EITHER</code>	The target object supports both shared and unshared invocations.
<code>SHARED</code>	The target object supports synchronous invocations and asynchronous includes that do not involve a routing element.
<code>UNSHARED</code>	The target object.

You cannot create a POA that mixes the `InvocationPolicyValue` `EITHER` or `UNSHARED` values with the `OTSPolicyValue` `FORBIDS` or `ADAPTS` values. Attempting to do this raises a `PortableServer::InvalidPolicy` exception.

If no `InvocationPolicy` object is passed to `create_POA()`, the `InvocationPolicy` defaults to `SHARED`.

Note

The unshared transaction model is not supported in this release.

Examples The following example shows the `SHARED` value:

```
//C++
CORBA::ORB_var orb = ...
CORBA::Any policy_val;
policy_val <=< CosTransactions::SHARED;
CORBA::Policy_var policy =
    orb->create_policy(CosTransactions::INVOCATION_POLICY_TYPE,
                      policy_val);
```

See Also `[CosTransactions](#general-data-types)::OTSPolicyValue`


```
[CosTransactio](#general-data-types)ns::NonTxTargetPolicyValue
```

NonTxTargetPolicyValue Data Type

```
typedef unsigned short NonTxTargetPolicyValue;
const NonTxTargetPolicyValue PREVENT = 0;
const NonTxTargetPolicyValue PERMIT = 1;
const CORBA::PolicyType NON_TX_TARGET_POLICY_TYPE = 57;
```

The `NonTxTargetPolicyValue` data type is used to create policy objects used by clients to affect the behavior of invocations on objects with an `OTSPolicy` of `FORBIDS`.

The `CORBA::ORB::create_policy()` operation creates the policy objects (passing the appropriate `NonTxTargetPolicyValue`). The policy object is passed in the list of policy objects passed to `CORBA::PolicyManager::set_policy_overrides()` and `CORBA::PolicyCurrent::set_policy_overrides()`.

See the `CORBA::PolicyCurrent` and `CORBA::PolicyManager` classes for more details on setting policies.

The behavior of the `NonTxTargetPolicy` values apply to invocations where there is a current transaction and the target object has the `OTSPolicyValue` of `FORBIDS`. The `NonTxTargetPolicy` values indicate the following:

<code>PREVENT</code>	The invocation is prevented from proceeding and the system exception <code>INVALID_TRANSACTION</code> is raised.
<code>PERMIT</code>	The invocation proceeds but not in the context of the current transaction.

The default `NonTxTargetPolicy` is `PREVENT`.

Examples The following example shows the `PERMIT` value:

```
//C++
CORBA::ORB_var orb = ...
CORBA::Any policy_val;
policy_val <=< CosTransactions::PERMIT;
CORBA::Policy_var policy =
    orb->create_policy(CosTransactions::NON_TX_TARGET_POLICY_TYPE,
                      policy_val);
```

See Also `[CosTransactions](#general-data-types) ::O TSPolicyValue`

`[CosTran](#general-data-types)sactions::InvocationPolicyValue`

TransactionPolicyValue Data Type

```
typedef unsigned short TransactionPolicyValue;
const TransactionPolicyValue Allows_shared = 0;
const TransactionPolicyValue Allows_none = 1;
const TransactionPolicyValue Requires_shared = 2;
const TransactionPolicyValue Allows_unshared = 3;
const TransactionPolicyValue Allows_either = 4;
const TransactionPolicyValue Requires_unshared = 5;
const TransactionPolicyValue Requires_either = 6;
const CORBA::PolicyType TRANSACTION_POLICY_TYPE = 36;
```

The `TransactionalPolicyValue` data type has been deprecated and replaced with the [OTSPolicyValue](#) and [InvocationPolicyValue](#) types.

The `TransactionalPolicyValue` data type has been retained in this release for backward compatibility. See the *CORBA Programmer's Guide* for details of interoperability with previous Orbix releases.

CosTransactions::Control Class

The `Control` class enables explicit control of a factory-created transaction; the factory creates a transaction and returns a `Control` instance associated with the transaction. The `Control` object provides access to the Coordinator and Terminator objects used to manage and complete the transaction.

A `Control` object can be used to propagate a transaction context explicitly. By passing a `Control` object as an argument in a request, the transaction context can be propagated. `TransactionFactory::create()` can be used to create a transaction and return the `Control` object associated with it.

// C++

```
class Control {
public:
    Terminator_ptr [get_terminator()](#costransactionscontrol-class);
    Coordinator_ptr [get_coordinator()](#costransactionscontrol-class);
};
typedef Control *Control_ptr;
class Control_var;
```

See Also `CosTransactions::Coordinator`

```
CosTransactions::Current::get_control()
CosTransactions::Coordinator::get_status()
CosTransactions::Terminator
CosTransactions::TransactionFactory::create()
NoTransaction
NotSubtransaction
```

`Control::get_coordinator()`

// C++

```
Coordinator_ptr get_coordinator()
    throw(CORBA::SystemException, Unavailable);
```

`get_coordinator()` returns the Coordinator object for the transaction with which the `Control` object is associated. The returned Coordinator object can be used to determine the status of the transaction, the relationship between the associated transaction and other transactions, to create subtransactions, and so on.

Exceptions

Unavailable

The Coordinator associated with the `Control` object is not available.

See Also `CosTransactions::Coordinator`

`Control::get_terminator()`

// C++

```
Terminator_ptr get_terminator()
    throw(CORBA::SystemException, Unavailable);
```

`get_terminator()` returns the Terminator object for the transaction with which the `Control` object is associated. The returned Terminator object can be used to either commit or roll back the transaction.

Exceptions

Unavailable

The Terminator associated with the `Control` object is not available.

See Also `CosTransactions::Terminator`

CosTransactions::Coordinator Class

The `Coordinator` class enables explicit control of a factory-created transaction; the factory creates a transaction and returns a `Control` instance associated with the transaction. `Control::get_coordinator()` returns the `Coordinator` object used to manage the transaction.

The operations defined by the `Coordinator` class can be used by the participants in a transaction to determine the status of the transaction, determine the relationship of the transaction to other transactions, mark the transaction for rollback, and create subtransactions.

The `Coordinator` class also defines operations for registering resources as participants in a transaction and registering subtransaction-aware resources with a subtransaction.

// C++

```

class Coordinator {
public:
    char *[get_transaction_name()](#costransactionscoordinator-class);
    Status [get_status()](#costransactionscoordinator-class);
    Status [get_parent_status()](#costransactionscoordinator-class);
    Status [get_top_level_status()](#costransactionscoordinator-class);
    CORBA::Boolean [is_same_transaction](#costransactionscoordinator-class)
(Coordinator_ptr);
    CORBA::Boolean [is_related_transaction](#costransactionscoordinator-
class)(Coordinator_ptr);
    CORBA::Boolean [is_ancestor_transaction](#costransactionscoordinator-
class)(Coordinator_ptr);
    CORBA::Boolean [is_descendant_transaction](#costransactionscoordinator-
class)(Coordinator_ptr);
    CORBA::Boolean [is_top_level_transaction()](#costransactionscoordinator-
class);
    unsigned long [hash_transaction()](#costransactionscoordinator-class);
    unsigned long [hash_top_level_tran()](#costransactionscoordinator-class);
    RecoveryCoordinator [register_resource](#costransactionscoordinator-
class)(Resource);
    void [register_subtran_aware](#costransactionscoordinator-class)
(SubtransactionAwareResource);
    Control_ptr [create_subtransaction()](#costransactionscoordinator-class);
    void [rollback_only()](#costransactionscoordinator-class);
    PropagationContext* [get_txcontext()](#costransactionscoordinator-class)
};
typedef Coordinator *Coordinator_ptr;
class Coordinator_var;

```

See Also CosTransactions::Control

```

CosTransactions::Control::get_coordinator()
CosTransactions::Terminator

```

Coordinator::create_subtransaction()

// C++

```

Control_ptr create_subtransaction()
    throw(CORBA::SystemException, Inactive, SubtransactionsUnavailable);

```

`create_subtransaction()` returns the `Control` object associated with the new subtransaction.

`create_subtransaction()` creates a new subtransaction for the transaction associated with the `Coordinator` object. A subtransaction is one that is embedded within another transaction; the transaction within which the subtransaction is embedded is referred to as its parent. A transaction that has no parent is a top-level transaction. A subtransaction executes within the scope of its parent transaction and can be used to isolate failures; if a subtransaction fails, only the subtransaction is rolled back. If a subtransaction commits, the effects of the commit are not permanent until the parent transaction commits. If the parent transaction rolls back, the subtransaction is also rolled back.

Exceptions

<code>SubtransactionsUnavailable</code>	Subtransactions are not supported.
<code>Inactive</code>	The transaction is already prepared.

See Also `CosTransactions::Control`

`Coordinator::get_parent_status()`

// C++

```
Status get_parent_status()
    throw(CORBA::SystemException);
```

`get_parent_status()` returns the status of the parent of the transaction associated with the `Coordinator` object. For more information, see `create_subtransaction()`.

The status returned indicates which phase of processing the transaction is in. See the reference page for the `Status` type for information about the possible status values. If the transaction associated with the `Coordinator` object is a subtransaction, the status of its parent transaction is returned. If there is no parent transaction, the status of the transaction associated with the `Coordinator` object itself is returned.

See Also `CosTransactions::Coordinator::create_subtransaction()`

```
CosTransactions::Coordinator::get_status()
CosTransactions::Coordinator::get_top_level_status()
CosTransactions::Status
```

`Coordinator::get_status()`

// C++

```
Status get_status()
    throw(CORBA::SystemException);
```

`get_status()` returns the status of the transaction associated with the `Coordinator` object. The status returned indicates which phase of processing the transaction is in. See the reference page for the Status type for information about the possible status values.

See Also `CosTransactions::Coordinator::get_parent_status()`

```
CosTransactions::Coordinator::get_top_level_status()
CosTransactions::Status
```

`Coordinator::get_top_level_status()`

// C++

```
Status get_top_level_status()
    throw(CORBA::SystemException);
```

`get_top_level_status()` returns the status of the top-level ancestor of the transaction associated with the `Coordinator` object. See `Coordinator::create_subtransaction()` for more information.

The status returned indicates which phase of processing the transaction is in. See the reference page for the Status type for information about the possible status values. If the transaction associated with the `Coordinator` object is the top-level transaction, its status is returned.

See Also `CosTransactions::Coordinator::create_subtransaction()`

```
CosTransactions::Coordinator::get_status()
CosTransactions::Coordinator::get_parent_status()
CosTransactions::Status
```

`Coordinator::get_transaction_name()`

// C++

```
char *get_transaction_name();
```

`get_transaction_name()` returns the name of the transaction associated with the `Coordinator` object.

Coordinator::get_txcontext()

// C++

```
PropagationContext* Coordinator::get_txcontext()
    throw (CORBA::SystemException, Unavailable);
```

Returns the propagation context object which is used to export the current transaction to a new transaction service domain.

Exceptions

Unavailable

The propagation context is unavailable.

See Also CosTransactions::TransactionFactory::recreate()

Coordinator::hash_top_level_tran()

// C++

```
unsigned long hash_top_level_tran()
    throw(CORBA::SystemException);
```

`hash_top_level_tran()` returns a hash code for the top-level ancestor of the transaction associated with the `Coordinator` object. If the transaction associated with the `Coordinator` object is the top-level transaction, its hash code is returned. See `create_subtransaction()` for more information. The returned hash code is typically used as an index into a table of `Coordinator` objects. The low-order bits of the hash code can be used to hash into a table with a size that is a power of two.

See Also CosTransactions::Coordinator::create_subtransaction()

```
CosTransactions::Coordinator::hash_transaction()
```

Coordinator::hash_transaction()

// C++

```
unsigned long hash_transaction()
    throw(CORBA::SystemException);
```

`hash_transaction()` returns a hash code for the transaction associated with the `Coordinator` object.

See Also `CosTransactions::Coordinator::hash_top_level_tran()`

`Coordinator::is_ancestor_transaction()`

// C++

```
CORBA::Boolean is_ancestor_transaction(
    Coordinator_ptr tc
)
    throw(CORBA::SystemException);
```

`is_ancestor_transaction()` returns true if the transaction is an ancestor or if the two transactions are the same; otherwise, the method returns false.

Parameters

`tc`

Specifies the coordinator of another transaction to compare with the `Coordinator` object.

`is_ancestor_transaction()` determines whether the transaction associated with the `Coordinator` object is an ancestor of the transaction associated with the coordinator specified in the `tc` parameter. See `create_subtransaction()` for more information.

See Also `CosTransactions::Coordinator::is_descendant_transaction()`

```
CosTransactions::Coordinator::is_related_transaction()
CosTransactions::Coordinator::is_same_transaction()
CosTransactions::Coordinator::create_subtransaction()
```

`Coordinator::is_descendant_transaction()`

// C++

```
CORBA::Boolean is_descendant_transaction(Coordinator_ptr tc)
    throw(CORBA::SystemException);
```

`is_descendant_transaction()` returns true if the transaction is a descendant or if the two transactions are the same; otherwise, the method returns false.

Parameters

`tc`

Specifies the coordinator of another transaction to compare with the `Coordinator` object.

`is_descendant_transaction()` determines whether the transaction associated with the `Coordinator` object is a descendant of the transaction associated with the coordinator specified in the `tc` parameter. See `Coordinator::create_subtransaction()` for more information.

See Also `CosTransactions::Coordinator::is_descendant_transaction()`

```
CosTransactions::Coordinator::is_related_transaction()
CosTransactions::Coordinator::is_same_transaction()
CosTransactions::Coordinator::is_top_level_transaction()
CosTransactions::Coordinator::create_subtransaction()
```

`Coordinator::is_related_transaction()`

// C++

```
CORBA::Boolean is_related_transaction(
    Coordinator_ptr tc
)
    throw(CORBA::SystemException);
```

`is_related_transaction()` returns true if both transactions are descendants of the same transaction; otherwise, the method returns false.

Parameters

`tc`

Specifies the coordinator of another transaction to compare with the `Coordinator` object.

`is_related_transaction()` determines whether the transaction associated with the `Coordinator` object and the transaction associated with the coordinator specified in the `tc` parameter have a common ancestor. See `create_subtransaction()` for more information.

See Also `CosTransactions::Coordinator::is_descendant_transaction()`

```
CosTransactions::Coordinator::is_ancestor_transaction()
CosTransactions::Coordinator::is_same_transaction()
CosTransactions::Coordinator::is_top_level_transaction()
CosTransactions::Coordinator::create_subtransaction()
```

`Coordinator::is_same_transaction()`

// C++

```
CORBA::Boolean is_same_transaction(
    Coordinator_ptr tc
)
    throw(CORBA::SystemException);
```

`is_same_transaction()` returns true if the transactions associated with the two `Coordinator` objects are the same transaction; otherwise, the method returns false.

Parameters

`tc`

Specifies the coordinator of another transaction to compare with the `Coordinator` object.

`is_same_transaction()` determines whether the transaction associated with the `Coordinator` object and the transaction associated with the coordinator specified in the `tc` parameter are the same transaction.

See Also `CosTransactions::Coordinator::is_descendant_transaction()`

```

CosTransactions::Coordinator::is_related_transaction()
CosTransactions::Coordinator::is_ancestor_transaction()
CosTransactions::Coordinator::is_top_level_transaction()

```

Coordinator::is_top_level_transaction()

// C++

```

CORBA::Boolean is_top_level_transaction()
    throw(CORBA::SystemException);

```

`is_top_level_transaction()` returns true if the transaction is a top-level transaction; otherwise, the method returns false. `is_top_level_transaction()` determines whether the transaction associated with a `Coordinator` object is a top-level transaction. See `create_subtransaction()` for more information.

See Also `CosTransactions::Coordinator::is_descendant_transaction()`

```

CosTransactions::Coordinator::is_related_transaction()
CosTransactions::Coordinator::is_same_transaction()
CosTransactions::Coordinator::is_ancestor_transaction()
CosTransactions::Coordinator::create_subtransaction()

```

Coordinator::register_resource()

// C++

```

RecoveryCoordinator register_resource(
    Resource resource
)
    throw(CORBA::SystemException, Inactive);

```

`register_resource()` registers a specified resource as a participant in the transaction associated with a `Coordinator` object. When the transaction ends, the registered resource must commit or roll back changes made as part of the transaction. Only server applications can register resources. See `Resource` class for more information. `register_resource()` returns a `RecoveryCoordinator` object that the registered `Resource` object can use during recovery.

Parameters

resource

The resource to register as a participant.

Exceptions

CORBA::TRANSACTION_ROLLEDBACK

The transaction is marked for rollback only.

See Also CosTransactions::RecoveryCoordinator

CosTransactions::Resource

Coordinator::register_subtran_aware()

// C++

```
void register_subtran_aware(
    SubtransactionAwareResource resource
)
    throw(CORBA::SystemException, NotSubtransaction, Inactive);
```

`register_subtran_aware()` registers a specified resource with the subtransaction associated with a `Coordinator` object. The resource is registered with the subtransaction only, not as a participant in the top-level transaction. (`register_resource()` can be used to register the resource as a participant in the top-level transaction.) Only server applications can register resources.

Parameters

resource

The resource to register.

When the transaction ends, the registered resource must commit or roll back changes made as part of the subtransaction. See the reference page for the `SubtransactionAwareResource` class for more information.

Exceptions

NotSubtransaction	The transaction associated with the Coordinator object is not a subtransaction
Inactive	The subtransaction or any ancestor of the subtransaction has ended.
CORBA::TRANSACTION_ROLLEDBACK	The transaction is marked for rollback only.

See AlsoCosTransactions::RecoveryCoordinator

CosTransactions::SubtransactionAwareResource

Coordinator::register_synchronization()

// C++

```
void register_synchronization(
    Synchronization sync
);
    throw(CORBA::SystemException, Inactive);
```

register_synchronization() registers a specified synchronization object for the transaction associated with a Coordinator object. See the reference page for the Synchronization class for more information.

Parameters

sync

The synchronization object to register.

Exceptions

Inactive	The transaction is already prepared.
CORBA::TRANSACTION_ROLLEDBACK	The transaction is marked for rollback only.

See AlsoCosTransactions::RecoveryCoordinator

CosTransactions::Synchronization

Coordinator::rollback_only()

// C++

```
void rollback_only()  
    throw(CORBA::SystemException, Inactive);
```

`rollback_only()` marks the transaction associated with the `Coordinator` object so that the only possible outcome for the transaction is to roll back. The transaction is not rolled back until the participant that created the transaction either commits or aborts the transaction.

OTS allows `Terminator::rollback()` to be called instead of `rollback_only()`. Calling `Terminator::rollback()` rolls back the transaction immediately, preventing unnecessary work from being done between the time the transaction is marked for rollback and the time the transaction is actually rolled back.

Exceptions

Inactive

The transaction is already prepared.

See Also `CosTransactions::Terminator::rollback()`

CosTransactions::RecoveryCoordinator Class

The `RecoveryCoordinator` class enables a recoverable object to control the recovery process for an associated resource. A `RecoveryCoordinator` object can be obtained for a recoverable object via the Coordinator object associated with the recoverable object. `Coordinator::register_resource()` returns a `RecoveryCoordinator` object.

// C++

```
class RecoveryCoordinator {
    public:
        Status [replay_completion](#costransactionsrecoverycoordinator-class)
        (Resource_ptr);
};
typedef RecoveryCoordinator *RecoveryCoordinator_ptr;
class RecoveryCoordinator_var;
```

See Also `CosTransactions::Resource`

`RecoveryCoordinator::replay_completion()`

// C++

```
Status replay_completion(
    Resource_ptr resource
)
    throw(CORBA::SystemException, NotPrepared);
```

`replay_completion()` notifies the recovery coordinator that the `commit()` or `rollback()` operations have not been performed for the associated resource. Notifying the coordinator that the resource has not completed causes completion to be retried, which is useful in certain failure cases. The method returns the current status of the transaction.

Parameters

`resource`

The resource associated with the recovery coordinator.

Exceptions

NotPrepared

The resource is not in the prepared state.

See Also CosTransactions::Resource

CosTransactions::Status

CosTransactions::Resource Class

The `Resource` class represents a recoverable resource, that is, a transaction participant that manages data subject to change within a transaction. The `Resource` class specifies the protocol that must be defined for a recoverable resource. Interfaces that inherit from this class must implement each of the member methods to manage the data appropriately for the recoverable object based on the outcome of the transaction. These methods are invoked by the Transaction Service to execute two-phase commit; the requirements of these methods are described in the following sections.

To become a participant in a transaction, a `Resource` object must be registered with that transaction. `Coordinator::register_resource()` can be used to register a resource for the transaction associated with the `Coordinator` object.

The full name for the class is `CosTransactions :: Resource`.

// C++

```
class Resource {
    public:
        virtual Vote prepare();
        virtual void rollback();
        virtual void commit();
        virtual void commit_one_phase();
        virtual void forget();
};
typedef Resource *Resource_ptr;
class Resource_var;
```

See Also `CosTransactions::Synchronization`

```
CosTransactions::RecoveryCoordinator  
CosTransactions::Vote
```

Two-phase Commit

The two-phase commit requires methods `prepare()` and `commit()`.

`prepare()` must be defined to vote on the outcome of the transaction with which the resource is registered. The transaction service invokes this method as the first phase of a two-phase commit; the return value controls the second phase:

- Returns `VoteReadOnly` if the resource's data is not modified by the transaction. The transaction service does not invoke any other methods on the resource, and the resource can forget all knowledge of the transaction.
- Returns `VoteCommit` if the resource's data is written to stable storage by the transaction and the transaction is prepared. Based on the outcome of other participants in the transaction, the transaction service calls either `commit()` or `rollback()` for the resource. The resource should store a reference to the `RecoveryCoordinator` object in stable storage to support recovery of the resource.
- Returns `VoteRollback` for all other situations. The transaction service calls `rollback()` for the resource, and the resource can forget all knowledge of the transaction.

`commit()` must be defined to commit all changes made to the resource as part of the transaction. If `forget()` has already been called, no changes need to be committed. If the resource has not been prepared, the `NotPrepared` exception must be thrown.

Use the heuristic outcome exceptions to report heuristic decisions related to the resource. The resource must remember heuristic outcomes until `forget()` is called, so that the same outcome can be returned if the transaction service calls `commit()` again.

One-phase Commit

`commit_one_phase()` must be defined to commit all changes made to the resource as part of the transaction. The transaction service may invoke this method if the resource is the only participant in the transaction. Unlike `commit()`, `commit_one_phase()` does not require that the resource be prepared first. Use the heuristic outcome exceptions to report heuristic decisions related to the resource. The resource must remember heuristic outcomes until `forget()` is called, so that the same outcome can be returned if the transaction service calls `commit_one_phase()` again.

Rollback Transaction

`rollback()` must be defined to undo all changes made to the resource as part of the transaction. If `forget()` has been called, no changes need to be undone. Use the heuristic outcome exceptions to report heuristic decisions related to the resource. The resource must remember heuristic outcomes until `forget()` is called, so that the same outcome can be returned if the transaction service calls `rollback()` again.

Forget Transaction

`forget()` must be defined to cause the resource to forget all knowledge of the transaction. The transaction service invokes this method if the resource throws a heuristic outcome exception in response to `commit()` or `rollback()`.

CosTransactions::SubtransactionAwareResource Class

Note

This class is not supported in this release of OTS for Orbix. The information in this section therefore does not apply to this release.

The `SubtransactionAwareResource` class represents a recoverable resource that makes use of nested transactions. This specialized resource object allows the resource to be notified when a subtransaction for which it is registered either commits or rolls back.

The `SubtransactionAwareResource` class specifies the protocol that must be defined for this type of recoverable resource. Interfaces that inherit from this class must implement each of the member methods to manage the recoverable object's data appropriately based on the outcome of the subtransaction. These methods are invoked by the transaction service; the requirements of these methods are described below.

`Coordinator::register_subtran_aware()` can be used to register a resource with the subtransaction associated with the Coordinator object. The resource can also register with the top-level transaction by using `Coordinator::register_resource()` as well. In this case, the protocol for the Resource class must be defined in addition to the protocol for `SubtransactionAwareResource`. See the reference page for the Resource class for more information.

// C++

```
class SubtransactionAwareResource : Resource {
public:
    virtual void commit_subtransaction(Coordinator);
    virtual void rollback_subtransaction();
};
typedef SubtransactionAwareResource *SubtransactionAwareResource_ptr;
class SubtransactionAwareResource_var;
```

See Also `CosTransactions::Coordinator`

```
CosTransactions::Resource  
CosTransactions::Status
```

Commit Subtransaction

`commit_subtransaction()` must be defined to commit all changes made to the resource as part of the subtransaction. If an ancestor transaction rolls back, the subtransaction's changes are rolled back. The transaction service invokes this method if the resource is registered with a subtransaction and it is committed.

The method must be defined to take a `Coordinatorobject` as its only argument. When the transaction service invokes this method, it passes the `Coordinator` object associated with the parent transaction.

Rollback Subtransaction

`rollback_subtransaction()` must be defined to undo all changes made to the resource as part of the subtransaction. The transaction service invokes this method if the resource is registered with a subtransaction and it is rolled back.

CosTransactions::Synchronization Class

The `Synchronization` class represents a non-recoverable object that maintains transient state data and is dependent on a recoverable object to ensure that the data is persistent. To make data persistent, a synchronization object moves its data to one or more resources before the transaction completes.

The `Synchronization` class specifies a protocol that must be defined for this type of object. A synchronization object must be implemented as a class derived from the `Synchronization` class. The derived class must implement each of the member methods to ensure that the data maintained by the nonrecoverable object is made recoverable. The transaction service invokes these methods before and after the registered resources commit; the specific requirements of these methods are described in the following sections.

`Coordinator::register_synchronization()` can be used to register a synchronization object with the transaction associated with the Coordinator object.

// C++

```
class Synchronization : TransactionalObject {
public:
    virtual void before_completion();
    virtual void after_completion(Status);
};
```

Before Completion

`before_completion()` must be defined to move the synchronization object's data to a recoverable object. The transaction service invokes this method prior to the prepare phase of the transaction. The method is invoked only if the synchronization object is registered with a transaction and the transaction attempts to commit.

The only exceptions this method can throw are `CORBA::SystemException` exceptions. Throwing other exceptions can cause the transaction to be marked for rollback only.

After Completion

`after_completion()` must be defined to do any necessary processing required by the synchronization object; for example, the method could be used to release locks held by the transaction. The transaction service invokes this method after the outcome of the transaction is complete. The method is invoked only if the synchronization object is registered with a transaction and the transaction has either committed or rolled back.

The method must be defined to take a `Status` value as its only argument. When the transaction service invokes this method, it passes the status of the transaction with which the synchronization object is registered.

The only exceptions this method can throw are `CORBA::SystemException` exceptions. Any exceptions that are thrown have no effect on the commitment of the transaction.

See Also `CosTransactions::Coordinator`

```
CosTransactions::Coordinator::register_synchronization()  
CosTransactions::Resource  
CosTransactions::Status
```

CosTransactions::Terminator Class

The `Terminator` class enables explicit termination of a factory-created transaction. The transaction with which the `Terminator` object is associated can be either committed or rolled back.

`Control::get_terminator()` can be used to return the `Terminator` object associated with a transaction.

// C++

```
class Terminator {
public:
    void [commit](#costransactionsterminator-class)(CORBA::Boolean);
    void [rollback()](#costransactionsterminator-class);
};
typedef Terminator *Terminator_ptr;
class Terminator_var;
```

See Also `CosTransactions::Coordinator`

```
CosTransactions::Control::get_terminator()
CosTransactions::Control
CosTransactions::Status
```

`Terminator::commit()`

// C++

```
void commit(
    CORBA::Boolean report_heuristics
)
    throw(CORBA::SystemException,
        HeuristicHazard,
        TRANSACTION_ROLLEDBACK);
```

`commit()` attempts to commit the transaction associated with the `Terminator` object. If the `report_heuristics` parameter is true, the `HeuristicHazard` exception is thrown when the participants report that a heuristic decision has possibly been made.

Parameters

```
report_heuristics
```

Specifies whether to report heuristic decisions for the commit.

Exceptions

```
CORBA::TRANSACTION_ROLLEDBACK
```

The transaction has been marked as rollback-only, or all participants in the transaction do not agree to commit.

See Also CosTransactions::Coordinator

```
CosTransactions::Terminator
CosTransactions::Terminator::rollback()
CosTransactions::Control
```

Terminator::rollback()

// C++

```
void rollback();
```

`rollback()` rolls back the transaction associated with the `Terminator` object.

See Also CosTransactions::Coordinator

```
CosTransactions::Terminator
CosTransactions::Terminator::commit()
```

CosTransactions::TransactionalObject Class

The TransactionalObject interface has been deprecated and replaced with transactional policies (see [OTSPolicyValue Data Type](#)). Backward compatibility with existing OTS implementations is provided for outbound requests only and only if the target object does not have a transactional policy in its IOR.

See the *CORBA Programmer's Guide* for details of interoperability with existing OTS implementations.

// C++

```
class TransactionalObject {};  
typedef TransactionalObject *TransactionalObject_ptr;  
class TransactionalObject_var;
```

CosTransactions::TransactionFactory Class

The `TransactionFactory` class represents a transaction factory that allows the originator of transactions to begin a new transaction for use with the explicit model of transaction demarcation. Servers provide a default instance of this class. Clients can bind to the default instance by using the standard binding mechanism for the object request broker.

// C++

```
class TransactionFactory {
public:
    Control_ptr [create](#dseventlogadmineventlogfactory-interface)
(unsigned long timeout);
    Control_ptr [recreate](#costransactiontransactionfactory-class)
(const PropagationContext& ctx);
};
typedef TransactionFactory *TransactionFactory_ptr;
class TransactionFactory_var;
```

See Also `CosTransactions::Control`

`TransactionFactory::create()`

// C++

```
Control_ptr create(unsigned long timeout)
    throw(CORBA::SystemException);
```

`create()` creates a new top-level transaction for use with the explicit model of transaction demarcation. A Control object is returned for the transaction. The Control object can be used to propagate the transaction context. See the reference page for the Control class for more information.

Parameters

timeout

Specifies the number of seconds that the transaction waits to complete before rolling back. If the `timeout` parameter is zero, no timeout is set for the transaction.

See Also CosTransactions::TransactionFactory

CosTransactions::Control

TransactionFactory::recreate()

// C++

```
Control_ptr TransactionFactory::recreate(  
    const PropagationContext& ctx);
```

Creates a new representation for an existing transaction defined in the propagation context `ctx`. This is used to import a transaction from another domain. The method returns a control object for the new transaction representation.

See Also CosTransactions::Coordinator::get_txcontext()

CosTypedEventChannelAdmin Module

The `CosTypedEventChannelAdmin` module defines the interfaces for making connections between suppliers and consumers that use either generic or typed communication. Its interfaces are specializations of the corresponding interfaces in the `CosEventChannel` module.

Note

Orbix's implementation of typed events only supports the typed push style of event communication. The `TypedProxyPullSupplier` interface, the `TypedSupplierAdmin::obtain_typed_pull_consumer()` operation, and the `TypedConsumerAdmin::obtain_typed_pull_supplier()` operation are **not** implemented.

CosTypedEventChannelAdmin Exceptions

`CosTypedEventChannelAdmin::InterfaceNotSupported`

exception `InterfaceNotSupported {};`

`InterfaceNotSupported` is raised when an attempt to obtain a `TypedProxyPushConsumer` fails to find an implementation that supports the strongly typed interface required by the client.

`CosTypedEventChannelAdmin::NoSuchImplementation`

exception `NoSuchImplementation {};`

`NoSuchImplementation` is raised when an attempt to obtain a `ProxyPushSupplier` fails to find an implementation that supports the strongly typed interface required by the client.

CosTypedEventChannelAdmin Data Types

`CosTypedEventChannelAdmin::Key` Type

typedef string `Key;`

A string that holds the interface repository ID of the strongly typed interface used by a typed event client.

CosTypedEventChannelAdmin::TypedConsumerAdmin Interface

```
interface TypedConsumerAdmin : CosEventChannelAdmin::ConsumerAdmin
{
    TypedProxyPullSupplier obtain_typed_pull_supplier(
        in Key supported_interface)
    raises (InterfaceNotSupported);
    CosEventChannelAdmin::ProxyPushSupplier
        obtain_typed_push_supplier(in Key uses_interface)
    raises (NoSuchImplementation);
};
```

The `TypedConsumerAdmin` interface extends the functionality of the generic `ConsumerAdmin` to support connecting consumer to a typed event channel.

`TypedConsumerAdmin::obtain_typed_pull_supplier()`

```
TypedProxyPullSupplier obtain_typed_pull_supplier(
    in Key supported_interface)
raises (InterfaceNotSupported);
```

The `obtain_typed_pull_supplier()` operation returns a `TypedProxyPullSupplier` that supports the interface `Pull<supported_interface>`.

Parameters

`supported_interface`

Specifies the interface which the returned `TypedProxyPullSupplier` must support.

Exceptions

`InterfaceNotSupported`

Raised if `TypedProxyPullSupplier` implementation supporting the specified interface is available.

TypedConsumerAdmin::obtain_typed_push_supplier()

```
CosEventChannelAdmin::ProxyPushSupplier  
  obtain_typed_push_supplier(in Key uses_interface)  
  raises (NoSuchImplementation);
```

The `obtain_typed_push_supplier()` operation returns a `ProxyPushSupplier` that makes calls on interface `uses_interface`.

Parameters

`uses_interface`

Specifies the interface on which the returned `ProxyPushSupplier` must make calls.

Exceptions

`NoSuchImplementation`

Raised if no `ProxyPushConsumer` can be found that supports the specified interface.

Unsupported Operations

The Application Server Platform does not support the typed pull model or the connection of generic consumers to a typed event channel. Therefore, a `TypedConsumerAdmin` object will throw `NO_IMPLEMENT` for the following operations:

- `obtain_typed_pull_supplier()`
- `obtain_push_supplier()`
- `obtain_pull_supplier()`

CosTypedEventChannelAdmin::TypedEventChannel Interface

```
interface TypedEventChannel
{
    TypedConsumerAdmin for_consumers();
    TypedSupplierAdmin for_suppliers();
    void destroy();
};
```

This interface is the equivalent of `CosEventChannelAdmin::EventChannel` for typed events. It provides a factory for `TypedConsumerAdmin` objects and `TypedSupplierAdmin` objects. Both of which are capable of providing proxies for typed communication.

CosTypedEventChannelAdmin::TypedProxyPushConsumer Interface

```
interface TypedProxyPushConsumer :
  CosEventChannelAdmin::ProxyPushConsumer,
  CosTypedEventComm::TypedPushConsumer
{
};
```

The `TypedProxyPushConsumer` interface extends the functionality of the `ProxyPushConsumer` to support connecting push suppliers to a typed event channel.

By inheriting from `CosEventChannelAdmin::ProxyPushConsumer`, this interface supports:

- connection and disconnection of push suppliers.
- generic push operation.

By inheriting from `CosTypedEventComm::TypedPushConsumer`, it extends the functionality of the generic `ProxyPushConsumer` to enable its associated supplier to use typed push communication. When a reference to a `TypedProxyPushConsumer` is returned by `get_typed_consumer()`, it has the interface identified by the `Key`.

Unsupported Operations

The `TypedProxyPushConsumer` reference will throw `NO_IMPLEMENT` for the `push()` operation. A supplier should instead call `push()` on the reference it obtains from the `get_typed_consumer()` operation.

CosTypedEventChannelAdmin::TypedSupplierAdmin Interface

```
interface TypedSupplierAdmin : CosEventChannelAdmin::SupplierAdmin
{
    TypedProxyPushConsumer obtain_typed_push_consumer(
        in Key supported_interface)
        raises (InterfaceNotSupported);
    CosEventChannelAdmin::ProxyPullConsumer obtain_typed_pull_consumer(in Key
uses_interface)
        raises (NoSuchImplementation);
};
```

The `TypedSupplierAdmin` interface extends the functionality of the generic `SupplierAdmin` to support connecting suppliers to a typed event channel.

`TypedSupplierAdmin::obtain_typed_push_consumer()`

```
TypedProxyPushConsumer obtain_typed_push_consumer(
    in Key supported_interface)
    raises (InterfaceNotSupported);
```

The `obtain_typed_push_consumer()` operation returns a `TypedProxyPushConsumer` that supports the specified interface.

Parameters

`supported_interface`

Specifies the interface that the returned `TypedProxyPushConsumer` must support.

Exceptions

`InterfaceNotSupported`

Raised if no consumer implementation supporting the specified interface is available.

TypedSupplierAdmin::obtain_typed_pull_consumer()

```
CosEventChannelAdmin::ProxyPullConsumer  
  obtain_typed_pull_consumer(in Key uses_interface)  
  raises (NoSuchImplementation);
```

The `obtain_typed_pull_consumer()` operation returns a `ProxyPullConsumer` that calls operations in the interface `Pull<uses_interface>`.

Parameters

`uses_interface`

Specifies the interface which the returned `ProxyPullConsumer` must support.

Exceptions

`NoSuchImplementation`

Raised if no `ProxyPullConsumer` can be found that supports the specified interface.

Unsupported Operations

The Application Server Platform does not support the typed pull model or the connection of generic suppliers to a typed event channel. Therefore, the `TypedSupplierAdmin` reference will throw `NO_IMPLEMENT` for the following operations:

- `obtain_typed_pull_consumer()`
- `obtain_push_consumer()`
- `obtain_pull_consumer()`

CosTypedEventComm Module

This module specifies two interfaces used to support typed event communication. `TypedPushConsumer` supports push style typed event communication. Typed event clients retain the capability to use generic event communication.

Note

Orbix's implementation of typed events only supports typed push style events. The `TypedPullSupplier` interface is **not** implemented.

CosTypedEventComm::TypedPushConsumer Interface

```
interface TypedPushConsumer : CosEventComm::PushConsumer
{
    Object get_typed_consumer();
};
```

The `TypedPushConsumer` interface is used to implement push-style consumers that wish to participate in typed event communication. By inheriting from the generic `PushConsumer` interface, this interface retains the ability to participate in generic push-style event communication. This inheritance also requires that `TypedPushConsumer` objects implement the generic `push()` operation. However, if the consumer will be used solely for typed event communication, the `push()` implementation can simply raise the standard CORBA exception `NO_IMPLEMENT`.

`TypedPushConsumer::get_typed_consumer()`

`Object get_typed_consumer();`

`get_typed_consumer()` returns a reference to a typed push consumer. This reference is returned as a reference to type `Object` and must be narrowed to the appropriate interface. If the push supplier and the typed push consumer do not support the same interface, the `narrow()` will fail.

CSI Overview

The CSI module defines the basic data types needed for the OMG Common Secure Interoperability (CSIV2) specification. This reference page is a partial extract from the CSI module that includes only the data types needed for the `IT_CSI` module.

CSI::OID Sequence

```
typedef sequence <octet> OID;
    // ASN.1 Encoding of an OBJECT IDENTIFIER
```

The type that represents an ASN.1 object identifier in binary format.

CSI::OIDList Sequence

```
typedef sequence <OID> OIDList;
```

The type that represents a list of ASN.1 object identifiers.

CSI::GSS_NT_ExportedName

```
typedef sequence <octet> GSS_NT_ExportedName;
```

An encoding of a GSS Mechanism-Independent Exported Name Object as defined in [IETF RFC 2743] Section 3.2, "GSS Mechanism-Independent Exported Name Object Format," p. 84. See <http://www.ietf.org/rfc/rfc2743.txt>.

See Also `IT_CSI::AuthenticationServicePolicy::target_name`

CSI::IdentityTokenType

```
typedef unsigned long IdentityTokenType;
```

The type of a CSIV2 identity token.

See Also `CSI::IdentityToken`

CSI::ITTAbsent


```
const IdentityTokenType ITTAbsent = 0;
```

The identity token is absent. This indicates that the invocation is not being made on behalf of another principal.

See AlsoCSI::IdentityToken

CSI::ITTAnonymous

```
const IdentityTokenType ITTAnonymous = 1;
```

Indicates that the invocation is being made on behalf of an unidentified and unauthenticated principal.

See AlsoCSI::IdentityToken

CSI::ITTPrincipalName

```
const IdentityTokenType ITTPrincipalName = 2;
```

Indicates that the invocation is being made on behalf of an identifiable and authenticated principal.

See AlsoCSI::IdentityToken

CSI::ITTX509CertChain

```
const IdentityTokenType ITTX509CertChain = 4;
```

Not used in the current implementation of CSIV2.

See AlsoCSI::IdentityToken

CSI::ITTDistinguishedName

```
const IdentityTokenType ITTDistinguishedName = 8;
```

Not used in the current implementation of CSIV2.

See AlsoCSI::IdentityToken

CSI::IdentityExtension

```
typedef sequence <octet> IdentityExtension;
```

A data type that enables the range of identity tokens to be extended. The OMG reserves this type for future extensions.

See Also CSI::IdentityToken

CSI::IdentityToken Union

```
union IdentityToken switch ( IdentityTokenType ) {
    case ITTAbsent: boolean absent;
    case ITTAnonymous: boolean anonymous;
    case ITTPrincipalName: GSS_NT_ExportedName principal_name;
    case ITTX509CertChain: X509CertificateChain certificate_chain;
    case ITTDistinguishedName: X501DistinguishedName dn;
    default: IdentityExtension id;
};
```

The type that is used to represent an identity token. Only the following identity token types are currently used by Orbix:

- ITTAbsent
- ITTAnonymous
- ITTPrincipalName

CSI::StringOID

```
typedef string StringOID;
```

This type is the string representation of an ASN.1 OBJECT IDENTIFIER (OID). OIDs are represented by the string `oid:` followed by the integer base-10 representation of the OID separated by dots. For example, the OID corresponding to the OMG is represented as: `"oid:2.23.130"`

CSI::GSS_NT_Export_Name_OID

```
const StringOID GSS_NT_Export_Name_OID = "oid:1.3.6.1.5.6.4";
```

The GSS Object Identifier for name objects of the Mechanism-Independent Exported Name Object type is:

```
{ iso(1) org(3) dod(6) internet(1) security(5) nametypes(6) gss-api-  
exported-name(4) }
```

CSIIOP Overview

The CSI inter-ORB protocol (CSIIOP) IDL module defines the data types that are used for encoding the CSIV2 service contexts and IOR components . This reference page is a partial extract from the CSIIOP module that includes only the data types needed for the `IT_CSI` module.

CSIIOP::AssociationOptions

```
typedef unsigned short AssociationOptions;
```

The type used to define association option flags.

CSIIOP::NoProtection

```
const AssociationOptions NoProtection = 1;
```

Not needed in the current implementation of CSIV2.

CSIIOP::Integrity

```
const AssociationOptions Integrity = 2;
```

Not needed in the current implementation of CSIV2.

CSIIOP::Confidentiality

```
const AssociationOptions Confidentiality = 4;
```

Not needed in the current implementation of CSIV2.

CSIIOP::DetectReplay

```
const AssociationOptions DetectReplay = 8;
```

Not needed in the current implementation of CSIV2.

CSIIOP::DetectMisordering

```
const AssociationOptions DetectMisordering = 16;
```

Not needed in the current implementation of CSIV2.

CSIIOP::EstablishTrustInTarget

```
const AssociationOptions EstablishTrustInTarget = 32;
```

Not needed in the current implementation of CSIV2.

CSIIOP::EstablishTrustInClient

```
const AssociationOptions EstablishTrustInClient = 64;
```

The `EstablishTrustInClient` association option can be specified in the `support` attribute or in the `target_requires` attribute of the `IT_CSI::AuthenticationServicePolicy` policy. This policy enables you to specify that a client or server can require and support client authentication over the transport using CSIV2.

See Also `IT_CSI::AuthenticationService`

```
IT_CSI::AuthenticationServicePolicy
```

CSIIOP::NoDelegation

```
const AssociationOptions NoDelegation = 128;
```

Not supported in the current implementation of CSIV2.

CSIIOP::SimpleDelegation

```
const AssociationOptions SimpleDelegation = 256;
```

Not supported in the current implementation of CSIV2.

CSIIOP::CompositeDelegation

```
const AssociationOptions CompositeDelegation = 512;
```

Not supported in the current implementation of CSIV2.

CSIIOP::IdentityAssertion

```
const AssociationOptions IdentityAssertion = 1024;
```

The `IdentityAssertion` association option can be specified in the `support` attribute of the `IT_CSI::AttributeServicePolicy` policy. This policy enables you to specify that a client or server supports identity assertion (principal propagation) using CSIV2.

See Also `IT_CSI::AttributeService`

```
IT_CSI::AttributeServicePolicy
```

CSIIOP::DelegationByClient

```
const AssociationOptions DelegationByClient = 2048;
```

Not supported in the current implementation of CSIV2.

CSIIOP::ServiceConfigurationSyntax Type

```
typedef unsigned long ServiceConfigurationSyntax;
```

The type used to identify a syntax for specifying privilege authority names.

The high order 20-bits of each `ServiceConfigurationSyntax` constant shall contain the Vendor Minor Codeset ID (VMCID) of the organization that defined the syntax. The low order 12 bits shall contain the organization-scoped syntax identifier. The high-order 20 bits of all syntaxes defined by the OMG shall contain the VMCID allocated to the OMG (that is, `0x4F4D0`).

See Also `CSIIOP::ServiceConfiguration`

CSIIOP::SCS_GeneralNames

```
const ServiceConfigurationSyntax SCS_GeneralNames = CSI::OMGVMCID | 0;
```

Identifies the `GeneralNames` syntax (as defined in [IETF RFC 2459]) for specifying privilege authority names.

CSIIOP::SCS_GSSExportedName

```
const ServiceConfigurationSyntax SCS_GSSExportedName = CSI::OMGVMCID | 1;
```

Identifies the GSS exported name syntax (as defined in [IETF RFC 2743] Section 3.2) for specifying privilege authority names.

CSIIOP::ServiceSpecificName

```
typedef sequence <octet> ServiceSpecificName;
```

A type that contains a privilege authority name, encoded using either the `CSIIOP::SCS_GeneralNames` or the `CSIIOP::SCS_GSSExportedName` syntax.

See Also CSIIOP::ServiceConfiguration

CSIIOP::ServiceConfiguration Structure

```
struct ServiceConfiguration {
    ServiceConfigurationSyntax syntax;
    ServiceSpecificName name;
};
```

Not used in the current implementation of CSIV2.

CSIIOP::ServiceConfigurationList Sequence

```
typedef sequence <ServiceConfiguration> ServiceConfigurationList;
```

A list of `ServiceConfiguration` structures.

Not used in the current implementation of CSIV2.

DsEventLogAdmin Module

The `DsEventLogAdmin` module defines the `EventLog` interface which provides logging capabilities for event service clients. This module also defines the `EventLogFactory` interface which is used to instantiate `EventLog` objects.

DsEventLogAdmin::EventLogFactory Interface

The `EventLogFactory` interface defines two operations for instatiating `EventLog` objects.

`EventLogFactory::create()`

`EventLog` `create`(in `LogFullActionType` `full_action`,

```
    in unsigned long long max_size,
    in DsLogAdmin::CapacityAlarmThresholdList thresholds,
    out LogId id);
raises (InvalidLogFullAction
        InvalidThreshold);
```

Returns an instantiated `EventLog` object. The `LogId` returned is assigned by the service and can be used to access the returned `EventLog` object.

Parameters

<code>full_action</code>	Specifies what the log object will do when it fills up.
<code>max_size</code>	Specifies the maximum amount of data, in bytes, the log can hold.
<code>thresholds</code>	Specifies , as a percentage of max log size, the points at which an <code>ThresholdAlarm</code> event will be generated.
<code>id</code>	The <code>LogId</code> assigned to the <code>EventLog</code> object by the service.

Exceptions

<code>InvalidLogFullAction</code>	The specified <code>full_action</code> is not a valid <code>LogFullActionType</code> .
<code>InvalidThreshold</code>	One of the thresholds specified is invalid.

`EventLogFactory::create_with_id()`

`EventLog` `create_with_id`(in `LogId` `id`,

```

        in LogFullActionType full_action,
        in unsigned long long max_size)
        in DsLogAdmin::CapacityAlarmThresholdList thresholds)
raises(DsLogAdmin::LogIdAlreadyExists,
       DsLogAdmin::InvalidLogFullAction,
       DsLogAdmin::InvalidThreshold);

```

Returns an instantiated [EventLog](#) object with a user supplied id.

Parameters

<code>id</code>	Specifies the <code>LogId</code> to assign the <code>EventLog</code> .
<code>full_action</code>	Specifies what the log object will do when it fills up.
<code>max_size</code>	Specifies the maximum amount of data, in bytes, the log can hold.
<code>thresholds</code>	Specifies , as a percentage of max log size, the points at which an <code>ThresholdAlarm</code> event will be generated.

Exceptions

<code>LogIdAlreadyExists</code>	A log with the specified id already exists.
<code>InvalidLogFullAction</code>	The specified <code>full_action</code> is not a valid <code>LogFullActionType</code> .
<code>InvalidThreshold</code>	One of the thresholds specified is invalid.

DsLogAdmin Module

`DsLogAdmin` specifies the `Log` interfaces which forms the basis for the `BasicLog` interface, `EventLog` interface, and the `NotifyLog` interface. `DsLogAdmin` also specifies the `BasicLog` and `BasicLogFactory` to support the basic logging service. In addition, this module specifies the `Iterator` interface to support the iterators returned when retrieving records from a log.

This module also specifies all of the exceptions and major datatypes used by the telecom logging service.

DsLogAdmin Exceptions

`DsLogAdmin::InvalidParam` Exception

```
exception InvalidParam {string details};
```

Raised when an illegal value is used to set a log's properties. It contains the name of the property being set and the illegal value.

`DsLogAdmin::InvalidThreshold` Exception

```
exception InvalidThreshold {};
```

Raised when an attempt is made to set a threshold alarm at a value outside the range of 0%-99%.

`DsLogAdmin::InvalidTime` Exception

```
exception InvalidTime{};
```

Raised by `set_week_mask()` when one of the values specified for a start or stop time is not within the valid range.

`DsLogAdmin::InvalidTimeInterval` Exception

```
exception InvalidTimeInterval{};
```

Raised by `set_week_mask()` when one of the time intervals used to set a log's schedule is improperly formed. For example, the stop time is before the start. Also raised if the intervals overlap.

`DsLogAdmin::InvalidMask` Exception

```
exception InvalidMask{};
```

Raised by `set_week_mask()` when the days parameter used in setting a log's schedule is malformed.

DsLogAdmin::LogIdAlreadyExists Exception

```
exception LogIdAlreadyExists{};
```

Raised by `create_with_id()` if an attempt is made to create a log with an id that is already in use.

DsLogAdmin::InvalidGrammar Exception

```
exception InvalidGrammar{};
```

Raised by `query()` and `delete_records()` if an unsupported constraint grammar is specified. The grammar implemented in Orbix's telecom logging service is `EXTENDED_TCL`.

DsLogAdmin::InvalidConstraint Exception

```
exception InvalidConstraint{};
```

Raised by `query()` and `delete_records()` if a constraint expression is not syntactically correct according to the specified grammar.

DsLogAdmin::LogFull Exception

```
exception LogFull{short n_records_written;;};
```

Raised when an attempt is made to log records in a log that is full and has its `full_action` set to `halt`. It returns the number of records that were successfully written to the log.

DsLogAdmin::LogOffDuty Exception

```
exception LogOffDuty{};
```

Raised when an attempt is made to log records in a log whose availability status is off duty.

DsLogAdmin::LogLocked Exception

```
exception LogLocked{};
```

Raised when an attempt is made to log records in a log whose administrative state is `locked`.

DsLogAdmin::LogDisabled Exception

```
exception LogDisabled{};
```

Raised when an attempt is made to log records in a log whose operational state is `disabled`.

DsLogAdmin::InvalidRecordId Exception

```
exception InvalidRecordId{};
```

Raised when the record id specified does not exist in the log.

DsLogAdmin::InvalidAttribute Exception

```
exception InvalidAttribute{string attr_name; any value;;}
```

Raised when one of the attributes set on a record is invalid. It returns the name of the invalid attribute and the value specified for it.

DsLogAdmin::InvalidLogFullAction Exception

```
exception InvalidLogFullAction{};
```

Raised if an attempt is made to set a log's `full_action` to a value other than `wrap` or `halt`.

DsLogAdmin::UnsupportedQoS Exception

```
exception UnsupportedQoS{QoSList denied};
```

DsLogAdmin Constants

`DsLogAdmin` defines the majority of the constant values used when developing a telecom logging service application.

Querying Constants

`DsLogAdmin` defines one constant to support queries:

```
const string default_grammar = "EXTENDED_TCL";
```

Full Action Constants

Two constants are defined to support a log's `full_action`:

```
const LogFullActionType wrap = 0;
const LogFullActionType halt = 1;
```

Scheduling Constants

DsLogAdmin defines the following constants to support log scheduling:

```
const unsigned short Sunday      = 1;
const unsigned short Monday     = 2;
const unsigned short Tuesday    = 4;
const unsigned short Wednesday  = 8;
const unsigned short Thursday   = 16;
const unsigned short Friday     = 32;
const unsigned short Saturday   = 64;
```

QoS Constants

DsLogAdmin defines the following constants to support log QoS properties:

```
const [QoSType](#dslogadmin-datatypes) QoSNone = 0;
const [QoSType](#dslogadmin-datatypes) QoSFlush = 1;
const [QoSType](#dslogadmin-datatypes) QoSReliable = 2;
```

DsLogAdmin Datatypes

DsLogAdmin::LogId Type

```
typedef unsigned long LogId;
```

Specifies a log's unique id. The id is used by several methods for specifying which log to use or to locate a specific log.

DsLogAdmin::RecordId Type

```
typedef unsigned long long RecordId;
```

Specifies a record's id. A record's id is unique within the log storing it.

DsLogAdmin::RecordIdList Sequence

```
typedef sequence<RecordId> RecordIdList;
```

Specifies a list of record ids. The list does not need to be in any particular order.

DsLogAdmin::Constraint Type

```
typedef string Constraint;
```

Specifies the constraints used for querying a log's records.

DsLogAdmin::TimeT Type

```
typedef TimeBase::TimeT TimeT;
```

Used to record logging times and for setting a log's duration.

DsLogAdmin::NVPair Structure

```
struct NVPair
```

```
{
  string name;
  any    value;
};
```

Specifies a name/value pair used to construct attributes for records.

Members

name	The name of the attribute. The value can be any string.
value	An any containing the setting for the attribute.

DsLogAdmin::NVList Sequence

```
typedef sequence<NVPair> NVList;
```

A list of name/value record attributes.

DsLogAdmin::TimeInterval Structure

```
struct TimeInterval
```

```
{
    TimeT start;
    TimeT stop;
};
```

Specifies the start and stop times for a logging session.

Members

<code>start</code>	The start time for the current logging session.
<code>stop</code>	The end time for the current logging session.

DsLogAdmin::LogRecord Structure

struct LogRecord

```
{
    [RecordId](#dslogadmin-datatypes) id;
    [TimeT](#dslogadmin-datatypes) time;
    [NVList](../corbanvlist_class/corbanvlist_class.md) attr_list;
    any info;
};
```

The data stored when a new record is logged.

Members

<code>id</code>	The unique identifier for the record
<code>time</code>	The time at which the record was logged.
<code>attr_list</code>	An optional list of attributes specified by the client
<code>info</code>	The data contained in the record.

DsLogAdmin::RecordList Sequence

typedef sequence<[LogRecord](#)> RecordList;

A list of records.

DsLogAdmin::Anys Sequence

```
typedef sequence<any> Anys;
```

A sequence of data stored in individual `any` packages.

DsLogAdmin::AvailabilityStatus Structure

```
struct AvailabilityStatus
```

```
{
    boolean off_duty;
    boolean log_full;
};
```

Represents the availability of a log.

Members

<code>off_duty</code>	<code>true</code> means the log is not scheduled to accept new events. <code>false</code> means it is scheduled to receive new events.
<code>log_full</code>	If the log is full this member will be <code>true</code> .

DsLogAdmin::LogFullActionType Type

```
typedef unsigned short LogFullActionType;
```

Specifies a log's `full_action`. It can either be `halt` or `wrap`.

DsLogAdmin::Time24 Structure

```
struct Time24
```

```
{
    unsigned short hour;    // 0-23
    unsigned short minute; // 0-59
};
```

Specifies the fine grained times for a log's schedule

Members

<code>hour</code>	An hour specified in 24 hour format
<code>minute</code>	The minute within an hour. Can be a value from 0-59.

DsLogAdmin::Time24Interval Structure

struct Time24Interval

```
{
    [Time24](#dslogadmin-datatypes) start;
    [Time24](#dslogadmin-datatypes) stop;
};
```

A fine grained interval during which a log is scheduled to log new records.

Members

<code>start</code>	The time at which a log will begin logging new records.
<code>stop</code>	The time at which a log will stop logging new records.

DsLogAdmin::IntervalsOfDay Sequence

typedef sequence<[Time24Interval](#)> IntervalsOfDay;

A list of fine grained logging intervals.

DsLogAdmin::DaysOfWeek Type

typedef unsigned short DaysOfWeek;

A bit mask specifying the days of the week a fine grained logging interval is valid. It is constructed using the scheduling constants listed in [Scheduling Constants](#).

DsLogAdmin::WeekMaskItem Structure

struct WeekMaskItem

```
{
    [DaysOfWeek] (#dslogadmin-datatypes)    days;
    [IntervalsOfDay] (#dslogadmin-datatypes) intervals;
};
```

Specifies a fined grain log schedule.

Members

<code>days</code>	A bitmask specifying the days of the week for which the specified intervals are valid.
<code>intervals</code>	The fine grained logging intervals.

DsLogAdmin::WeekMask Sequence

```
typedef sequence<WeekMaskItem> WeekMask;
```

Specifies a log's fine grained logging schedule.

DsLogAdmin::Threshold Type

```
typedef unsigned short Threshold;
```

Specifies a threshold point, in terms of a percentage of how full a log is, at which to generate an alarm. Valid values are from 0 - 100 .

DsLogAdmin::CapacityAlarmThresholdList Sequence

```
typedef sequence<Threshold> CapacityAlarmThresholdList;
```

A list of thresholds at which alarms are generated.

DsLogAdmin::OperationalState Enum

```
enum OperationalState {disabled, enabled};
```

Specifies if a log is ready to log new records.

Table 11: Log operational states

Operational State	Reason
<code>enabled</code>	The log is healthy and its full functionality is available for use.

Operational State	Reason
<code>disabled</code>	The log has encountered a runtime error and is unavailable. The log will not accept any new records and it may not be able to retrieve valid records. The log will still attempt to forward events if its ForwardingState is set to on.

DsLogAdmin::AdministrativeState Enum

```
enum AdministrativeState {locked, unlocked};
```

Specifies if a log can accept new records.

DsLogAdmin::ForwardingState Enum

```
enum ForwardingState {on, off}
```

Specifies if a log will forward events or not.

DsLogAdmin::LogList Sequence

```
typedef sequence<Log> LogList;
```

A sequence of log object references.

DsLogAdmin::LogIdList Sequence

```
typedef sequence<LogId> LogIdList;
```

A sequence of log ids.

DsLogAdmin::QoSType Type

```
typedef unsigned short QoSType;
```

Specifies the log's QoS level. Valid values are `QoSNone`, `QoSFlush`, and `QoSReliable`.

DsLogAdmin::QoSList Sequence

```
typedef sequence<QoSType> QoSList;
```

A list of `QoSType`.

DsLogAdmin::BasicLog Interface

The `BasicLog` interface extends the `Log` interface to support the logging by event-unaware CORBA objects. It defines only one method, `destroy()`, which is used to destroy a `BasicLog` object.

```
interface BasicLog : [Log](../dslogadminlog_interface/  
dslogadminlog_interface.md)  
{  
    void destroy();  
};
```

DsLogAdmin::BasicLogFactory Interface

The `BasicLogFactory` interface provides the functionality to instantiate a `BasicLog` object.

```
interface BasicLogFactory : [LogMgr](../dslogadminlogmgr_interface/
dslogadminlogmgr_interface.md)
{
    [BasicLog](../dslogadminbasiclog_interface/dslogadminbasiclog_interface.md)
    create(in [LogFullActionType](#dslogadmin-datatypes) full_action,
          in unsigned long long max_size,
          out [LogId](#dslogadmin-datatypes) id)
        raises ([InvalidLogFullAction](#dslogadmin-exceptions));
    [BasicLog](../dslogadminbasiclog_interface/dslogadminbasiclog_interface.md)
    create_with_id(in [LogId](#dslogadmin-datatypes) id,
                  in [LogFullActionType](#dslogadmin-datatypes)
full_action,
                  in unsigned long long max_size)
        raises ([LogIdAlreadyExists](#dslogadmin-exceptions),
[InvalidLogFullAction](#dslogadmin-exceptions));
};
```

`BasicLogFactory::create()`

`BasicLog` `create`(in `LogFullActionType` `full_action`,

```
          in unsigned long long max_size,
          out [LogId](#dslogadmin-datatypes) id);
        raises ([InvalidLogFullAction](#dslogadmin-exceptions));
```

Returns an instantiated `BasicLog` object. The `LogId` returned is assigned by the service and can be used to access the returned `BasicLog` object.

Parameters

<code>full_action</code>	Specifies what the log object will do when it fills up.
<code>max_size</code>	Specifies the maximum amount of data, in bytes, the log can hold.

<code>id</code>	The LogId assigned to the BasicLog object by the service.

Exceptions

```
[InvalidLogFullAction] (#dslogadmin-exceptions)
```

The specified full_action is not a valid [LogFullActionType](#).

BasicLogFactory::create_with_id()

[BasicLog](#) create_with_id(in [LogId](#) id,

```

                                in [LogFullActionType] (#dslogadmin-datatypes)
full_action,
                                in unsigned long long max_size)
    raises ([LogIdAlreadyExists] (#dslogadmin-exceptions),
[InvalidLogFullAction] (#dslogadmin-exceptions));
```

Returns an instantiated [BasicLog](#) object with a user supplied id.

Parameters

<code>id</code>	Specifies the LogId to assign the BasicLog.
<code>full_action</code>	Specifies what the log object will do when it fills up.
<code>max_size</code>	Specifies the maximum amount of data, in bytes, the log can hold.

Exceptions

<code>InvalidLogFullAction</code>	The specified full_action is not a valid LogFullActionType .
<code>LogIdAlreadyExists</code>	A log with the specified id already exists.

DsLogAdmin::Iterator Interface

The `Iterator` interface provides the methods for accessing records returned by the iterator when querying a log. It also provides the method used to release the resources consumed by the returned iterator.

```
interface Iterator
{
    [RecordList](#dslogadmin-datatypes) [get](#dslogadminiterator-interface)(in
unsigned long position,
                                in unsigned long how_many)
    raises([InvalidParam](#dslogadmin-exceptions));
    void destroy();
};
```

Iterator::get()

`RecordList` get(in unsigned long position,

```
                                in unsigned long how_many)
    raises([InvalidParam](#dslogadmin-exceptions));
```

Retrieves the specified number of records from the iterator object and returns them as a `RecordList`.

Parameters

<code>position</code>	The number of the record from which to start retrieving records.
<code>how_many</code>	The number of records to return.

Exceptions

```
[InvalidParam](#dslogadmin-exceptions)
```

Raised if the position is negative or past the end of the list.

Iterator::destroy()


```
void destroy();
```

Releases the resources used by the iterator object. If an iterator object is returned, you must explicitly destroy it.

DsLogAdmin::Log Interface

The `Log` interface provides all of the basic functionality for log objects. All other log interfaces inherit from this interface. The `Log` interface provides the methods for managing a log's functional properties including its `full_action` and maximum size. It also defines the methods for querying the log for records, retrieving records from the log, and deleting records from the log. In addition, it defines the `flush()` method and two methods for copying logs.

```

interface Log
{
    [LogMgr](../dslogadminlogmgr_interface/dslogadminlogmgr_interface.md)
    [my_factory](#dslogadminlog-interface)();
    [LogId](#dslogadmin-datatypes) [id](#dslogadminlog-interface)();
    unsigned long [get_max_record_life](#dslogadminlog-interface)();
    void [set_max_record_life](#dslogadminlog-interface)(in unsigned long
life);
    unsigned long long [get_max_size](#dslogadminlog-interface)();
    void [set_max_size](#dslogadminlog-interface)(in unsigned long long size)
        raises ([InvalidParam](#dslogadmin-exceptions));
    unsigned long long [get_current_size](#dslogadminlog-interface)();
    unsigned long long [get_n_records](#dslogadminlog-interface)();
    [LogFullActionType](#dslogadmin-datatypes) [get_log_full_action]
(#dslogadminlog-interface)();
    void [set_log_full_action](#dslogadminlog-interface)(in [LogFullActionType]
(#dslogadmin-datatypes) action)
        raises ([InvalidLogFullAction](#dslogadmin-exceptions));
    [AdministrativeState](#dslogadmin-datatypes) [get_administrative_state]
(#dslogadminlog-interface)();
    void [set_administrative_state](#dslogadminlog-interface)(in
[AdministrativeState](#dslogadmin-datatypes) state);
    [ForwardingState](#dslogadmin-datatypes) [get_forwarding_state]
(#dslogadminlog-interface)();
    void [set_forwarding_state](#dslogadminlog-interface)(in [ForwardingState]
(#dslogadmin-datatypes) state);
    [OperationalState](#dslogadmin-datatypes) [get_operational_state]
(#dslogadminlog-interface)();
    [AvailabilityStatus](#dslogadmin-datatypes) [get_availability_status]
(#dslogadminlog-interface)();
    [TimeInterval](#dslogadmin-datatypes) [get_interval](#dslogadminlog-
interface)();
    void [set_interval](#dslogadminlog-interface)(in [TimeInterval]
(#dslogadmin-datatypes) interval)
        raises ([InvalidTime](#dslogadmin-exceptions), [InvalidTimeInterval]
(#dslogadmin-exceptions));
    [CapacityAlarmThresholdList](#dslogadmin-datatypes)
[get_capacity_alarm_thresholds](#dslogadminlog-interface)();
    void [set_capacity_alarm_thresholds](#dslogadminlog-interface)(in
[CapacityAlarmThresholdList](#dslogadmin-datatypes) threshs)
        raises ([InvalidThreshold](#dslogadmin-exceptions));
    [WeekMask](#dslogadmin-datatypes) [get_week_mask](#dslogadminlog-interface)
();
    void [set_week_mask](#dslogadminlog-interface)(in [WeekMask](#dslogadmin-
datatypes) masks)
        raises ([InvalidTime](#dslogadmin-exceptions), [InvalidTimeInterval]

```

```

(#dslogadmin-exceptions), [InvalidMask](#dslogadmin-exceptions));
    [QoSList](#dslogadmin-datatypes) [get_log_qos](#dslogadminlog-interface)();
    void [set_log_qos](#dslogadminlog-interface)(in [QoSList](#dslogadmin-
datatypes) qos) raises ([UnsupportedQoS](#qos-and-admin-exceptions))
    [RecordList](#dslogadmin-datatypes) [query](#dslogadminlog-interface)(in
string grammar, in [Constraint](#costrading-data-types) c,
        out [Iterator](../dslogadminiterator_interface/
dslogadminiterator_interface.md) i)
        raises([InvalidGrammar](#cosnotifyfilter-exceptions), [InvalidConstraint]
(#cosnotifyfilter-exceptions));
    [RecordList](#dslogadmin-datatypes) [retrieve](#dslogadminlog-interface)(in
[TimeT](#dslogadmin-datatypes) from_time, in long how_many,
        out [Iterator](../dslogadminiterator_interface/
dslogadminiterator_interface.md) i);
    unsigned long [match](#cosnotifyfilterfilter-interface)(in string grammar,
in [Constraint](#costrading-data-types) c)
        raises([InvalidGrammar](#cosnotifyfilter-exceptions), [InvalidConstraint]
(#cosnotifyfilter-exceptions));
    unsigned long [delete_records](#dslogadminlog-interface)(in string grammar,
in [Constraint](#costrading-data-types) c)
        raises([InvalidGrammar](#cosnotifyfilter-exceptions), [InvalidConstraint]
(#cosnotifyfilter-exceptions));
    unsigned long [delete_records_by_id](#dslogadminlog-interface)(in
[RecordIdList](#dslogadmin-datatypes) ids);
    void [write_records](#dslogadminlog-interface)(in [Anys](#dslogadmin-
datatypes) records)
        raises([LogFull](#dslogadmin-exceptions), [LogOffDuty](#dslogadmin-
exceptions), [LogLocked](#dslogadmin-exceptions), [LogDisabled](#dslogadmin-
exceptions));
    void [write_recordlist](#dslogadminlog-interface)(in [RecordList]
(#dslogadmin-datatypes) list)
        raises([LogFull](#dslogadmin-exceptions), [LogOffDuty](#dslogadmin-
exceptions), [LogLocked](#dslogadmin-exceptions), [LogDisabled](#dslogadmin-
exceptions));
    void [set_record_attribute](#dslogadminlog-interface)(in [RecordId]
(#dslogadmin-datatypes) id, in [NVList](../corbanvlist_class/
corbanvlist_class.md) attr_list)
        raises([InvalidRecordId](#dslogadmin-exceptions), [InvalidAttribute]
(#dslogadmin-exceptions));
    unsigned long [set_records_attribute](#dslogadminlog-interface)(in string
grammar,
        in [Constraint](#costrading-data-types)
c,
        in [NVList](../corbanvlist_class/
corbanvlist_class.md) attr_list)
        raises([InvalidGrammar](#cosnotifyfilter-exceptions), [InvalidConstraint]
(#cosnotifyfilter-exceptions), [InvalidAttribute](#dslogadmin-exceptions));

```

```

[NVList](../corbanvlist_class/corbanvlist_class.md) [get_record_attribute]
(#dslogadminlog-interface)(in [RecordId](#dslogadmin-datatypes) id)
    raises([InvalidRecordId](#dslogadmin-exceptions));
[Log](#dslogadminlog-interface) [copy](#policy-methods)(out [LogId]
(#dslogadmin-datatypes) id);
[Log](#dslogadminlog-interface) [copy_with_id](#dslogadminlog-interface)(in
[LogId](#dslogadmin-datatypes) id) raises([LogIdAlreadyExists](#dslogadmin-
exceptions));
void [flush](#dslogadminlog-interface)() raises([UnsupportedQoS](#qos-and-
admin-exceptions));
};

```

Log::my_factory()

[LogMgr](#) my_factory();

Returns an object reference to the log object's log factory.

Log::id()

[LogId](#) id();

Returns the id of the log.

Log::get_max_record_life()

unsigned long get_max_record_life();

Returns the maximum amount of time, in seconds, that a record stays valid in the log.

Log::set_max_record_life()

void set_max_record_life(in unsigned long life);

Sets the maximum amount of time, in seconds, that a record stays valid in the log. After a record has become stale, it will automatically be removed from the log.

Parameters

life

The number of seconds for which records will remain valid. Zero specifies an infinite life span.

Log::get_max_size()

unsigned long long get_max_size();

Returns the maximum size, in bytes, of the log.

Log::set_max_size()

void set_max_size(in unsigned long long size)

```
raises ( [InvalidParam] (#dslogadmin-exceptions) );
```

Set the maximum size, in bytes, of the log.

Parameters

size

The maximum size of the log object in bytes.

Exceptions

```
[InvalidParam] (#dslogadmin-exceptions)
```

The size specified is smaller than the current size of the log.

Log::get_current_size()

unsigned long long get_current_size();

Returns the current size of the log in octets.

Log::get_n_records()

unsigned long long get_n_records();

Returns the current number of records in the log.

Log::get_log_full_action()

[LogFullActionType](#) get_log_full_action();

Returns the log's `full_action` setting.

Log::set_log_full_action()

void set_log_full_action(in [LogFullActionType](#) action)

```
raises([InvalidLogFullAction](#dslogadmin-exceptions));
```

Sets the log's `full_action`.

Parameters

`action`

The log's `full_action`. Valid values are `wrap` and `halt`.

Exceptions

```
[InvalidLogFullAction](#dslogadmin-exceptions)
```

The `full_action` specified is not a supported.

```
Log::get_administrative_state()
```

```
AdministrativeState get_administrative_state();
```

Returns the log's administrative state.

```
Log::set_administrative_state()
```

```
void set_administrative_state(in AdministrativeState state);
```

Sets the log's administrative state.

Parameters

`state`

The new administrative state for the log. Valid states are `locked` and `unlocked`.

```
Log::get_forwarding_state()
```

```
ForwardingState get_forwarding_state();
```

Returns the log's forwarding state. If the log's forwarding state is `on`, the log will forward events.

```
Log::set_forwarding_state()
```

```
void set_forwarding_state(in ForwardingState state);
```

Changes the log's forwarding state.

Parameters

state

The new forwarding state. The valid values are:

on—specifies that the log will forward events.

off—specifies that the log will not forward events.

Log::get_operational_state()

[OperationalState](#) get_operational_state();

Returns the log's operational state. The log can either be `enabled` or `disabled`.

Log::get_interval()

[TimeInterval](#) get_interval();

Returns the log's coarse grained logging interval.

Log::set_interval()

void set_interval(in [TimeInterval](#) interval)

```
raises ([InvalidTime](#dslogadmin-exceptions), [InvalidTimeInterval]
(#dslogadmin-exceptions));
```

Changes the log's coarse grained logging interval.

Parameters

interval

The log's new coarse grained logging interval. Zero sets the log to an infinite duration.

Exceptions

`InvalidTime`

One of the times specified is not a legal time.

<code>InvalidTimeInte rval</code>	The start time of the interval is after the stop time. Also, the stop time is prior to the current time.

`Log::get_availability_status()`

[AvailabilityStatus](#) `get_availability_status();`

Returns the log's availability. The log can be on duty, off duty, full, or both off duty and full.

`Log::get_capacity_alarm_thresholds()`

[CapacityAlarmThresholdList](#) `get_capacity_alarm_thresholds();`

Returns a list of the log's alarm thresholds.

`Log::set_capacity_alarm_thresholds()`

`void set_capacity_alarm_thresholds(in CapacityAlarmThresholdList threshs)`

```
raises ([InvalidThreshold](#dslogadmin-exceptions));
```

Sets threshold alarms in the log.

Parameters

`threshs`

A sequence of [Threshold](#) specifying at what points threshold alarm events are to be generated.

Exceptions

```
[InvalidThreshold](#dslogadmin-exceptions)
```

Raised if one of the thresholds is not in the valid range.

`Log::get_week_mask()`

[WeekMask](#) `get_week_mask();`

Returns the log's weekly schedule.

`Log::set_week_mask()`

void set_week_mask(in [WeekMask](#) masks)

```
raises ([InvalidTime](#dslogadmin-exceptions), [InvalidTimeInterval]
(#dslogadmin-exceptions), [InvalidMask](#dslogadmin-exceptions));
```

Changes the log's weekly schedule.

Parameters

masks

The new schedule to set on the log.

Exceptions

<code>InvalidTime</code>	One of the times set on the log is not a valid time.
<code>InvalidTimeInterval</code>	One of the stop times specified is before its associated start time. Also, one of the time intervals overlaps another time interval.
<code>InvalidMask</code>	The WeekMask is malformed.

Log::get_log_qos()

[QoSList](#) get_log_qos();

Returns the log's QoS settings.

Log::set_log_qos()

void set_log_qos(in [QoSList](#) qos) raises ([UnsupportedQoS](#));

Sets the log's QoS type. Valid settings are `QoSNone`, `QoSFlush`, and `QoSReliable`.

Parameters

qos

The QoS properties to set on the log.

Exceptions

```
[UnsupportedQoS] (#qos-and-admin-exceptions)
```

One of the QoS properties specified for the log is invalid. The invalid setting is returned.

Log::query()

[RecordList](#) query(in string grammar, in [Constraint](#) c, out [Iterator](#) i)

```
raises([InvalidGrammar] (#cosnotifyfilter-exceptions), [InvalidConstraint]
(#cosnotifyfilter-exceptions));
```

Retreives records from the log based on a constraint.

Parameters

<code>grammar</code>	The grammar used to consruct the constraint. The telecom logging service support the <code>EXTENDED_TCL</code> grammar
<code>c</code>	The constraint string against which records are matched.
<code>i</code>	Used when a large number of records are retrieved. If it not used it will be <code>nil</code> .

Exceptions

<code>InvalidGrammar</code>	The telecom logging service does not support the specified grammar.
<code>InvalidConstraint</code>	The constraint does not conform to the specified grammar.

Log::retrieve()

[RecordList](#) retrieve(in TimeT from_time, in long how_many,

```
out Iterator i);
```

Returns the specified number of records starting at the specified time. If the number of records is larger than can be stored in the return parameter, the remaining records are accessible through the [Iterator](#).

Parameters

<code>from_time</code>	The time at which the first record to retrieve was logged.
<code>how_many</code>	The number of records to retrieve. A negative value causes the method to retrieve records prior to the specified time.
<code>i</code>	The Iterator object reference.

Log::match()

unsigned long match(in string grammar, in Constraint c)

```
raises([InvalidGrammar](#cosnotifyfilter-exceptions), [InvalidConstraint]
(#cosnotifyfilter-exceptions));
```

Returns the number of records that match the specified constraint.

Parameters

<code>grammar</code>	The grammar used to specify the constraint. The telecom logging service supports the <code>EXTENDED_TCL</code> grammar.
<code>c</code>	The constraint string.

Exceptions

<code>InvalidGrammar</code>	The telecom logging service does not support the specified grammar.
<code>InvalidConstraint</code>	The constraint does not conform to the specified grammar.

Log::delete_records()

unsigned long delete_records(in string grammar, in [Constraint](#) c)

```
raises([InvalidGrammar](#cosnotifyfilter-exceptions), [InvalidConstraint]
(#cosnotifyfilter-exceptions));
```

Deletes all of the records that match the specified constraint and returns the number of records deleted.

Parameters

<code>grammar</code>	The grammar used to specify the constraint. The telecom logging service supports the <code>EXTENDED_TCL</code> grammar.
<code>c</code>	The constraint string.

Exceptions

<code>InvalidGrammar</code>	The telecom logging service does not support the specified grammar.
<code>InvalidConstraint</code>	The constraint does not conform to the specified grammar.

`Log::delete_records_by_id()`

`unsigned long delete_records_by_id(in RecordIdList ids);`

Deletes the specified records and returns the number of deleted records.

Parameters

`ids`

A sequence of record ids specifying the records to delete.

`Log::write_records()`

`void write_records(in Anys records)`

```
raises([LogFull](#dslogadmin-exceptions), [LogOffDuty](#dslogadmin-exceptions), [LogLocked](#dslogadmin-exceptions), [LogDisabled](#dslogadmin-exceptions));
```

Writes a series of records to a log. The you cannot specify any optional attributes and cannot discover the records id.

Parameters

records

A sequence of `any` that contains the data for a group of records.

Exceptions

<code>LogFull</code>	The log is full and its <code>full_action</code> is set to <code>halt</code> .
<code>LogOffDuty</code>	The log is not currently scheduled to accept new records.
<code>LogLocked</code>	The log's administrative state is set to not accept new records.
<code>LogDisabled</code>	The log has encountered a processing error and is unable to accept new records.

`Log::write_recordlist()`

`void write_recordlist(in RecordList list)`

```
raises([LogFull](#dslogadmin-exceptions), [LogOffDuty](#dslogadmin-exceptions), [LogLocked](#dslogadmin-exceptions), [LogDisabled](#dslogadmin-exceptions));
```

Writes a series of records to the log. You can construct records that include an optional attribute list and each record in the list will be updated to include the time it was logged and its record id.

Parameters

list

A sequence of [LogRecord](#) that contains the data for a group of records.

Exceptions

<code>LogFull</code>	The log is full and its <code>full_action</code> is set to <code>halt</code> .
<code>LogOffDuty</code>	The log is not currently scheduled to accept new records.
<code>LogLocked</code>	The log's administrative state is set to not accept new records.

<code>LogDisabled</code>	The log has encountered a processing error and is unable to accept new records.

`Log::set_record_attribute()`

`void set_record_attribute(in RecordId id, in NVList attr_list)`

```
raises([InvalidRecordId](#dslogadmin-exceptions), [InvalidAttribute]
(#dslogadmin-exceptions));
```

Sets attributes for a single record which is specified by its record id.

Parameters

<code>id</code>	The id of the record on which you wish to set attributes.
<code>attr_list</code>	The list of attributes that you want to set on the record.

Exceptions

<code>InvalidRecordId</code>	The record specified dose not exist.
<code>InvalidAttribute</code>	One of the attributes is illegal.

`Log::set_records_attribute()`

`unsigned long set_records_attribute(in string grammar,`

```
                                in [Constraint](#costrading-data-types)
c,
                                in [NVList](../corbanvlist_class/
corbanvlist_class.md) attr_list)
raises([InvalidGrammar](#cosnotifyfilter-exceptions), [InvalidConstraint]
(#cosnotifyfilter-exceptions), [InvalidAttribute](#dslogadmin-exceptions));
```

Sets attributes for all records that match the constraint. It returns the numbers of records whose attributes were changed.

Parameters

<code>grammar</code>	The grammar used to specify the constraint. The telecom logging service supports the <code>EXTENDED_TCL</code> grammar.
<code>c</code>	The constraint string.
<code>attr_list</code>	The list of attributes that you want to set on the record.

Exceptions

<code>InvalidGrammar</code>	The telecom logging service does not support the specified grammar.
<code>InvalidConstraint</code>	The constraint does not conform to the specified grammar.
<code>InvalidAttribute</code>	One of the attributes is illegal.

`Log::get_record_attribute()`

`NVList get_record_attribute(in RecordId id)`

```
raises([InvalidRecordId](#dslogadmin-exceptions));
```

Returns the list of attributes that are set on the specified record.

Parameters

`id`

The id of the record whose attributes you want to retrieve.

Exceptions

```
[InvalidRecordId](#dslogadmin-exceptions)
```

The record specified does not exist.

`Log::copy()`

`Log copy(out LogId id);`

Copies the log object and returns a reference to the new log object.

Parameters

id

The id assigned to the newly created log.

Log::copy_with_id()

Log copy_with_id(in [LogId](#) id)

```
raises ([LogIdAlreadyExists](#dslogadmin-exceptions));
```

Copies the log and returns a reference to the newly created log. This method allows you to specify the log's id.

Parameters

id

The new log's id.

Exceptions

```
[LogIdAlreadyExists](#dslogadmin-exceptions)
```

The user assigned id is already in use.

Log::flush()

void flush()

```
raises ([UnsupportedQoS](#qos-and-admin-exceptions));
```

Causes the log to flush its memory buffer to its associated permanent store.

Exceptions

[UnsupportedQoS] (#qos-and-admin-exceptions)

The log does not support `QoSFlush`.

DsLogAdmin::LogMgr Interface

The `LogMgr` interface is inherited by all the log factory interfaces. It defines three methods of discovering deployed log objects.

```
interface LogMgr
{
  [LogList](#dslogadmin-datatypes) [list_logs](#dslogadminlogmgr-interface)
  ();
  [Log](../dslogadminlog_interface/dslogadminlog_interface.md) [find_log]
  (#dslogadminlogmgr-interface)(in [LogId](#dslogadmin-datatypes) id);
  [LogIdList](#dslogadmin-datatypes) [list_logs_by_id](#dslogadminlogmgr-
  interface)();
};
```

LogMgr::list_logs()

[LogList](#) list_logs();

Returns a list of object references, one for each log object associated with the factory.

LogMgr::find_log()

[Log](#) find_log(in [LogId](#) id);

Returns an object reference to the specified log. If the log does not exist, it returns a `nil` reference.

LogMgr::list_logs_by_id()

[LogIdList](#) list_logs_by_id();

Returns a list containing the ids of all logs associated with the factory.

DsLogNotification Module

The `DsLogNotification` module defines the data types used to transmit log generated events to logging clients.

DsLogNotification::PerceivedSeverityType Type

typedef unsigned short PerceivedSeverityType;

```
const PerceivedSeverityType critical = 0;
const PerceivedSeverityType minor = 1;
const PerceivedSeverityType cleared = 2;
```

Defines the severity of a threshold alarm. A threshold alarm's severity is considered `minor` unless the log is full.

DsLogNotification::ThresholdAlarm Structure

struct ThresholdAlarm

```
{
    [Log](../dslogadminlog_interface/dslogadminlog_interface.md)
    logref;
    [LogId](#dslogadmin-datatypes)    id;
    TimeT    time;
    [Threshold](#dslogadmin-datatypes) crossed_value;
    [Threshold](#dslogadmin-datatypes) observed_value;
    [PerceivedSeverityType](#dslognotification-module) perceived_severity;
};
```

The data type passed in a threshold alarm event.

Members

<code>logref</code>	An object reference to the log object which caused the event.
<code>id</code>	The id of the log object which caused the event.
<code>time</code>	The time the event was generated.

<code>crossed_value</code>	The capacity threshold which was passed to trigger the event.
<code>observed_value</code>	The actual percentage of the log that is full.
<code>perceived_severity</code>	The severity of the alarm. If the severity is critical then the log object is full.

DsLogNotification::ObjectCreation Structure

struct ObjectCreation

```
{
    [LogId](#dslogadmin-datatypes) id;
    TimeT time;
};
```

The data type passed in an object creation event.

Members

<code>id</code>	The id of the newly created log object.
<code>time</code>	The time the log object was generated.

DsLogNotification::ObjectDeletion Structure

struct ObjectDeletion

```
{
    [LogId](#dslogadmin-datatypes) id;
    TimeT time;
};
```

The data type passed in an object deletion event.

Members

<code>id</code>	The id of the deleted log object.

<code>time</code>	The time the log object was deleted.

DsLogNotification::AttributeType Type

typedef unsigned short AttributeType;

```
const AttributeType capacityAlarmThreshold = 0;
const AttributeType logFullAction          = 1;
const AttributeType maxLogSize             = 2;
const AttributeType startTime             = 3;
const AttributeType stopTime              = 4;
const AttributeType weekMask              = 5;
const AttributeType filter                 = 6;
const AttributeType maxRecordLife         = 7;
const AttributeType qualityOfService      = 8;
```

The data type and constants used to represent the type of attribute changed in an attribute change event.

DsLogNotification::AttributeValueChange Structure

```
struct AttributeValueChange
```

```
{
    [Log](../dslogadminlog_interface/dslogadminlog_interface.md) logref;
    [LogId](#dslogadmin-datatypes) id;
    TimeT time;
    [AttributeType](#dslognotification-module) type;
    any old_value;
    any new_value;
};
```

Members

<code>logref</code>	An object reference to the log object which caused the event.
<code>id</code>	The id of the log object which caused the event.
<code>time</code>	The time the event was generated.

<code>type</code>	The attribute that was changed.
<code>old_value</code>	The previous value of the attribute.
<code>new_value</code>	The attribute's new value.

DsLogNotification::StateType Type

typedef unsigned short StateType;

```
const StateType administrativeState = 0;
const StateType operationalState   = 1;
const StateType forwardingState    = 2;
```

The data type and constants used to represent which type of state was changed in a state change event.

DsLogNotification::StateChange Structure

struct StateChange

```
{
    [Log](../dslogadminlog_interface/dslogadminlog_interface.md) logref;
    [LogId](#dslogadmin-datatypes) id;
    TimeT time;
    [StateType](#dslognotification-module) type;
    any new_value;
};
```

The data type passed in a state change event.

Members

<code>logref</code>	An object reference to the log object which caused the event.
<code>id</code>	The id of the log object which caused the event.
<code>time</code>	The time the event was generated.
<code>type</code>	The type of state that was changed.

<code>new_value</code>	The new state.

DsLogNotification::ProcessingErrorAlarm Structure

struct ProcessingErrorAlarm

```
{  
    long error_num;  
    string error_string;  
};
```

The data type passed when a processing error event occurs.

Members

<code>error_num</code>	The error number.
<code>error_string</code>	A string explaining the error.

DsNotifyLogAdmin Module

The `DsNotifyLogAdmin` module extends the functionality of the interfaces specified in the `DsLogAdmin` module to support notification style push and pull communication and forwarding of structured and sequenced events. The extended functionality also includes notification style event filtering and subscription/publication functionality.

Dynamic Module

The `Dynamic` module is used by the `PortableInterceptor` module and contains the following data types:

- `ContextList` type
- `ExceptionList` sequence
- `Parameter` structure
- `ParameterList` sequence
- `RequestContext` type

`Dynamic::ContextList`

// IDL

```
typedef CORBA::StringSeq ContextList;
```

`Dynamic::ExceptionList`

// IDL

```
typedef sequence<CORBA::TypeCode> ExceptionList;
```

`Dynamic::Parameter`

// IDL

```
struct Parameter {
    any argument;
    CORBA::ParameterMode mode;
};
```

`Dynamic::ParameterList`

// IDL

```
typedef sequence<Parameter> ParameterList;
```

`Dynamic::RequestContext`

// IDL

```
typedef CORBA::StringSeq RequestContext;
```

DynamicAny Overview

The `DynamicAny` namespace implements the IDL `DynamicAny` module which includes the following classes:

```
DynAny  
DynAnyFactory  
DynArray  
DynEnum  
DynFixed  
DynSequence  
DynStruct  
DynUnion  
DynValue
```

The common data types in the scope of the `DynamicAny` module include the following:

```
[AnySeq] (#dynamicany-overview)  
[DynAnySeq] (#dynamicany-overview)  
[FieldName] (#dynamicany-overview)  
[NameDynAnyPair] (#dynamicany-overview)  
[NameDynAnyPairSeq] (#dynamicany-overview)  
[NameValuePair] (#dynamicany-overview)  
[NameValuePairSeq] (#dynamicany-overview)
```

For most IDL data types there is a straight-forward language mapping that an object implementation uses to interpret data. However, an `any` data type can be passed to a program that may not have any static information about how to interpret the type of data in the `any` value. The `DynamicAny` module provides a runtime mechanism for constructing `any` values, traversing them, and extracting the data from `any` values. This mechanism is especially helpful for writing generic clients and servers such as bridges, browsers, debuggers, and user interface tools.

Applications dynamically construct and interpret `any` values using `DynAny` objects. For complex `any` types a `DynAny` object is an ordered collection of other component `DynAny` objects.

A `DynAny` object can be created as follows:

- Invoking a method on a `DynAnyFactory` object.
- Invoking a method on an existing `DynAny` object.

A constructed DynAny object supports methods that enable the creation of new DynAny objects that encapsulate access to the value of some constituent of the DynAny object. DynAny objects also support a copy method for creating new DynAny objects.

There is a different interface associated with each kind of constructed IDL type that inherits from the DynAny interface. The interfaces that inherit the DynAny interface include:

```
DynArray  
DynEnum  
DynFixed  
DynSequence  
DynStruct  
DynUnion  
DynValue
```

Exceptions are represented by the DynStruct interface and value types are represented by the DynValue interface.

DynamicAny::AnySeq Sequence

```
class AnySeq: private ITCxxUSeq< CORBA::Any > {
```

```

public:
    typedef AnySeq_var _var_type;
    AnySeq(
        CORBA::ULong max,
        CORBA::ULong length,
        CORBA::Any* buf,
        CORBA::Boolean release = 0
    ) : ITCxxUSeq< CORBA::Any >(max, length, buf, release) {}
    AnySeq() : ITCxxUSeq< CORBA::Any >() {}
    AnySeq(
        CORBA::ULong max
    ) : ITCxxUSeq< CORBA::Any >(max) {}
    AnySeq(
        const AnySeq& seq
    ) : ITCxxUSeq< CORBA::Any >(seq) {}
    AnySeq& operator=(
        const AnySeq& seq
    )
    {
        ITCxxUSeq< CORBA::Any >::operator=(seq);
        return *this;
    }
    ITCxxUSeq< CORBA::Any >::maximum;
    ITCxxUSeq< CORBA::Any >::length;
    ITCxxUSeq< CORBA::Any >::operator[];
    ITCxxUSeq< CORBA::Any >::replace;
    ITCxxUSeq< CORBA::Any >::get_buffer;
    ITCxxUSeq< CORBA::Any >::allocbuf;
    ITCxxUSeq< CORBA::Any >::freebuf;
    ITCxxUSeq< CORBA::Any >::operator new;
    ITCxxUSeq< CORBA::Any >::operator delete;
};

```

A sequence of CORBA::Any values.

See Also DynamicAny::DynSequence

DynamicAny::DynArray

DynamicAny::DynAnySeq Sequence

class DynAnySeq:

```

private ITCxxUIntfSeq< DynAny_ptr,
    DynAny, ITCxxIntfAlloc< DynAny_ptr, DynAny > > {
public:
    typedef DynAnySeq_var _var_type;
    DynAnySeq(
        CORBA::ULong max,
        CORBA::ULong length,
        DynAny_ptr* buf,
        CORBA::Boolean release = 0
    ) : ITCxxUIntfSeq< DynAny_ptr, DynAny, ITCxxIntfAlloc< DynAny_ptr,
DynAny > >(max, length, buf, release) {}
    DynAnySeq() : ITCxxUIntfSeq< DynAny_ptr, DynAny, ITCxxIntfAlloc<
DynAny_ptr, DynAny > >() {}
    DynAnySeq(
        CORBA::ULong max
    ) : ITCxxUIntfSeq< DynAny_ptr, DynAny, ITCxxIntfAlloc< DynAny_ptr,
DynAny > >(max) {}
    DynAnySeq(
        const DynAnySeq& seq
    ) : ITCxxUIntfSeq< DynAny_ptr, DynAny, ITCxxIntfAlloc< DynAny_ptr,
DynAny > >(seq) {}
    DynAnySeq& operator=(
        const DynAnySeq& seq
    )
    {
        ITCxxUIntfSeq< DynAny_ptr, DynAny, ITCxxIntfAlloc< DynAny_ptr,
DynAny > >::operator=(seq);
        return *this;
    }
    ITCxxUIntfSeq< DynAny_ptr, DynAny, ITCxxIntfAlloc< DynAny_ptr, DynAny
> >::maximum;
    ITCxxUIntfSeq< DynAny_ptr, DynAny, ITCxxIntfAlloc< DynAny_ptr, DynAny
> >::length;
    ITCxxUIntfSeq< DynAny_ptr, DynAny, ITCxxIntfAlloc< DynAny_ptr, DynAny
> >::operator[];
    ITCxxUIntfSeq< DynAny_ptr, DynAny, ITCxxIntfAlloc< DynAny_ptr, DynAny
> >::replace;
    ITCxxUIntfSeq< DynAny_ptr, DynAny, ITCxxIntfAlloc< DynAny_ptr, DynAny
> >::get_buffer;
    ITCxxUIntfSeq< DynAny_ptr, DynAny, ITCxxIntfAlloc< DynAny_ptr, DynAny
> >::allocbuf;
    ITCxxUIntfSeq< DynAny_ptr, DynAny, ITCxxIntfAlloc< DynAny_ptr, DynAny
> >::freebuf;
    ITCxxUIntfSeq< DynAny_ptr, DynAny, ITCxxIntfAlloc< DynAny_ptr, DynAny
> >::operator new;
    ITCxxUIntfSeq< DynAny_ptr, DynAny, ITCxxIntfAlloc< DynAny_ptr, DynAny

```

```
> >::operator delete;
};
```

A sequence of DynAny values.

See Also DynamicAny::DynSequence

```
DynamicAny::DynArray
```

DynamicAny::FieldName Type

```
// IDL
typedef string FieldName;
```

```
// C++
```

```
typedef char* FieldName;
```

A string representing the name of a member in a structure, union, or value type.

See Also DynamicAny::DynStruct

```
DynamicAny::DynUnion
DynamicAny::DynValue
```

DynamicAny::NameDynAnyPair Structure

```
// IDL
struct NameDynAnyPair {
    FieldName id;
    DynAny value;
};
```

```
struct NameDynAnyPair {
```



```
typedef NameDynAnyPair_var _var_type;
ITGenFieldName_mgr id;
ITGenDynAny_mgr value;
};
```

A structure containing the name and value of a field or member.

See Also DynamicAny::NameDynAnyPairSeq

DynamicAny::NameDynAnyPairSeq Sequence

```
class NameDynAnyPairSeq: private ITCxxUSeq< NameDynAnyPair > {
```

```

public:
    typedef NameDynAnyPairSeq_var _var_type;
    NameDynAnyPairSeq(
        CORBA::ULong max,
        CORBA::ULong length,
        NameDynAnyPair* buf,
        CORBA::Boolean release = 0
    ) : ITCxxUSeq< NameDynAnyPair >(max, length, buf, release) {}
    NameDynAnyPairSeq() : ITCxxUSeq< NameDynAnyPair >() {}
    NameDynAnyPairSeq(
        CORBA::ULong max
    ) : ITCxxUSeq< NameDynAnyPair >(max) {}
    NameDynAnyPairSeq(
        const NameDynAnyPairSeq& seq
    ) : ITCxxUSeq< NameDynAnyPair >(seq) {}
    NameDynAnyPairSeq& operator=(
        const NameDynAnyPairSeq& seq
    )
    {
        ITCxxUSeq< NameDynAnyPair >::operator=(seq);
        return *this;
    }
    ITCxxUSeq< NameDynAnyPair >::maximum;
    ITCxxUSeq< NameDynAnyPair >::length;
    ITCxxUSeq< NameDynAnyPair >::operator[];
    ITCxxUSeq< NameDynAnyPair >::replace;
    ITCxxUSeq< NameDynAnyPair >::get_buffer;
    ITCxxUSeq< NameDynAnyPair >::allocbuf;
    ITCxxUSeq< NameDynAnyPair >::freebuf;
    ITCxxUSeq< NameDynAnyPair >::operator new;
    ITCxxUSeq< NameDynAnyPair >::operator delete;
};

```

A sequence of NameDynAnyPair structures.

See Also DynamicAny::DynStruct

DynamicAny::DynValue

DynamicAny::NameValuePair Structure

```

struct NameValuePair {

```

```
typedef NameValuePair_var _var_type;
ITGenFieldName_mgr id;
CORBA::Any value;
};
```

A structure containing the name and value of a field or member.

See Also DynamicAny::NameValuePairSeq

DynamicAny::NameValuePairSeq Sequence

```
class NameValuePairSeq: private ITCxxUSeq< NameValuePair > {
```

```

public:
    typedef NameValuePairSeq_var _var_type;
    NameValuePairSeq(
        CORBA::ULong max,
        CORBA::ULong length,
        NameValuePair* buf,
        CORBA::Boolean release = 0
    ) : ITCxxUSeq< NameValuePair >(max, length, buf, release) {}
    NameValuePairSeq() : ITCxxUSeq< NameValuePair >() {}
    NameValuePairSeq(
        CORBA::ULong max
    ) : ITCxxUSeq< NameValuePair >(max) {}
    NameValuePairSeq(
        const NameValuePairSeq& seq
    ) : ITCxxUSeq< NameValuePair >(seq) {}
    NameValuePairSeq& operator=(
        const NameValuePairSeq& seq
    )
    {
        ITCxxUSeq< NameValuePair >::operator=(seq);
        return *this;
    }
    ITCxxUSeq< NameValuePair >::maximum;
    ITCxxUSeq< NameValuePair >::length;
    ITCxxUSeq< NameValuePair >::operator[];
    ITCxxUSeq< NameValuePair >::replace;
    ITCxxUSeq< NameValuePair >::get_buffer;
    ITCxxUSeq< NameValuePair >::allocbuf;
    ITCxxUSeq< NameValuePair >::freebuf;
    ITCxxUSeq< NameValuePair >::operator new;
    ITCxxUSeq< NameValuePair >::operator delete;
};

```

A sequence of NameValuePair structures.

See Also DynamicAny::DynStruct

DynamicAny::DynValue

DynamicAny::DynAny Class

Your application can dynamically construct and interpreted `Any` values using `DynAny` objects. A `DynAny` object is associated with a data value which corresponds to a copy of the value inserted into an `any`. Portable programs should use the `DynAny` interface to access and modify the contents of an `Any` in those cases where basic insertion and extraction operators are not sufficient.

`DynAny` methods can be organized as follows:

Table 12: DynAny Methods

General Methods	Insert Methods	Get Methods
<code>assign()</code>	<code>insert_any()</code>	<code>get_any()</code>
<code>component_count()</code>	<code>insert_boolean()</code>	<code>get_boolean()</code>
<code>copy()</code>	<code>insert_char()</code>	<code>get_char()</code>
<code>current_component()</code>	<code>insert_double()</code>	<code>get_double()</code>
<code>destroy()</code>	<code>insert_dyn_any()</code>	<code>get_dyn_any()</code>
<code>~DynAny()</code>	<code>insert_float()</code>	<code>get_float()</code>
<code>equal()</code>	<code>insert_long()</code>	<code>get_long()</code>
<code>from_any()</code>	<code>insert_longdouble()</code>	<code>get_longdouble()</code>
<code>next()</code>	<code>insert_longlong()</code>	<code>#p_d21029e1_d21030e1_d21031e1_d21032e1get_longlong()</code>
<code>rewind()</code>	<code>insert_longlong()</code>	<code>get_longlong()</code>
<code>seek()</code>	<code>insert_octet()</code>	<code>get_octet()</code>
<code>to_any()</code>	<code>insert_reference()</code>	<code>get_reference()</code>
<code>type()</code>	<code>insert_short()</code>	<code>get_short()</code>
	<code>insert_string()</code>	<code>get_string()</code>
	<code>insert_typecode()</code>	<code>get_typecode()</code>
	<code>insert_ulong()</code>	<code>get_ulong()</code>
	<code>insert_ulonglong()</code>	<code>get_ulonglong()</code>
	<code>insert_ushort()</code>	<code>get_ushort()</code>
	<code>insert_val()</code>	<code>get_val()</code>
	<code>insert_wchar()</code>	<code>get_wchar()</code>
	<code>insert_wstring()</code>	<code>get_wstring()</code>

The following exceptions are also defined in the `DynAny` class:

```
[InvalidValue](#cosnotifyfilter-exceptions)
[TypeMismatch](#it_configconfiguration-interface)
```

The `DynAny` class is the base for the following classes:

```

DynArray
DynEnum
DynFixed
DynSequence
DynStruct
DynUnion
DynValue

```

Because the values of `Any` types can be quite complex, it is helpful to think of a `DynAny` object as an ordered collection of other *component* `DynAny` objects. For simpler `DynAny` objects that represent a basic type, the ordered collection of components is empty. For example, a `long` or a type without components (such as an empty exception) has empty components.

The `DynAny` interface allows a client to iterate through the components of the values pointed to by these objects. Each `DynAny` object maintains the notion of a *current position* into its collection of component `DynAny` objects. The current position is identified by an index value that runs from 0 to `n-1`, where `n` is the number of components. Methods are available that allow you to recursively examine `DynAny` contents. For example, you can determine the current position using `current_component()`, and `component_count()` returns the number of components in the `DynAny` object. You can also use `rewind()`, `seek()`, and `next()` to change the current position. If a `DynAny` is initialized with a value that has components, the index is initialized to 0. The special index value of -1 indicates a current position that points nowhere. For example, some values (such as an empty exception) cannot have a current position. In these cases the index value is fixed at -1.

You can use the iteration operations, together with `current_component()`, to dynamically compose an `Any` value. After creating a dynamic any, such as a `DynStruct`, you can use `current_component()` and `next()` to initialize all the components of the value. Once the dynamic value is completely initialized, `to_any()` creates the corresponding `Any` value.

You use the `insert_type()` and `get_type()` methods to not only handle basic `DynAny` objects but they are also helpful in handling constructed `DynAny` objects. when you insert a basic data type value into a constructed `DynAny` object, it initializes the current component of the constructed data value associated with the `DynAny` object.

For example, invoking `insert_boolean()` on a `DynStruct` object implies inserting a boolean data value at the current position of the associated structure data value. In addition, you can use the `insert_type()` and `get_type()` methods to traverse `Any` values associated with sequences of basic data types without the need to generate a `DynAny` object for each element in the sequence.

The `DynAny` object has a `destroy()` method that you can use to destroy a top-level `DynAny` object and any component `DynAny` objects obtained from it.

Exceptions `TypeMismatch` is raised if you call methods `insert_type()` or `get_type()` on a `DynAny` whose current component itself has components.

`MARSHAL` is raised if you attempt to export `DynAny` objects to other processes or externalize one with `CORBA::ORB::object_to_string()`. This is because `DynAny` objects are intended to be local to the process in which they are created and used.

`NO_IMPLEMENT` might be raised if you attempt the following:

- Invoke operations exported through the `CORBA::Object` interface even though `DynAny` objects export operations defined in this standard interface.
- Use a `DynAny` object with the DII.

The following code is the complete class:


```

// class is in namespace DynamicAny
class IT_DYNANY_API DynAny : public virtual CORBA::Object {
public:
    typedef DynamicAny::DynAny_ptr _ptr_type;
    typedef DynamicAny::DynAny_var _var_type;
    virtual ~DynAny();
    static DynAny_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static DynAny_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static DynAny_ptr _duplicate(
        DynAny_ptr p
    );
    inline static DynAny_ptr _nil();
    class IT_DYNANY_API InvalidValue: public CORBA::UserException
    { ... };
    class IT_DYNANY_API TypeMismatch: public CORBA::UserException
    { ... };
    virtual ::CORBA::TypeCode_ptr type() = 0;
    virtual void assign(
        DynAny_ptr dyn_any
    ) = 0;
    virtual void from_any(
        const CORBA::Any& value
    ) = 0;
    virtual CORBA::Any* to_any() = 0;
    virtual CORBA::Boolean equal(
        DynAny_ptr dyn_any
    ) = 0;
    virtual void destroy() = 0;
    virtual DynAny_ptr copy() = 0;
    virtual void insert_boolean(
        CORBA::Boolean value
    ) = 0;
    virtual void insert_octet(
        CORBA::Octet value
    ) = 0;
    virtual void insert_char(
        CORBA::Char value
    ) = 0;
    virtual void insert_short(
        CORBA::Short value
    ) = 0;
    virtual void insert_ushort(

```

```

        CORBA::UShort value
    ) = 0;
    virtual void insert_long(
        CORBA::Long value
    ) = 0;
    virtual void insert_ulong(
        CORBA::ULong value
    ) = 0;
    virtual void insert_float(
        CORBA::Float value
    ) = 0;
    virtual void insert_double(
        CORBA::Double value
    ) = 0;
    virtual void insert_string(
        const char* value
    ) = 0;
    virtual void insert_reference(
        CORBA::Object_ptr value
    ) = 0;
    virtual void insert_typecode(
        ::CORBA::TypeCode_ptr value
    ) = 0;
    virtual void insert_longlong(
        CORBA::LongLong value
    ) = 0;
    virtual void insert_ulonglong(
        CORBA::ULongLong value
    ) = 0;
    virtual void insert_longdouble(
        CORBA::LongDouble value
    ) = 0;
    virtual void insert_wchar(
        CORBA::WChar value
    ) = 0;
    virtual void insert_wstring(
        const CORBA::WChar* value
    ) = 0;
    virtual void insert_any(
        const CORBA::Any& value
    ) = 0;
    virtual void insert_dyn_any(
        DynAny_ptr value
    ) = 0;
    virtual void insert_val(
        CORBA::ValueBase* value
    ) = 0;

```

```

virtual CORBA::Boolean get_boolean() = 0;
virtual CORBA::Octet get_octet() = 0;
virtual CORBA::Char get_char() = 0;
virtual CORBA::Short get_short() = 0;
virtual CORBA::UShort get_ushort() = 0;
virtual CORBA::Long get_long() = 0;
virtual CORBA::ULong get_ulong() = 0;
virtual CORBA::Float get_float() = 0;
virtual CORBA::Double get_double() = 0;
virtual char* get_string() = 0;
virtual CORBA::Object_ptr get_reference() = 0;
virtual ::CORBA::TypeCode_ptr get_typecode() = 0;
virtual CORBA::LongLong get_longlong() = 0;
virtual CORBA::ULongLong get_ulonglong() = 0;
virtual CORBA::LongDouble get_longdouble() = 0;
virtual CORBA::WChar get_wchar() = 0;
virtual CORBA::WChar* get_wstring() = 0;
virtual CORBA::Any* get_any() = 0;
virtual DynAny_ptr get_dyn_any() = 0;
virtual CORBA::ValueBase* get_val() = 0;
virtual CORBA::Boolean seek(
    CORBA::Long index
) = 0;
virtual void rewind() = 0;
virtual CORBA::Boolean next() = 0;
virtual CORBA::ULong component_count() = 0;
virtual DynAny_ptr current_component() = 0;
static const IT_FWString _it_fw_type_id;
};

```

for descriptions of the standard helper functions:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`DynAny::assign()`

// C++

```
virtual void assign(
    DynAny_ptr  dyn_any
) = 0;
```

Initializes the value associated with a `DynAny` object with the value associated with another `DynAny` object.

Parameters

`dyn_any`

The `DynAny` object to initialize to.

The current position of the target `DynAny` is set to zero for values that have components and to -1 for values that do not have components.

Exceptions

`TypeMismatch`

The type of the passed `DynAny` is not equivalent to the type of the target `DynAny`.

`DynAny::component_count()`

// C++

```
virtual CORBA::ULong component_count() = 0;
```

Returns the number of components of a `DynAny`. For a `DynAny` without components, it returns zero.

The operation only counts the components at the top level. For example, if you invoke `component_count()` on a `DynStruct` with a single member, the return value is 1, irrespective of the type of the member.

Table 13: Return Values for `DynAny::component_count()`

Type	Return Value
<code>DynSequence</code>	The current number of elements.
<code>DynStruct</code> <code>DynValue</code>	The number of members.

Type	Return Value
DynArray	The number of elements.
DynUnion	2 if the discriminator indicates that a named member is active. 1 Otherwise.
DynFixed DynEnum	zero

Exceptions

TypeMismatch

The method is called on a `DynAny` that cannot have components, such as a `DynEnum` or an empty exception.

See Also `DynamicAny::DynAny::current_component()`

```
DynamicAny::DynAny::seek()
DynamicAny::DynAny::rewind()
DynamicAny::DynAny::next()
```

`DynAny::copy()`

// C++

```
virtual DynAny_ptr copy() = 0;
```

Returns a new `DynAny` object whose value is a deep copy of the `DynAny` on which it is invoked.

The operation is polymorphic, that is, invoking it on one of the types derived from `DynAny`, such as `DynStruct`, creates the derived type but returns its reference as the `DynAny` base type.

`DynAny::current_component()`

```
// C++
virtual DynAny_ptr current_component() = 0;
```

Returns the `DynAny` for the component at the current position. It does not advance the current position, so repeated calls without an intervening call to `rewind()`, `next()`, or `seek()` return the same component. If the current position current position is -1, the method returns a nil reference.

The returned `DynAny` object reference can be used to get or set the value of the current component. If the current component represents a complex type, the returned reference can be narrowed based on the `TypeCode` to get the interface corresponding to the complex type.

Exceptions

TypeMismatch

The method is called on a `DynAny` that cannot have components, such as a `DynEnum` or an empty exception.

See Also `DynamicAny::DynAny::component_count()`

```
DynamicAny::DynAny::seek()
DynamicAny::DynAny::rewind()
DynamicAny::DynAny::next()
```

`DynAny::destroy()`

```
// C++
```

```
virtual void destroy() = 0;
```

Destroys a `DynAny` object. This operation frees any resources used to represent the data value associated with a `DynAny` object.

Destroying a top-level `DynAny` object (one that was not obtained as a component of another `DynAny`) also destroys any component `DynAny` objects obtained from it. Destroying a non-top level (component) `DynAny` object does nothing.

You can manipulate a component of a `DynAny` object beyond the life time of its top-level `DynAny` by making a copy of the component with `copy()` before destroying the top-level `DynAny` object.

Enhancement Orbix guarantees to always destroy all local objects it creates when the last reference to them is released so you do not have to call `destroy()`. However, code that relies on this feature is not strictly CORBA compliant and may leak resources with other ORBs. (According

to the CORBA specification, simply calling CORBA::release() on all references to a `DynAny` object does not delete the object or its components so each `DynAny` object created must be explicitly destroyed to avoid memory leaks.)

Exceptions

`OBJECT_NOT_EXIST`

A destroyed `DynAny` object or any of its components is referenced.

See Also `DynamicAny::DynAny::copy()`

```
CORBA::release()
IT_CORBA::RefCountedLocalObject
```

`DynAny::~~DynAny()` Destructor

// C++

```
virtual ~DynAny();
```

The destructor for a `DynAny` object.

`DynAny::equal()`

// C++

```
virtual CORBA::Boolean equal(
    DynAny_ptr dyn_any
) = 0;
```

Compares two `DynAny` values for equality and returns true if the values are equal, false otherwise. Two `DynAny` values are equal if their type codes are equivalent and, recursively, all respective component `DynAny` values are equal. The current position of the two `DynAny` values being compared has no effect on the result of `equal()`.

Parameters

`dyn_any`

The `DynAny` value to compare.

`DynAny::from_any()`

```
// C++
```

```
virtual void from_any(
    const CORBA::Any& value
) = 0;
```

Initializes the value associated with a `DynAny` object with the value contained in an Any type.

The current position of the target `DynAny` is set to zero for values that have components and to -1 for values that do not have components.

Parameters

value

An Any value to initialize the `DynAny` object to.

Exceptions

<code>TypeMismatch</code>	The type of the passed <code>Any</code> is not equivalent to the type of the target <code>DynAny</code> .
<code>InvalidValue</code>	The passed <code>Any</code> does not contain a legal value (such as a null string).

See Also `DynamicAny::DynAny::to_any()`

`DynAny::get_any()`

```
// C++
```

```
virtual CORBA::Any* get_any() = 0;
```

Returns an Any value from the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_any` (an Any TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_any`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.

<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_any()`

`DynAny::get_boolean()`

// C++

```
virtual CORBA::Boolean get_boolean() = 0;
```

Returns a Boolean value from the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_boolean` (a `boolean` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_boolean`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_boolean()`

`DynAny::get_char()`

// C++

```
virtual CORBA::Char get_char() = 0;
```

Returns a Char value from the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_char` (a `char` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_char`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.

InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_char()`

`DynAny::get_double()`

// C++

```
virtual CORBA::Double get_double() = 0;
```

Returns a `Double` value from the `DynAny` object.

It is valid for you to use this method if the `TypeCode` contained in the `DynAny` is equivalent to `_tc_double` (a `double` `TypeCode`), or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent to `_tc_double`. The current position is unchanged after the call.

Exceptions

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_double()`

`DynAny::get_dyn_any()`

// C++

```
virtual DynAny_ptr get_dyn_any() = 0;
```

Returns a `DynAny` reference value from the `DynAny` object. `get_dyn_any()` is provided to deal with Any values that contain another any.

It is valid for you to use this method if the `TypeCode` contained in the `DynAny` is equivalent to the `TypeCode` of a `DynAny` or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent the `TypeCode` of a `DynAny`. The current position is unchanged after the call.

Exceptions

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_dyn_any()`

`DynAny::get_float()`

// C++

```
virtual CORBA::Float get_float() = 0;
```

Returns a Float value from the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_float` (a `float` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_float`. The current position is unchanged after the call.

Exceptions

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_float()`

`DynAny::get_long()`

// C++

```
virtual CORBA::Long get_long() = 0;
Returns a Long value from the DynAny object.
```

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_long` (a `long` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_long`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_long()`

`DynAny::get_longdouble()`

// C++

```
virtual CORBA::LongDouble get_longdouble() = 0;
```

Returns a `LongDouble` value from the `DynAny` object.

It is valid for you to use this method if the `TypeCode` contained in the `DynAny` is equivalent to `_tc_longdouble` (a `long double` `TypeCode`), or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent to `_tc_longdouble`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_longdouble()`

`DynAny::get_longlong()`

// C++

```
virtual CORBA::LongLong get_longlong() = 0;
```

Returns a `LongLong` value from the `DynAny` object.

It is valid for you to use this method if the `TypeCode` contained in the `DynAny` is equivalent to `_tc_longlong` (a `long long` `TypeCode`), or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent to `_tc_longlong`. The current position is unchanged after the call.

Exceptions

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_longlong()`

`DynAny::get_octet()`

// C++

```
virtual CORBA::Octet get_octet() = 0;
```

Returns an Octet value from the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_octet` (an `octet` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_octet`. The current position is unchanged after the call.

Exceptions

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_octet()`

`DynAny::get_reference()`

// C++

```
virtual CORBA::Object_ptr get_reference() = 0;
```

Returns an Object reference from the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_Object` (an object reference TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_Object`. The current position is unchanged after the call.

Exceptions

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_reference()`

`DynAny::get_short()`

// C++

```
virtual CORBA::Short get_short() = 0;
```

Returns a Short value from the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_short` (a `short` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_short`. The current position is unchanged after the call.

Exceptions

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_short()`

`DynAny::get_string()`

// C++

```
virtual char* get_string() = 0;
```

Returns a string value from the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_string` (a `string` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_string`. The current position is unchanged after the call.

Exceptions

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_string()`

`DynAny::get_typecode()`

// C++

```
virtual CORBA::TypeCode_ptr get_typecode() = 0;
```

Returns a `TypeCode` value from the `DynAny` object.

It is valid for you to use this method if the `TypeCode` contained in the `DynAny` is equivalent to `_tc_TypeCode` (a `TypeCode`), or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent to `_tc_TypeCode`. The current position is unchanged after the call.

Exceptions

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_typecode()`

`DynAny::get_ulong()`

// C++

```
virtual CORBA::ULong get_ulong() = 0;
```

Returns a `ULong` value from the `DynAny` object.

It is valid for you to use this method if the `TypeCode` contained in the `DynAny` is equivalent to `_tc_ulong` (an `unsigned long` `TypeCode`), or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent to `_tc_ulong`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_ulong()`

`DynAny::get_ulonglong()`

// C++

```
virtual CORBA::ULongLong get_ulonglong() = 0;
```

Returns a `ULongLong` value from the `DynAny` object.

It is valid for you to use this method if the `TypeCode` contained in the `DynAny` is equivalent to `_tc_ulonglong` (an `unsigned long long` `TypeCode`), or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent to `_tc_ulonglong`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_ulonglong()`

`DynAny::get_ushort()`

// C++

```
virtual CORBA::UShort get_ushort() = 0;
```

Returns a `UShort` `short` value from the `DynAny` object.

It is valid for you to use this method if the `TypeCode` contained in the `DynAny` is equivalent to `_tc_ushort` (an `unsigned short` `TypeCode`), or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent to `_tc_ushort`. The current position is unchanged after the call.

Exceptions

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_ushort()`

`DynAny::get_val()`

// C++

```
virtual CORBA::ValueBase* get_val() = 0;
```

Returns a value type value from the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to a value type TypeCode, or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to a value type TypeCode. The current position is unchanged after the call.

Exceptions

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_val()`

`DynAny::get_wchar()`

// C++

```
virtual CORBA::WChar get_wchar() = 0;
```

Returns a WChar value from the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_wchar` (a `wchar` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_wchar`. The current position is unchanged after the call.

Exceptions

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_wchar()`

`DynAny::get_wstring()`

// C++

```
virtual CORBA::WChar* get_wstring() = 0;
```

Returns a wide string value from the `DynAny` object.

It is valid for you to use this method if the `TypeCode` contained in the `DynAny` is equivalent to `_tc_wstring` (a wide string `TypeCode`), or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent to `_tc_wstring`. The current position is unchanged after the call.

Exceptions

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::insert_wstring()`

`DynAny::insert_any()`

// C++

```
virtual void insert_any(
    const CORBA::Any& value
) = 0;
```

Inserts an Any value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the `TypeCode` contained in the `DynAny` is equivalent to `_tc_any` (an `Any` `TypeCode`), or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent to `_tc_any`. The current position is unchanged after the call.

Exceptions

<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.
<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the inserted type.

See Also `DynamicAny::DynAny::get_any()`

`DynAny::insert_boolean()`

// C++

```
virtual void insert_boolean(
    CORBA::Boolean value
) = 0;
```

Inserts a Boolean value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the `TypeCode` contained in the `DynAny` is equivalent to `_tc_boolean` (a `boolean` `TypeCode`), or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent to `_tc_boolean`. The current position is unchanged after the call.

Exceptions

<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the inserted type.

See Also `DynamicAny::DynAny::get_boolean()`

`DynAny::insert_char()`

// C++

```
virtual void insert_char(
    CORBA::Char value
) = 0;
```

Inserts a Char value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_char` (a `char` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_char`. The current position is unchanged after the call.

Exceptions

InvalidValue	The <code>DynAny</code> has components and the current position is -1.
TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the inserted type.

See Also `DynamicAny::DynAny::get_char()`

`DynAny::insert_double()`

// C++

```
virtual void insert_double(
    CORBA::Double value
) = 0;
```

Inserts a Double value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_double` (a `double` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_double`. The current position is unchanged after the call.

Exceptions

<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.
<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the inserted type.

See Also `DynamicAny::DynAny::get_double()`

`DynAny::insert_dyn_any()`

// C++

```
virtual void insert_dyn_any(
    DynAny_ptr value
) = 0;
```

Inserts a `DynAny` value into the `DynAny` object. `insert_dyn_any()` is provided to deal with Any values that contain another `any`.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to the TypeCode of a `DynAny` or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent the TypeCode of a `DynAny`. The current position is unchanged after the call.

Exceptions

<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.
<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the inserted type.

See Also `DynamicAny::DynAny::get_dyn_any()`

`DynAny::insert_float()`

// C++

```
virtual void insert_float(
    CORBA::Float value
) = 0;
```

Inserts a Float value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_float` (a `float` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_float`. The current position is unchanged after the call.

Exceptions

<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.
<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the inserted type.

See Also `DynamicAny::DynAny::get_float()`

DynAny::insert_long()

// C++

```
virtual void insert_long(
    CORBA::Long value
) = 0;
```

Inserts a Long value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_long` (a `long` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_long`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::get_long()`

`DynAny::insert_longdouble()`

// C++

```
virtual void insert_longdouble(
    CORBA::LongDouble value
) = 0;
```

Inserts a LongDouble value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this function if the `TypeCode` contained in the `DynAny` is equivalent to `_tc_longdouble` (a `long double` `TypeCode`), or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent to `_tc_longdouble`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::get_longdouble()`

`DynAny::insert_long long()`

// C++

```
virtual void insert_longlong(
    CORBA::LongLong value
) = 0;
```

Inserts a `LongLong` value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the `TypeCode` contained in the `DynAny` is equivalent to `_tc_longlong` (a `long long` `TypeCode`), or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent to `_tc_longlong`. The current position is unchanged after the call.

Exceptions

<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the inserted type.

See Also `DynamicAny::DynAny::get_longlong()`

`DynAny::insert_octet()`

// C++

```
virtual void insert_octet(
    CORBA::Octet value
) = 0;
```

Inserts an Octet value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_octet` (an `octet` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_octet`. The current position is unchanged after the call.

Exceptions

TypeMismatch	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
InvalidValue	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::get_octet()`

`DynAny::insert_reference()`

// C++

```
virtual void insert_reference(
    CORBA::Object_ptr value
) = 0;
```

Inserts an Object reference into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_Object` (an object reference TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_Object`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::get_reference()`

`DynAny::insert_short()`

// C++

```
virtual void insert_short(
    CORBA::Short value
) = 0;
```

Inserts a Short value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_short` (a `short` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_short`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::get_short()`

`DynAny::insert_string()`

// C++

```
virtual void insert_string(
    const char* value
) = 0;
```

Inserts a string into the `DynAny` object.

Parameters

`value`

The value to insert into the `DynAny` object.

You can insert both bounded and unbounded strings using `insert_string()`.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_string` (a `string` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_string`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the inserted type.

<code>InvalidValue</code>	- The <code>DynAny</code> has components and the current position is -1.
<code>ue</code>	- The string inserted is longer than the bound of a bounded string.

See Also `DynamicAny::DynAny::get_string()`

`DynAny::insert_typecode()`

// C++

```
virtual void insert_typecode(
    ::CORBA::TypeCode_ptr value
) = 0;
```

Inserts a `TypeCode` value into the `DynAny` object.

Parameters

`value`

The value to insert into the `DynAny` object.

It is valid for you to use this method if the `TypeCode` contained in the `DynAny` is equivalent to `_tc_TypeCode` (a `TypeCode`), or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent to `_tc_TypeCode`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.
<code>ue</code>	

See Also `DynamicAny::DynAny::get_typecode()`

`DynAny::insert_ulong()`

// C++

```
virtual void insert_ulong(
    CORBA::ULong value
) = 0;
```

Inserts a ULong value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_ulong` (an `unsigned long` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_ulong`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::get_ulong()`

`DynAny::insert_ulonglong()`

// C++

```
virtual void insert_ulonglong(
    CORBA::ULongLong value
) = 0;
```

Inserts a ULongLong value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_ulonglong` (an `unsigned long long` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_ulonglong`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::get_ulonglong()`

`DynAny::insert_ushort()`

// C++

```
virtual void insert_ushort(
    CORBA::UShort value
) = 0;
```

Inserts a UShort value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_ushort` (an `unsigned short` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_ushort`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	

<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::get_ushort()`

`DynAny::insert_val()`

// C++

```
virtual void insert_val(
    CORBA::ValueBase* value
) = 0;
```

Inserts a value type value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the `TypeCode` contained in the `DynAny` is equivalent to a value type `TypeCode`, or, if the `TypeCode` at the current position (a `DynAny` objects with components) is equivalent to a value type `TypeCode`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::get_val()`

`DynAny::insert_wchar()`

// C++

```
virtual void insert_wchar(
    CORBA::WChar value
) = 0;
```

Inserts a WChar value into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_wchar` (a wide character TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_wchar`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the requested type.
<code>InvalidValue</code>	The <code>DynAny</code> has components and the current position is -1.

See Also `DynamicAny::DynAny::get_wchar()`

`DynAny::insert_wstring()`

// C++

```
virtual void insert_wstring(
    const CORBA::WChar* value
) = 0;
```

Inserts a wide string into the `DynAny` object.

Parameters

value

The value to insert into the `DynAny` object.

You can insert both bounded and unbounded strings using `insert_wstring()`.

It is valid for you to use this method if the TypeCode contained in the `DynAny` is equivalent to `_tc_wstring` (a wide `string` TypeCode), or, if the TypeCode at the current position (a `DynAny` objects with components) is equivalent to `_tc_wstring`. The current position is unchanged after the call.

Exceptions

<code>TypeMismatch</code>	The accessed component in the <code>DynAny</code> is of a type that is not equivalent to the inserted type.
<code>InvalidValue</code>	- The <code>DynAny</code> has components and the current position is -1. - The string inserted is longer than the bound of a bounded string.

See Also `DynamicAny::DynAny::get_wstring()`

`DynAny::InvalidValue` User Exception

```
class IT_DYNANY_API InvalidValue: public CORBA::UserException {
```

```

public:
    InvalidValue();
    void operator=(
        const InvalidValue&
    );
    static InvalidValue* _downcast(
        CORBA::Exception* exc
    );
    static const InvalidValue* _downcast(
        const CORBA::Exception* exc
    );
    static InvalidValue* _narrow(
        CORBA::Exception* exc
    );
    static const InvalidValue* _narrow(
        const CORBA::Exception* exc
    );
    virtual void _raise() const;
    virtual CORBA::TypeCode_ptr _it_get_typecode() const;
    virtual CORBA::Exception* _it_copy() const;
    virtual void _it_insert(
        CORBA::Any& any,
        CORBA::Boolean consume
    );
    virtual ~InvalidValue();
};
static CORBA::TypeCode_ptr _tc_InvalidValue;

```

A user exception meaning that an invalid value has been used as a parameter.

See Also DynamicAny::DynAny::TypeMismatch

DynAny::next()

// C++

```
virtual CORBA::Boolean next() = 0;
```

Advances the current position to the next component of the `DynAny` object. Returns true if the resulting current position indicates a component, false otherwise. Invoking `next()` on a `DynAny` that has no components returns false. A false return value always sets the current position to -1.

See Also DynamicAny::DynAny::component_count()

```
DynamicAny::DynAny::current_component()
DynamicAny::DynAny::seek()
DynamicAny::DynAny::rewind()
```

```
DynAny::rewind()
// C++
```

```
virtual void rewind() = 0;
```

Sets the current position to the first component of the `DynAny` object. This is equivalent to calling `seek(0)`.

See Also `DynamicAny::DynAny::seek()`

```
DynAny::seek()
// C++
```

```
virtual CORBA::Boolean seek(
    CORBA::Long index
) = 0;
```

Sets the current position to a component of the `DynAny` object. The method returns true if the resulting current position indicates a component of the `DynAny` object and false if the position does not correspond to a component.

Parameters

```
index
```

The new index to set the current position to. An index can range from 0 to `n-1`. An index of zero corresponds to the first component.

Calling `seek` with a negative index is legal and sets the current position to -1 to indicate no component. The method returns false in this case.

Passing a non-negative index value for a `DynAny` that does not have a component at the corresponding position sets the current position to - 1 and returns false.

See Also `DynamicAny::DynAny::component_count()`

```
DynamicAny::DynAny::current_component()
DynamicAny::DynAny::rewind()
DynamicAny::DynAny::next()
```

DynAny::to_any()

// C++

```
virtual CORBA::Any* to_any() = 0;
```

Returns an Any value created from a `DynAny` object. A copy of the TypeCode associated with the `DynAny` object is assigned to the resulting any. The value associated with the `DynAny` object is copied into the Any value.

See Also DynamicAny::DynAny::from_any()

DynAny::type()

// C++

```
virtual CORBA::TypeCode_ptr type() = 0;
```

Returns the TypeCode associated with a `DynAny` object.

A `DynAny` object is created with a TypeCode value assigned to it. This value determines the type of the value handled through the `DynAny` object. `type()` returns the TypeCode associated with a `DynAny` object.

Note that the TypeCode associated with a `DynAny` object is initialized at the time the `DynAny` is created and cannot be changed during the lifetime of the `DynAny` object.

DynAny::TypeMismatch User Exception

```

class IT_DYNANY_API TypeMismatch: public CORBA::UserException {
public:
    TypeMismatch();
    void operator=(
        const TypeMismatch&
    );
    static TypeMismatch* _downcast(
        CORBA::Exception* exc
    );
    static const TypeMismatch* _downcast(
        const CORBA::Exception* exc
    );
    static TypeMismatch* _narrow(
        CORBA::Exception* exc
    );
    static const TypeMismatch* _narrow(
        const CORBA::Exception* exc
    );
    virtual void _raise() const;
    virtual CORBA::TypeCode_ptr _it_get_typecode() const;
    virtual CORBA::Exception* _it_copy() const;
    virtual void _it_insert(
        CORBA::Any& any,
        CORBA::Boolean consume
    );
    virtual ~TypeMismatch();
};
static CORBA::TypeCode_ptr _tc_TypeMismatch;

```

A user exception meaning that the type of a parameter does not match the type of the target.

This exception is also raised when attempts are made to access `DynAny` components illegally. For example:

- If an attempt is made to access an object's component but the type of object does not have components.
- If an attempt is made to call an `insert_type()` or `get_type()` method on a `DynAny` object whose current component itself has components.

See Also `DynamicAny::DynAny::InvalidValue`

DynamicAny::DynAnyFactory Class

You can create DynAny objects by invoking operations on the `DynAnyFactory` object. You obtain a reference to the `DynAnyFactory` object by calling `CORBA::ORB::resolve_initial_references()` with the identifier parameter set to "`DynAnyFactory`".

A typical first step in dynamic interpretation of an Any involves creating a DynAny object using or `create_dyn_any_from_type_code()`. Then, depending on the type of the Any, you narrow the resulting DynAny object reference to one of the following complex types of object references:

```
DynFixed  
DynStruct  
DynSequence  
DynArray  
DynUnion  
DynEnum  
DynValue
```

Finally, you can use `DynAny::to_any()` (which each of these classes inherits from the DynAny class) to create an Any value from the constructed DynAny.

Exceptions `MARSHAL` : an attempt is made to exported references to `DynAnyFactory` objects to other processes or if an attempt is made to externalized them with `ORB::object_to_string()`. `DynAnyFactory` objects are intended to be local to the process in which they are created and used.

```

// class is in namespace DynamicAny
class IT_DYNANY_API DynAnyFactory : public virtual CORBA::Object {
public:
    typedef DynamicAny::DynAnyFactory_ptr _ptr_type;
    typedef DynamicAny::DynAnyFactory_var _var_type;
    virtual [~DynAnyFactory()](#dynamicanydynanyfactory-class);
    static DynAnyFactory_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static DynAnyFactory_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static DynAnyFactory_ptr _duplicate(
        DynAnyFactory_ptr p
    );
    inline static DynAnyFactory_ptr _nil();
    class IT_DYNANY_API [InconsistentTypeCode](#dynamicanydynanyfactory-
class):
        public CORBA::UserException
        { ... }
        static CORBA::TypeCode_ptr _tc_InconsistentTypeCode;
        virtual DynAny_ptr [create_dyn_any](#dynamicanydynanyfactory-class)(
            const CORBA::Any& value
        ) = 0;
        virtual DynAny_ptr [create_dyn_any_from_type_code]
        (#dynamicanydynanyfactory-class)(
            ::CORBA::TypeCode_ptr type
        ) = 0;
        static const IT_FWString _it_fw_type_id;
};

```

for descriptions of the standard helper functions:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`DynAnyFactory::create_dyn_any()`

// C++

```
virtual DynAny_ptr create_dyn_any(
    const CORBA::Any& value
) = 0;
```

Returns a new DynAny object from an Any value.

Parameters

value

An Any value to use to set the DynAny object.

A copy of the TypeCode associated with the any value is assigned to the resulting DynAny object. The value associated with the DynAny object is a copy of the value in the original Any. The current position of the created DynAny object is set to zero if the passed value has components; otherwise, the current position is set to -1.

ExceptionsInconsistentTypeCode: the value has a TypeCode with a TCKind of `tk_Principal`, `tk_native`, or `tk_abstract_interface`.

See Also`DynamicAny::DynAnyFactory::create_dyn_any_from_type_code()`

`DynAnyFactory::create_dyn_any_from_type_code()`

// C++

```
virtual DynAny_ptr create_dyn_any_from_type_code(
    ::CORBA::TypeCode_ptr type
) = 0;
```

Returns a new DynAny object from a TypeCode value. Depending on the TypeCode, the created object may be of type DynAny, or one of its derived types, such as DynStruct. The returned reference can be narrowed to the derived type.

Parameters

type

A TypeCode value to use to set the DynAny object.

[Table 14](#) shows the initial default values set depending on the type created:

Table 14: Default Values When Using `create_dyn_any_from_type_code()`

Type	Default Value
Any values	An Any containing a TypeCode with a TCKind value of <code>tk_null</code> and no value.
Boolean	FALSE
<code>char</code>	zero
DynArray	The operation sets the current position to zero and recursively initializes elements to their default value.
DynEnum	The operation sets the current position to -1 and sets the value of the enumerator to the first enumerator value indicated by the TypeCode.
DynFixed	Operations set the current position to -1 and sets the value to zero.
DynSequence	The operation sets the current position to -1 and creates an empty sequence.
DynStruct	The operation sets the current position to -1 for empty exceptions and to zero for all other TypeCode values. The members (if any) are recursively initialized to their default values.
DynUnion	The operation sets the current position to zero. The discriminator value is set to a value consistent with the first named member of the union. That member is activated and recursively initialized to its default value.
DynValue	The members are initialized as for a DynStruct.
numeric types	zero
object references	nil
<code>octet</code>	zero
string	the empty string
TypeCode	A TypeCode with a TCKind value of <code>tk_null</code>
<code>wchar</code>	zero
<code>wstring</code>	the empty string

Exceptions
InconsistentTypeCode: the TypeCode has a TCKind of `tk_Principal`, `tk_native`, or `tk_abstract_interface`.

See AlsoDynamicAny::DynAnyFactory::create_dyn_any()

DynAnyFactory::~~DynAnyFactory() Destructor

// C++

```
virtual ~DynAnyFactory();
```

Destroys the `DynAnyFactory` object.

See AlsoCORBA::ORB::resolve_initial_references()

```
CORBA::ORB::list_initial_services()
```

DynAnyFactory::InconsistentTypeCode User Exception Class

// C++

```

class IT_DYNANY_API InconsistentTypeCode:
    public CORBA::UserException
{
public:
    InconsistentTypeCode();
    void operator=(
        const InconsistentTypeCode&
    );
    static InconsistentTypeCode* _downcast(
        CORBA::Exception* exc
    );
    static const InconsistentTypeCode* _downcast(
        const CORBA::Exception* exc
    );
    static InconsistentTypeCode* _narrow(
        CORBA::Exception* exc
    );
    static const InconsistentTypeCode* _narrow(
        const CORBA::Exception* exc
    );
    virtual void _raise() const;
    virtual CORBA::TypeCode_ptr _it_get_typecode() const;
    virtual CORBA::Exception* _it_copy() const;
    virtual void _it_insert(
        CORBA::Any& any,
        CORBA::Boolean consume
    );
    virtual ~InconsistentTypeCode();
};
static CORBA::TypeCode_ptr _tc_InconsistentTypeCode;

```

A user exception meaning that a parameter has an inconsistent TypeCode compared to the object.

DynamicAny::DynArray Class

`DynArray` objects let you dynamically manipulate Any values as arrays. The following methods let you get and set array elements:

```
[get_elements()](#dynamicanydynarray-class)
[set_elements()](#dynamicanydynarray-class)
[get_elements_as_dyn_any()](#dynamicanydynarray-class)
[set_elements_as_dyn_any()](#dynamicanydynarray-class)
```

This class inherits from the `DynAny` class. Use `component_count()` to get the dimension of the array. Use the iteration methods such as `seek()` to access portions of the array.

```
// C++ class is in namespace DynamicAny
class IT_DYNANY_API DynArray : public virtual DynAny {
public:
    typedef DynamicAny::DynArray_ptr _ptr_type;
    typedef DynamicAny::DynArray_var _var_type;
    virtual [~DynArray()](#dynamicanydynarray-class);
    static DynArray_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static DynArray_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static DynArray_ptr _duplicate(
        DynArray_ptr p
    );
    inline static DynArray_ptr _nil();
    virtual AnySeq* [get_elements()](#dynamicanydynarray-class) = 0;
    virtual void [set_elements](#dynamicanydynarray-class)(
        const AnySeq & value
    ) = 0;
    virtual DynAnySeq* [get_elements_as_dyn_any()](#dynamicanydynarray-class)
= 0;
    virtual void [set_elements_as_dyn_any](#dynamicanydynarray-class)(
        const DynAnySeq & value
    ) = 0;
    static const IT_FWString _it_fw_type_id;
};
```

See Also DynamicAny::DynAny

for descriptions of the standard helper functions:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

DynArray::~DynArray() Destructor

// C++

```
virtual ~DynArray();
```

The destructor for a `DynArray` object.

```
DynArray::get_elements()
```

```
// C++
```

```
virtual AnySeq* get_elements() = 0;
```

Returns a sequence of Any values containing the elements of the array.

See Also `DynamicAny::DynArray::set_elements()`

```
DynamicAny::DynArray::get_elements_as_dyn_any()
DynamicAny::DynAny::component_count()
```

```
DynArray::get_elements_as_dyn_any()
```

```
// C++
```

```
virtual DynAnySeq* get_elements_as_dyn_any() = 0;
```

Returns a sequence of DynAny objects that describes each member in the array.

Use this method instead of [get_elements\(\)](#) if you want to avoid converting DynAny objects to Any objects when your application needs to handle `DynArray` objects extensively.

See Also `DynamicAny::DynArray::get_elements()`

```
DynamicAny::DynArray::set_elements_as_dyn_any()
DynamicAny::DynAny::component_count()
```

```
DynArray::set_elements()
```

```
// C++
```

```
virtual void set_elements(
    const AnySeq & value
) = 0;
```

Sets the array values with a sequence of Any values.

Parameters

value

A sequence of Any values containing the elements for the array.

This method sets the current position to -1 if the sequence has a zero length and it sets it to 0 otherwise.

Exceptions `TypeMismatch` is raised if an inconsistent value is passed in the sequence.

`InvalidValue` is raised if the sequence length does not match the array length.

See Also `DynamicAny::DynArray::get_elements()`

```
DynamicAny::DynArray::set_elements_as_dyn_any()
DynamicAny::DynAny::component_count()
```

`DynArray::set_elements_as_dyn_any()`

// C++

```
virtual void set_elements_as_dyn_any(
    const DynAnySeq & value
) = 0;
```

Initializes the array data associated with a `DynArray` object from a sequence of `DynAny` objects. Use this method instead of `set_elements()` if you want to avoid converting `DynAny` objects to `Any` objects when your application needs to handle `DynArray` objects extensively.

Parameters

value

A sequence of `DynAny` objects representing the array elements.

This method sets the current position to -1 if the sequence has a zero length and it sets it to 0 otherwise.

Exceptions `TypeMismatch` is raised if an inconsistent value is passed in the sequence.

`InvalidValue` is raised if the sequence length does not match the array length.

See Also `DynamicAny::DynArray::get_elements_as_dyn_any()`

```
DynamicAny::DynArray::set_elements()  
DynamicAny::DynAny::component_count()
```


DynamicAny::DynEnum Class

A `DynEnum` object lets you dynamically manipulate an Any value as an enumerated value. The key methods allow you to get and set a value as an IDL identifier string or you can manipulate the number that the enumerated value represents:

```
[get_as_string()](#dynamicanydynenum-class)
[set_as_string()](#dynamicanydynenum-class)
[get_as_ulong()](#dynamicanydynenum-class)
[set_as_ulong()](#dynamicanydynenum-class)
```

This class inherits from the `DynAny` class. The current position of a `DynEnum` is always -1 because it can only be one value at a given time.

```
// C++ class is in namespace DynamicAny
class IT_DYNANY_API DynEnum : public virtual DynAny {
public:
    typedef DynamicAny::DynEnum_ptr _ptr_type;
    typedef DynamicAny::DynEnum_var _var_type;
    virtual [~DynEnum()](#dynamicanydynenum-class);
    static DynEnum_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static DynEnum_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static DynEnum_ptr _duplicate(
        DynEnum_ptr p
    );
    inline static DynEnum_ptr _nil();
    virtual char* [get_as_string()](#dynamicanydynenum-class) = 0;
    virtual void [set_as_string](#dynamicanydynenum-class)(
        const char* value
    ) = 0;
    virtual CORBA::ULong [get_as_ulong()](#dynamicanydynenum-class) = 0;
    virtual void [set_as_ulong](#dynamicanydynenum-class)(
        CORBA::ULong value
    ) = 0;
    static const IT_FWString _it_fw_type_id;
};
```

See Also `DynamicAny::DynAny`

for descriptions of the standard helper functions:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`DynEnum::~~DynEnum()` Destructor

`virtual ~DynEnum();`

The destructor for a `DynEnum` object.

`DynEnum::get_as_string()`

// C++

```
virtual char* get_as_string() = 0;
```

Returns a string for the `DynEnum` that represents the IDL enumeration identifier.

See Also `DynamicAny::DynEnum::set_as_string()`

```
DynamicAny::DynEnum::get_as_ulong()
```

```
DynEnum::get_as_ulong()
```

```
// C++
```

```
virtual CORBA::ULong get_as_ulong() = 0;
```

Returns a number for the `DynEnum` that represents the enumerated ordinal value. Enumerators have ordinal values of 0 to `n-1`, as they appear from left to right in the corresponding IDL definition.

See Also `DynamicAny::DynEnum::set_as_ulong()`

```
DynamicAny::DynEnum::get_as_string()
```

```
DynEnum::set_as_string()
```

```
// C++
```

```
virtual void set_as_string(
    const char* value
) = 0;
```

Sets the enumerated identifier string value for the `DynEnum`.

Parameters

```
value
```

The identifier string to set the enumerated value to.

Exceptions

InvalidValue

The `value` string is not a valid IDL identifier for the corresponding IDL enumerated type.

See Also `DynamicAny::DynEnum::get_as_string()`

```
DynamicAny::DynEnum::set_as_ulong( )
```

```
DynEnum::set_as_ulong()
```

```
void set_as_ulong(
```

```
    int value
) throws org.omg.DynamicAny.DynAnyPackage.InvalidValue;
```

```
virtual void set_as_ulong(
```

```
    CORBA::ULong value
) = 0;
```

Sets the numerical value for the `DynEnum` that represents the enumerated ordinal value.

Parameters

`value`

The number to set the enumerated value to.

Exceptions

InvalidValue

The `value` is outside the range of ordinal values for the corresponding IDL enumerated type.

See Also `DynamicAny::DynEnum::get_as_ulong()`

```
DynamicAny::DynEnum::set_as_string( )
```

DynamicAny::DynFixed Class

A `DynFixed` object lets you dynamically manipulate an Any value as a fixed point value. This class inherits from the `DynAny` class. The key methods include [get_value\(\)](#) and [set_value\(\)](#).

These methods use strings to represent fixed-point values. A fixed-point format consists of an integer part of digits, a decimal point, a fraction part of digits, and a d or D. Examples include:

```
1.2d
35.98D
456.32
.467
```

Either the integer part or the fraction part (but not both) may be missing. The decimal point is not required for whole numbers. The `d` or `D` are optional. leading or trailing white space is allowed.

```
// C++ class is in namespace DynamicAny
class IT_DYNANY_API DynFixed : public virtual DynAny {
public:
    typedef DynamicAny::DynFixed_ptr _ptr_type;
    typedef DynamicAny::DynFixed_var _var_type;
    virtual [~DynFixed()](#dynamicanydynfixed-class);
    static DynFixed_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static DynFixed_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static DynFixed_ptr _duplicate(
        DynFixed_ptr p
    );
    inline static DynFixed_ptr _nil();
    virtual char* [get_value()](#dynamicanydynfixed-class) = 0;
    virtual CORBA::Boolean [set_value](#dynamicanydynfixed-class)(
        const char* val
    ) = 0;
    static const IT_FWString _it_fw_type_id;
};
```

See Also `DynamicAny::DynAny`

for descriptions of the standard helper functions:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`DynFixed::~~DynFixed()` Destructor

// C++

```
virtual ~DynFixed();
```

The destructor for a `DynFixed` object.

`DynFixed::get_value()`

// C++

```
virtual char* get_value() = 0;
```

Returns a string representing the fixed value of the `DynFixed` object.

See Also `DynamicAny::DynFixed::set_value()`

`DynFixed::set_value()`

// C++

```
virtual CORBA::Boolean set_value(
    const char* val
) = 0;
```

Sets the value of the `DynFixed`. The method returns true if `val` can be represented as the `DynFixed` without loss of precision. If `val` has more fractional digits than can be represented in the `DynFixed`, the fractional digits are truncated and the method returns false.

Parameters

`val`

A string containing the fixed point value to be set in the `DynFixed`. The string must contain a fixed string constant in the same format as would be used for IDL fixed-point literals. However, the trailing `d` or `D` is optional.

Exceptions

<code>InvalidValue</code>	<code>val</code> contains a value whose scale exceeds that of the <code>DynFixed</code> or is not initialized.
<code>TypeMismatch</code>	<code>val</code> does not contain a valid fixed-point literal or contains extraneous characters other than leading or trailing white space.

See Also `DynamicAny::DynFixed::get_value()`

DynamicAny::DynSequence Class

`DynSequence` objects let you dynamically manipulate Any values as sequences. The key methods allow you to manage the sequence length and get and set sequence elements:

```
[get_length()](#dynamicanydynsequence-class)
[set_length()](#dynamicanydynsequence-class)
[get_elements()](#dynamicanydynarray-class)
[set_elements()](#dynamicanydynarray-class)
[get_elements_as_dyn_any()](#dynamicanydynarray-class)
[set_elements_as_dyn_any()](#dynamicanydynarray-class)
```

This class inherits from the `DynAny` class.


```

// C++ class is in namespace DynamicAny
class IT_DYNANY_API DynSequence : public virtual DynAny {
public:
    typedef DynamicAny::DynSequence_ptr _ptr_type;
    typedef DynamicAny::DynSequence_var _var_type;
    virtual [~DynSequence()](#dynamicanydynsequence-class);
    static DynSequence_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static DynSequence_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static DynSequence_ptr _duplicate(
        DynSequence_ptr p
    );
    inline static DynSequence_ptr _nil();
    virtual CORBA::ULong [get_length()](#dynamicanydynsequence-class) = 0;
    virtual void [set_length](#dynamicanydynsequence-class)(
        CORBA::ULong len
    ) = 0;
    virtual AnySeq* [get_elements()](#dynamicanydynarray-class) = 0;
    virtual void [set_elements](#dynamicanydynarray-class)(
        const AnySeq & value
    ) = 0;
    virtual DynAnySeq* [get_elements_as_dyn_any()](#dynamicanydynarray-class)
= 0;
    virtual void [set_elements_as_dyn_any](#dynamicanydynarray-class)(
        const DynAnySeq & value
    ) = 0;
    static const IT_FWString _it_fw_type_id;
};

```

See Also DynamicAny::DynAny

for descriptions of the standard helper functions:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

DynSequence::~DynSequence()

virtual ~DynSequence();

The destructor for a `DynSequence` object.

`DynSequence::~get_elements()`

`virtual AnySeq* get_elements() = 0;`

Returns a sequence of Any values containing the elements of the sequence.

See Also `DynamicAny::DynSequence::set_elements()`

```
DynamicAny::DynSequence::get_elements_as_dyn_any()
```

`DynSequence::get_elements_as_dyn_any()`

`virtual DynAnySeq* get_elements_as_dyn_any() = 0;`

Returns a sequence of DynAny objects that describes each member in the sequence.

Use this method instead of [get_elements\(\)](#) if you want to avoid converting DynAny objects to Any objects when your application needs to handle `DynSequence` objects extensively.

See Also `DynamicAny::DynSequence::get_elements()`

```
DynamicAny::DynSequence::get_elements_as_dyn_any()
```

`DynSequence::get_length()`

`virtual CORBA::ULong get_length() = 0;`

Returns the number of elements in the sequence.

See Also `DynamicAny::DynSequence::set_length()`

```
DynamicAny::DynSequence::get_elements()
```

`DynSequence::set_elements()`

`virtual void set_elements(`

```
    const AnySeq & value
) = 0;
```

Sets the sequence values.

Parameters

value

A sequence of Any values containing the elements for the sequence.

This method sets the current position to -1 if the sequence has a zero length and it sets it to 0 otherwise.

Exceptions

<code>Invalidvalue</code>	The parameter's length is greater than the <code>DynSequence</code> length.
<code>TypeMismatch</code>	an inconsistent value is passed in. This can happen if: - The element type codes between the <code>DynSequence</code> and the parameter do not agree. - The <code>DynSequence</code> is a bounded sequence and the number of elements in the parameter are greater than the bound allows.

See Also `DynamicAny::DynSequence::get_elements()`

```
DynamicAny::DynSequence::set_elements_as_dyn_any( )
DynamicAny::DynSequence::get_length( )
DynamicAny::DynSequence::set_length( )
```

`DynSequence::set_elements_as_dyn_any()`

virtual void set_elements_as_dyn_any(

```
    const DynAnySeq & value
) = 0;
```

Initializes the sequence data associated with a `DynSequence` object from a sequence of `DynAny` objects. Use this method instead of `set_elements()` if you want to avoid converting `DynAny` objects to `Any` objects when your application needs to handle `DynSequence` objects extensively.

Parameters

value

A sequence of DynAny objects to represent the elements of the `DynSequence`.

This method sets the current position to -1 if the sequence has a zero length and it sets it to 0 otherwise.

Exceptions

<code>Invalidvalue</code>	The parameter's length is greater than the <code>DynSequence</code> length.
<code>TypeMismatch</code>	An inconsistent value is passed in. This can happen if: - The element type codes between the <code>DynSequence</code> and the parameter do not agree. - The <code>DynSequence</code> is a bounded sequence and the number of elements in the parameter are greater than the bound allows.

See Also `DynamicAny::DynSequence::get_elements_as_dyn_any()`

```
DynamicAny::DynSequence::set_elements()
DynamicAny::DynSequence::get_length()
DynamicAny::DynSequence::set_length()
```

`DynSequence::set_length()`

`void set_length(`

```
    int len
) throws org.omg.DynamicAny.DynAnyPackage.InvalidValue;
```

`virtual void set_length(`

```
    CORBA::ULong len
) = 0;
```

Sets the length of the sequence.

Parameters

`len`

The length desired for the sequence.

Increasing the length adds new (default-initialized) elements to the end of the sequence without affecting existing elements in the sequence. The new current position is set to the first new element if the previous current position was -1. The new current position remains the same as the old one if the previous current position indicates a valid element (was anything but -1).

Decreasing the length removes elements from the end of the sequence without affecting the rest of the elements. The new current position is as follows:

- If the previous current position indicates a valid element and that element is not removed, the new current position remains the same.
- If the previous current position indicates a valid element and that element is removed, the new current position is set to -1.
- If the sequence length is set to 0, the new current position is set to -1.
- If the previous current position was -1, the new current position remains -1.

Exceptions

`InvalidValue`

An attempt is made to increase the length of a bounded sequence to a value greater than the bound.

See Also `DynamicAny::DynSequence::get_length()`

`DynamicAny::DynSequence::set_elements()`

DynamicAny::DynStruct Class

You use `DynStruct` objects for dynamically handling structures and exceptions in Any values. This class inherits from the `DynAny` class. Key methods allow you to set and get the structure (or exception) as a sequence of name-value pairs:

```
[get_members()](#dynamicanydynvalue-class)
[set_members()](#dynamicanydynvalue-class)
[get_members_as_dyn_any()](#dynamicanydynvalue-class)
[set_members_as_dyn_any()](#dynamicanydynvalue-class)
```

Use the `DynAny` iteration methods such as `seek()` to set the current position to a member of the structure. You can also obtain the name and kind of `TypeCode` for a member at the current position:

```
// C++ class is in namespace DynamicAny
class IT_DYNANY_API DynStruct : public virtual DynAny {
public:
    typedef DynamicAny::DynStruct_ptr _ptr_type;
    typedef DynamicAny::DynStruct_var _var_type;
    virtual [~DynStruct()](#dynamicanydynstruct-class);
    static DynStruct_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static DynStruct_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static DynStruct_ptr _duplicate(
        DynStruct_ptr p
    );
    inline static DynStruct_ptr _nil();
    virtual FieldName = 0;
    virtual ::CORBA::TCKind = 0;
    virtual NameValuePairSeq* [get_members()](#dynamicanydynvalue-class) = 0;
    virtual void [set_members](#dynamicanydynvalue-class)(
        const NameValuePairSeq & value
    ) = 0;
    virtual NameDynAnyPairSeq* [get_members_as_dyn_any()](
        #dynamicanydynvalue-class) = 0;
    virtual void [set_members_as_dyn_any](#dynamicanydynvalue-class)(
        const NameDynAnyPairSeq & value
    ) = 0;
    static const IT_FWString _it_fw_type_id;
};
```

See Also DynamicAny::DynAny

for descriptions of the standard helper functions:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`DynStruct::current_member_kind()`

`virtual ::CORBA::TCKind current_member_kind() = 0;`

Returns the kind of TypeCode associated with the current position.

Exceptions

TypeMismatch	The DynStruct object represents an empty exception.
InvalidValue	The current position does not indicate a member.

See AlsoDynamicAny::DynAny::seek()

```
DynamicAny::DynStruct::current_member_name()
```

DynStruct::current_member_name()

virtual FieldName current_member_name() = 0;

Returns the name of the member at the current position. This method can return an empty value since the TypeCode of the value being manipulated may not contain the names of members.

Exceptions

TypeMismatch	DynStruct object represents an empty exception.
InvalidValue	The current position does not indicate a member.

See AlsoDynamicAny::DynAny::seek()

```
DynamicAny::DynStruct::current_member_kind()
```

DynStruct::~~DynStruct()

virtual ~DynStruct();

The destructor of a DynStruct object.

DynStruct::get_members()

virtual NameValuePairSeq* get_members() = 0;

Returns a sequence of members that describes the name and the value of each member in the structure (or exception) associated with a DynStruct object.

The sequence order is the same as the declaration order of members as indicated by the TypeCode of the DynStruct. The current position is not affected. The member names in the returned sequence will be empty strings if the TypeCode of the DynStruct does not contain member names.

See AlsoDynamicAny::DynStruct::set_members()


```
DynamicAny::DynStruct::get_members_as_dyn_any()
```

```
DynStruct::get_members_as_dyn_any()
```

```
virtual NameDynAnyPairSeq* get_members_as_dyn_any() = 0;
```

Returns a sequence of name-DynAny pairs that describes each member in the structure (or exception) associated with a DynStruct object. Use this method instead of [get_members\(\)](#) if you want to avoid converting DynAny objects to `any` objects when your application needs to handle `DynStruct` objects extensively.

The sequence order is the same as the declaration order of members as indicated by the TypeCode of the `DynStruct`. The current position is not affected. The member names in the returned sequence will be empty strings if the TypeCode of the `DynStruct` does not contain member names.

See Also `DynamicAny::DynStruct::set_members_as_dyn_any()`

```
DynamicAny::DynStruct::get_members()
```

```
DynStruct::set_members()
```

```
virtual void set_members()
```

```
    const NameValuePairSeq & value  
) = 0;
```

Initializes the structure data associated with a `DynStruct` object from a sequence of name-value pairs.

Parameters

```
value
```

A sequence of name-value pairs representing member names and the values of the members.

The current position is set to zero if the sequence passed in has a non-zero length. The current position is set to -1 if an empty sequence is passed in.

Members in the sequence must follow these rules:

- Members must be in the order in which they appear in the IDL specification of the structure.
- If member names are supplied in the sequence, they must either match the corresponding member name in the TypeCode of the `DynStruct` or they must be empty strings.

- Members must be supplied in the same order as indicated by the TypeCode of the `DynStruct`. The method does not reassign member values based on member names.

Exceptions

<code>InvalidValue</code>	The sequence has a number of elements that disagrees with the number of members as indicated by the TypeCode of the <code>DynStruct</code> .
<code>TypeMismatch</code>	Raised if: - One or more sequence elements have a type that is not equivalent to the TypeCode of the corresponding member. - The member names do not match the corresponding member name in the TypeCode of the <code>DynStruct</code>.

See Also `DynamicAny::DynStruct::get_members()`

```
DynamicAny::DynStruct::set_members_as_dyn_any()
DynamicAny::NameValuePairSeq
```

`DynStruct::set_members_as_dyn_any()`

virtual void set_members_as_dyn_any(

```
    const NameDynAnyPairSeq & value
) = 0;
```

Initializes the structure data associated with a `DynStruct` object from a sequence of name-DynAny pairs. Use this method instead of `set_members()` if you want to avoid converting `DynAny` objects to `any` objects when your application needs to handle `DynStruct` objects extensively.

Parameters

value

A sequence of name-`DynAny` pairs representing member names and the values of the members as `DynAny` objects.

The current position is set to zero if the sequence passed in has a non-zero length. The current position is set to -1 if an empty sequence is passed in.

Members in the sequence must follow these rules:

- Members must be in the order in which they appear in the IDL specification of the structure.
- If member names are supplied in the sequence, they must either match the corresponding member name in the TypeCode of the `DynStruct` or they must be empty strings.
- Members must be supplied in the same order as indicated by the TypeCode of the `DynStruct`. The method does not reassign `DynAny` values based on member names.

Exceptions

<code>InvalidValue</code>	The sequence has a number of elements that disagrees with the number of members as indicated by the TypeCode of the <code>DynStruct</code> .
<code>TypeMismatch</code>	Raised if: - One or more sequence elements have a type that is not equivalent to the TypeCode of the corresponding member. - The member names do not match the corresponding member name in the TypeCode of the <code>DynStruct</code>.

See Also `DynamicAny::DynStruct::get_members_as_dyn_any()`

```
DynamicAny::DynStruct::set_members( )
DynamicAny::NameDynAnyPairSeq
```

DynamicAny::DynUnion Class

The `DynUnion` class lets you dynamically manage an Any value as a union value. This class inherits from the `DynAny` class. Key methods to manipulate a union include:

```
[has_no_active_member()](#dynamicanydynunion-class)
[member()](#dynamicanydynunion-class)
[member_kind()](#dynamicanydynunion-class)
[member_name()](#dynamicanydynunion-class)
```

Other methods are available to manipulate a union's discriminator:

```
[discriminator_kind()](#dynamicanydynunion-class)
get_discriminator()
[set_discriminator()](#dynamicanydynunion-class)
[set_to_default_member()](#dynamicanydynunion-class)
[set_to_no_active_member()](#dynamicanydynunion-class)
```

A union can have only two valid current positions: Zero denotes the discriminator and 1 denotes the active member.

The value returned by `DynAny::component_count()` for a union depends on the current discriminator: it is 2 for a union whose discriminator indicates a named member, and 1 otherwise.

```

class IT_DYNANY_API DynUnion : public virtual DynAny {
public:
    typedef DynamicAny::DynUnion_ptr _ptr_type;
    typedef DynamicAny::DynUnion_var _var_type;
    virtual [~DynUnion()](#dynamicanydynunion-class);
    static DynUnion_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static DynUnion_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static DynUnion_ptr _duplicate(
        DynUnion_ptr p
    );
    inline static DynUnion_ptr _nil();
    virtual DynAny_ptr [get_discriminator()](#dynamicanydynunion-class) = 0;
    virtual void [set_discriminator](#dynamicanydynunion-class)(
        DynAny_ptr d
    ) = 0;
    virtual void [set_to_default_member()](#dynamicanydynunion-class) = 0;
    virtual void [set_to_no_active_member()](#dynamicanydynunion-class) = 0;
    virtual CORBA::Boolean [has_no_active_member()](#dynamicanydynunion-
class) = 0;
    virtual ::CORBA::TCKind [discriminator_kind()](#dynamicanydynunion-class)
= 0;
    virtual DynAny_ptr [member()](#dynamicanydynunion-class) = 0;
    virtual FieldName [member_name()](#dynamicanydynunion-class) = 0;
    virtual ::CORBA::TCKind [member_kind()](#dynamicanydynunion-class) = 0;
    static const IT_FWString _it_fw_type_id;
};

```

See Also `DynamicAny::DynAny`

for descriptions of the standard helper functions:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`DynUnion::discriminator_kind()`

`virtual ::CORBA::TCKind discriminator_kind() = 0;`

Returns the kind of TypeCode of the union's discriminator.

See Also DynamicAny::DynUnion::get_discriminator()

```
DynamicAny::DynUnion::set_discriminator()
```

DynUnion::~~DynUnion()

virtual ~DynUnion();

The destructor for a `DynUnion` object.

DynUnion::get_discriminator()

virtual DynAny_ptr get_discriminator() = 0;

Returns the current discriminator value of the `DynUnion`.

See Also DynamicAny::DynUnion::set_discriminator()

```
DynamicAny::DynUnion::discriminator_kind()
```

DynUnion::has_no_active_member()

virtual CORBA::Boolean has_no_active_member() = 0;

Returns true if the union has no active member (that is, the union's value consists solely of its discriminator because the discriminator has a value that is not listed as an explicit case label). The method returns false if:

- The IDL union has a default case.
- The IDL union's explicit case labels use the entire range of discriminator values.

See Also DynamicAny::DynUnion::member()

```
DynamicAny::DynUnion::set_to_default_member()
```

```
DynamicAny::DynUnion::set_to_no_active_member()
```

DynUnion::member()

virtual DynAny_ptr member() = 0;

Returns the currently active member. Note that the returned reference remains valid only for as long as the currently active member does not change.

Parameters

<code>InvalidValue</code>	The union has no active member.

<code>OBJECT_NOT_EXIST</code>	The returned reference is used beyond the life time of the currently active member.

See Also `DynamicAny::DynUnion::member_kind()`

```
DynamicAny::DynUnion::member_name()
DynamicAny::DynUnion::has_no_active_member()
```

`DynUnion::member_kind()`

`virtual ::CORBA::TCKind member_kind() = 0;`

Returns the kind of TypeCode of the currently active member.

Exceptions

`InvalidValue`

The method is called on a union without an active member.

See Also `DynamicAny::DynUnion::member()`

```
DynamicAny::DynUnion::member_name()
```

`DynUnion::member_name()`

`virtual FieldName member_name() = 0;`

Returns the name of the currently active member. The method returns an empty string if the union's TypeCode does not contain a member name for the currently active member.

Exceptions

`InvalidValue`

The method is called on a union without an active member.

See Also `DynamicAny::DynUnion::member()`

```
DynamicAny::DynUnion::member_kind()
```

`DynUnion::set_discriminator()`

virtual void set_discriminator(

```
    DynAny_ptr d
) = 0;
```

Sets the discriminator of the `DynUnion`.

Parameters

d

The value to set the discriminator to. Setting the discriminator to a value that is consistent with the currently active union member does not affect the currently active member. Setting the discriminator to a value that is inconsistent with the currently active member deactivates the member and activates the member that is consistent with the new discriminator value (if there is a member for that value) by initializing the member to its default value.

Setting the discriminator of a union sets the current position to 0 if the discriminator value indicates a non-existent union member (The method [has_no_active_member\(\)](#) would return true in this case). Otherwise, if the discriminator value indicates a named union member, the current position is set to 1, [has_no_active_member\(\)](#) would return false, and `component_count()` would return 2 in this case.

Exceptions

TypeMismatch

The `TypeCode` of the parameter is not equivalent to the `TypeCode` of the union's discriminator.

See Also `DynamicAny::DynUnion::get_discriminator()`

```
DynamicAny::DynUnion::has_no_active_member()
DynamicAny::DynUnion::set_to_default_member()
DynamicAny::DynUnion::set_to_no_active_member()
```

`DynUnion::set_to_default_member()`

virtual void set_to_default_member() = 0;

Sets the discriminator to a value that is consistent with the value of the default case of a union.

This method sets the current position to zero and causes `component_count()` to return 2.

Exceptions

TypeMismatch

The method is called on a union without an explicit default case.

See Also DynamicAny::DynUnion::has_no_active_member()

```
DynamicAny::DynUnion::set_discriminator()
DynamicAny::DynUnion::set_to_no_active_member()
DynamicAny::DynUnion::set_to_no_active_member()
```

DynUnion::set_to_no_active_member()

virtual void set_to_no_active_member() = 0;

Sets the discriminator to a value that does not correspond to any of the union's case labels.

This method sets the current position to zero and causes DynAny::component_count() to return 1.

Exceptions

TypeMismatch

Raised if this method is called on a union that:

- Does not have an explicit default case.
- Uses the entire range of discriminator values for explicit case labels.

See Also DynamicAny::DynUnion::has_no_active_member()

```
DynamicAny::DynUnion::set_discriminator()
DynamicAny::DynUnion::set_to_default_member()
```

DynamicAny::DynValue Class

You use `DynValue` objects for dynamically handling value types in Any values. Value types are used for objects-by-value. This class inherits from the `DynAny` class. Key methods allow you to set and get the value type as a sequence of name-value pairs:

```
[get_members()](#dynamicanydynvalue-class)
[set_members()](#dynamicanydynvalue-class)
[get_members_as_dyn_any()](#dynamicanydynvalue-class)
[set_members_as_dyn_any()](#dynamicanydynvalue-class)
```

Use the `DynAny` iteration methods such as `seek()` to set the current position to a member of the value type. You can also obtain the name and kind of `TypeCode` for a member at the current position:

```
[current_member_name()](#dynamicanydynstruct-class)
[current_member_kind()](#dynamicanydynvalue-class)
```

The class is as follows:

```

// class is in namespace DynamicAny
class IT_DYNANY_API DynValue : public virtual DynAny {
public:
    typedef DynamicAny::DynValue_ptr _ptr_type;
    typedef DynamicAny::DynValue_var _var_type;
    virtual [~DynValue()](#dynamicanydynvalue-class);
    static DynValue_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static DynValue_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static DynValue_ptr _duplicate(
        DynValue_ptr p
    );
    inline static DynValue_ptr _nil();
    virtual FieldName [current_member_name()](#dynamicanydynstruct-class) =
0;
    virtual ::CORBA::TCKind [current_member_kind()](#dynamicanydynvalue-
class) = 0;
    virtual NameValuePairSeq* [get_members()](#dynamicanydynvalue-class) = 0;
    virtual void [set_members](#dynamicanydynvalue-class)(
        const NameValuePairSeq & values
    ) = 0;
    virtual NameDynAnyPairSeq* [get_members_as_dyn_any()]
(#dynamicanydynvalue-class) = 0;
    virtual void [set_members_as_dyn_any](#dynamicanydynvalue-class)(
        const NameDynAnyPairSeq & value
    ) = 0;
    static const IT_FWString _it_fw_type_id;
};

```

See Also DynamicAny::DynAny

for descriptions of the standard helper functions:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`DynValue::current_member_kind()`

`virtual ::CORBA::TCKind current_member_kind() = 0;`

Returns the kind of TypeCode associated with the current position.

Exceptions

TypeMismatch	The DynValue object represents an empty value type.
InvalidValue	The current position does not indicate a member.

See AlsoDynamicAny::DynAny::seek()

```
DynamicAny::DynValue::current_member_name()
```

```
virtual FieldName current_member_name() = 0;
```

Returns the name of the member at the current position. This method can return an empty value since the TypeCode of the value being manipulated may not contain the names of members.

Exceptions

TypeMismatch	The DynValue object represents an empty value type.
InvalidValue	The current position does not indicate a member.

See AlsoDynamicAny::DynAny::seek()

```
DynamicAny::DynValue::current_member_kind()
```

```
DynValue::~~DynValue()
```

```
virtual ~DynValue();
```

The destructor for a DynValue object.

```
DynValue::get_members()
```

```
virtual NameValuePairSeq* get_members() = 0;
```

Returns a sequence of members that describes the name and the value of each member in the DynValue object.

The sequence order is the same as the declaration order of members as indicated by the TypeCode of the DynValue. The current position is not affected. The member names in the returned sequence will be empty strings if the TypeCode of the DynValue does not contain member names.

See AlsoDynamicAny::DynValue::set_members()

```
DynamicAny::DynValue::get_members_as_dyn_any()
```

```
DynValue::get_members_as_dyn_any()
```

```
virtual NameDynAnyPairSeq* get_members_as_dyn_any() = 0;
```

Returns a sequence of name- `DynAny` pairs that describes each member in the value type associated with a `DynValue` object. Use this method instead of `get_members()` if you want to avoid converting `DynAny` objects to `Any` objects when your application needs to handle `DynValue` objects extensively.

The sequence order is the same as the declaration order of members as indicated by the `TypeCode` of the `DynValue`. The current position is not affected. The member names in the returned sequence will be empty strings if the `TypeCode` of the `DynValue` does not contain member names.

See Also `DynamicAny::DynValue::set_members_as_dyn_any()`

```
DynamicAny::DynValue::get_members()
```

```
DynValue::set_members()
```

```
virtual void set_members()
```

```
    const NameValuePairSeq & values  
) = 0;
```

Initializes the data value associated with a `DynValue` object from a sequence of name-value pairs.

Parameters

```
values
```

A sequence of name-value pairs representing member names and the values of the members.

The current position is set to zero if the sequence passed in has a non-zero length. The current position is set to -1 if an empty sequence is passed in.

Members in the sequence must follow these rules:

- Members must be in the order in which they appear in the IDL specification.
- If member names are supplied in the sequence, they must either match the corresponding member name in the `TypeCode` of the `DynValue` or they must be empty strings.

- Members must be supplied in the same order as indicated by the TypeCode of the `DynValue`. The method does not reassign member values based on member names.

Exceptions

<code>InvalidValue</code>	The sequence has a number of elements that disagrees with the number of members as indicated by the TypeCode of the <code>DynValue</code> .
<code>TypeMismatch</code>	Raised if: - One or more sequence elements have a type that is not equivalent to the TypeCode of the corresponding member. - The member names do not match the corresponding member name in the TypeCode of the <code>DynValue</code>.

See Also `DynamicAny::DynValue::get_members()`

```
DynamicAny::DynValue::set_members_as_dyn_any( )
DynamicAny::NameValuePairSeq
```

```
DynValue::set_members_as_dyn_any()
virtual void set_members_as_dyn_any(
```

```
    const NameDynAnyPairSeq & value
) = 0;
```

Initializes the data value associated with a `DynValue` object from a sequence of name-`DynAny` pairs. Use this method instead of `set_members()` if you want to avoid converting `DynAny` objects to `any` objects when your application needs to handle `DynValue` objects extensively.

Parameters

`value`

A sequence of name-`DynAny` pairs representing member names and the values of the members as `DynAny` objects.

The current position is set to zero if the sequence passed in has a non-zero length. The current position is set to -1 if an empty sequence is passed in.

Members in the sequence must follow these rules:

- Members must be in the order in which they appear in the IDL specification of the structure.
- If member names are supplied in the sequence, they must either match the corresponding member name in the TypeCode of the `DynValue` or they must be empty strings.
- Members must be supplied in the same order as indicated by the TypeCode of the `DynValue`. The method does not reassign DynAny values based on member names.

Exceptions

<code>InvalidValue</code>	The sequence has a number of elements that disagrees with the number of members as indicated by the TypeCode of the <code>DynValue</code> .
<code>TypeMismatch</code>	Raised if: - One or more sequence elements have a type that is not equivalent to the TypeCode of the corresponding member. - The member names do not match the corresponding member name in the TypeCode of the <code>DynValue</code>.

See Also `DynamicAny::DynValue::get_members_as_dyn_any()`

```
DynamicAny::DynValue::set_members( )
DynamicAny::NameDynAnyPairSeq
```

GSSUP Overview

The Generic Security Service username/password (GSSUP) IDL module defines the data types needed for the GSSUP mechanism. This reference page is an *extract* from the GSSUP module that includes only the data types needed for the `IT_CSI` module.

GSSUP::GSSUPMechOID

```
const CSI::StringOID GSSUPMechOID = "oid:2.23.130.1.1.1";
```

The GSS Object Identifier allocated for the username/password mechanism, which is defined as follows:

```
{ iso-itu-t (2) international-organization (23) omg (130)
  security (1) authentication (1) gssup-mechanism (1) }
```

See Also `IT_CSI::AuthenticationService::client_authentication_mech`

```
IT_CSI::AuthenticationServicePolicy::client_authentication_mech
```

GSSUP::ErrorCode

```
typedef unsigned long ErrorCode;
```

The error code type returned by GSSUP operations.

See Also `IT_CSI::AuthenticateGSSUPCredentials::authenticate()`

GSSUP::GSS_UP_S_G_UNSPECIFIED

```
const ErrorCode GSS_UP_S_G_UNSPECIFIED = 1;
```

An error code indicating that the context validator has chosen not to reveal the GSSUP-specific cause of the failure.

See Also `IT_CSI::AuthenticateGSSUPCredentials::authenticate()`

GSSUP::GSS_UP_S_G_NOUSER


```
const ErrorCode GSS_UP_S_G_NOUSER = 2;
```

An error code indicating that the user is unknown to the target.

See Also `IT_CSI::AuthenticateGSSUPCredentials::authenticate()`

GSSUP::GSS_UP_S_G_BAD_PASSWORD

```
const ErrorCode GSS_UP_S_G_BAD_PASSWORD = 3;
```

An error code indicating that the supplied password was incorrect.

See Also `IT_CSI::AuthenticateGSSUPCredentials::authenticate()`

GSSUP::GSS_UP_S_G_BAD_TARGET

```
const ErrorCode GSS_UP_S_G_BAD_TARGET = 4;
```

An error code indicating that the *target name*, by which is meant a security policy domain (CSIv2 authentication domain), does not match a security policy domain in the target.

See Also `IT_CSI::AuthenticateGSSUPCredentials::authenticate()`

IT_Buffer

The IT_Buffer Module

A proprietary implementation of a segmented buffer, for use in ART-based applications.

Description

ART Buffers are not expected to maintain storage in a contiguous region of memory. Instead Buffers are made up of Segments and, where appropriate, are optimized for bulk access to these Segments. Segments, in turn, each represent a subrange of the data contained in a Storage instance. Storage instances can be shared by multiple Buffer instances, allowing messages to be parsed without copying.

IT_Buffer::RawData

An IDL native type providing efficient access to a Buffer's data.

Description

The `RawData` type provides access to a contiguous subset of the bytes contained in a `Buffer`. It is an IDL native type that maps to the language specific type that provides the most efficient access for marshaling and demarshaling individual primitives as well as for accessing bulk data.

C++ implementation

In C++, `RawData` maps to `CORBA::Octet*`.

IT_Buffer::StorageSeq

A sequence of local IT_Buffer::Storage objects.

IT_Buffer::Storage

A contiguous region of bytes of which subranges can be contained in Buffers.

Description

The ART core provides a heap-based `Storage` implementation. Plug-ins may provide special purpose `Storage` implementations—for example, referencing shared memory.

Instances of `Storage` must be safe to access concurrently, because they might be contained as `Segment`s in multiple `Buffer`s.

C++ implementation

In C++, the `_add_ref()` and `_remove_ref()` reference counting functions are used to manage instances of `Storage` type, ensuring that memory is not leaked.

`IT_Buffer::Storage::data`

Provides access to the bytes in the `Storage` object.

`IT_Buffer::Storage::length`

The number of bytes in `IT_Buffer::Storage::data`.

`IT_Buffer::Storage::another()`

Obtain another `Storage` instance of the same implementation type, and sharing any other relevant traits.

Returns An otherwise unused `Storage` instance.

Parameters

expiry

Latest time at which to give up. The `Storage` implementation is free to impose a stricter expiry, for example for resource management when more one call to `another()` is in progress.

Exceptions

`CORBA::TIMEOUT`

Raised if an appropriate `Storage` instance cannot be obtained before expiry.

`CORBA::NO_RESOURCES`

Raised if the operation gives up before the specified expiry time.

`IT_Buffer::Storage::reference()`

Increments the `Storage` instance's reference count.

C++ implementation

This function is not used in C++.

`IT_Buffer::Storage::unreference()`

Decrement the `Storage` instance's reference count.

C++ implementation

This function is not used in C++.

IT_Buffer::Segment

A contiguous subset of the data contained in a Buffer.

Description

A Segment represents a contiguous subset of the bytes contained in a Buffer. Segments are implemented by the ART core. Segment instances belong to a specific Buffer instance and are not reference counted in C++. Segment instances must be protected from concurrent access. The data attribute may expose bytes that belong to other Segments, which must not be examined or modified via this Segment.

IT_Buffer::Segment::data

A pointer to the block of raw memory where this segment is stored.

C++ implementation

In C++, the native `RawData` type maps to `CORBA::Octet*`.

IT_Buffer::Segment::offset

The offset in `IT_Buffer::Segment::data` at which this Segment's bytes begin.

Description

In other words, the first byte in this Segment is given by `Segment::data + Segment::offset`.

IT_Buffer::Segment::length

The number of bytes in `IT_Buffer::Segment::data` that belong to this Segment.

Description

The value of length is always greater than zero.

For example, the index after the last byte in the segment is given by `Segment::data + Segment::offset + Segment::length`.

IT_Buffer::Segment::underlying_storage

Returns the underlying storage as an `IT_Buffer::Storage` object.

IT_Buffer::Buffer

A randomly accessible linear finite sequence of bytes.

Description

A `Buffer` is made up of an ordered set of `Segment`s, each providing access to a contiguous subrange of the `Buffer`'s data. `Buffer`s are implemented by the ART core, and instances must be protected from concurrent access.

C++ implementation

`Buffer`s are not reference counted in C++.

`IT_Buffer::Buffer::length`

The number of bytes within the `Buffer` currently available for use.

`IT_Buffer::Buffer::original_length`

The number of bytes originally allocated to the `Buffer`.

`IT_Buffer::Buffer::storage_size`

The allocation unit size of the `Buffer`'s underlying `Storage` implementation.

`IT_Buffer::Buffer::segment_count`

The number of segments currently available for use.

`IT_Buffer::Buffer::rewind()`

Ensures that a subsequent call to `next_segment()` will return the first segment of the `Buffer`, or NULL if the length is zero.

`IT_Buffer::Buffer::next_segment()`

Gets the next `Segment` of the `Buffer`.

Description

The first call to `next_segment()` after a `Buffer` has been allocated or `rewind()` has been called returns the first `Segment` of the `Buffer`. A subsequent call returns the `Segment` following the `Segment` that was previously returned.

Returns The next segment, or NULL if the `Buffer` contains no additional segments.

`IT_Buffer::Buffer::grow()`

Attempts to increase the length of the `Buffer`.

Description

On successful return, the `Buffer`'s length will have increased by at least `increment` bytes. It may be larger, if adding an integral number of `Storage` instances results in more than the requested number of bytes. If the most recent call to `next_segment()` had returned NULL, a call subsequent to a successful `grow()` by a non-zero increment will return the first newly added `Segment`.

Parameters

`increment`

The minimum by which to increase the length.

`expiry`

Latest time at which to give up. The `Buffer` implementation is free to impose a stricter expiry time.

Exceptions

CORBA::TIMEOUT

Raised if the `Buffer` cannot be grown to at least `new_length` bytes before expiry.

CORBA::NO_RESOURCES

Raised if the operation gives up before the specified expiry time.

IT_Buffer::Buffer::trim()

Reduce the length, unreferencing any unneeded `Storage` instances.

Description

Trim always rewinds the `Buffer`.

Parameters

`from`

The index of the first byte to be included in the trimmed `Buffer`.

`to`

The index after the last byte to be included in the trimmed `Buffer`.

Exceptions

CORBA::BAD_PARAM

Raised if an invalid subrange is specified.

IT_Buffer::Buffer::eclipse()

Hides or exposes an initial subrange of the `Buffer` data.

Description

Nested eclipsing is allowed. The `Buffer` is always rewound by this operation.

Parameters

`delta`

Specifies the offset from the current `Buffer` start index to hide (when positive) or expose (when negative)

Exceptions

CORBA::BAD_PARAM

Raised if `delta` is outside the uneclipsed buffer.

IT_Buffer::Buffer::recycle()

Returns the `Buffer` to the `BufferManager`'s pool of unallocated `Buffer`s, unreferencing any `Storage` instances it contains.

Exceptions

CORBA::BAD_INV_ORDER

Raised if the buffer is already recycled.

IT_Buffer::Buffer::prepend()

Concatenates another `Buffer` with this `Buffer`.

Description

The contents of the `head` is inserted prior to the current first byte of this `Buffer`. The head `Buffer` is implicitly recycled.

Parameters

`head`

The other `Buffer`.

IT_Buffer::Buffer::append()

Concatenates this `Buffer` with another `Buffer`.

Description

The contents of the `tail` is inserted after the current last byte of this `Buffer`. The tail `Buffer` is implicitly recycled. If the most recent call to `next_segment()` had returned NULL, a call subsequent to the `append()` of a non-empty buffer returns the first appended segment.

Parameters

`tail`

The other `Buffer`.

`IT_Buffer::Buffer::extract()`

Extracts the specified range of bytes from this `Buffer`.

Description

The specified range of bytes are returned as a new `Buffer`. This `Buffer` is left containing the concatenation of the bytes before and after the specified range. Both this `Buffer` and the result are rewound.

Returns A new `Buffer` containing the extracted bytes.

Parameters

`from`

The index of the first byte to extract.

`to`

The index after the last byte to extract.

Exceptions

`CORBA::BAD_PARAM`

Raised if an invalid subrange is specified.

`IT_Buffer::Buffer::copy_octets()`

Copy a sub-range of the `Buffer` into an octet sequence.

Parameters

`buffer_offset`

The offset into the Buffer to copy from.

dest

The destination octet sequence. The octets in the given sequence object can be modified, but the implementation should *not* return a different sequence.

dest_offset

The offset into the destination to copy into.

length

The number of bytes to copy.

Exceptions

CORBA::BAD_PARAM

Raised if an invalid sub-range of the `Buffer` is specified.

IT_Buffer::BufferManager

A per-ORB singleton object for managing Buffers.

Description

An instance of `BufferManager` is provided by the ART core, and is obtained by resolving the `IT_BufferManager` initial reference string.

`IT_Buffer::BufferManager::get_buffer()`

Allocate a `Buffer` containing a single `Segment` that references the specified range of the specified `Storage` instance.

Returns The newly allocated `Buffer`.

Parameters

`initial_segment_storage`

The `Storage` object backing the initial segment.

`initial_segment_offset`

The offset in `initial_segment_storage` at which the initial segment begins.

initial_segment_length

The number of bytes in `initial_segment_storage` belonging to the initial segment.

IT_Buffer::BufferManager::get_segmented_buffer()

Allocates a `Buffer` containing a sequence of `Segment` s, each backed by the corresponding member of the provided sequence of `Storage` s, bounded by the relevant members of the offsets and lengths sequences.

Description

Typically used by a wrapping `Buffer` implementation.

Returns The newly allocated `Buffer` .

Parameters

storages

The sequence of `Storage` objects.

offsets

The sequence of offsets.

lengths

The sequence of lengths.

IT_Buffer::BufferManager::get_heap_buffer()

Allocate a `Buffer` containing the specified amount of heap-allocated `Storage`.

Returns The newly allocated `Buffer` .

Parameters

length

The number of bytes required; or zero, indicating a single `Segment` of the heap's preferred size.

IT_Buffer::BufferManager::get_octets_buffer()

Allocate a `Buffer` referencing an octet sequence's data.

Returns The newly allocated `Buffer` .

Parameters

octets

The octet sequence

offset

The offset into the octet sequence.

length

The number of octets to use.

IT_Buffer::BufferManager::adopt_octets_buffer()

Allocate a `Buffer` that adopts an octet sequence's data.

Returns The newly allocated `Buffer` .

Parameters

octets

The octet sequence

offset

The offset into the octet sequence.

length

The number of octets to use.

IT_Certificate Overview

The `IT_Certificate` module provides data types and interfaces that are used to manage and describe X.509 certificates. The following interfaces are provided in this module:

- AVA
- AVAList
- Extension
- ExtensionList
- Certificate
- X509Cert
- X509CertificateFactory

IT_Certificate::ASN_OID Structure

// IDL

```
struct ASN_OID
{
    OIDTag    tag;
    ASN1oid   asn1_oid;
    string    tag_name;
};
```

Holds an ASN.1 object ID (OID).

The ASN.1 OID can be specified by setting either the `tag` or `asn1_oid` structure members.

An `ASN_OID` structure returned by Orbix normally sets both the `tag` and `asn1_oid` members in the structure. The returned tag value will be `IT_OIDT_UNKNOWN`, however, if Orbix does not recognize the OID from its internal table of known OIDs.

The structure has the following members:

<code>tag</code>	An Orbix-specific tag to identify an AVA. For example, the <code>IT_Certificate::IT_OIDT_COMMON_NAME</code> tag identifies the Common Name AVA. If you set <code>tag</code> equal to the special value <code>IT_Certificate::IT_OIDT_UNKNOWN</code>, it will be ignored and the <code>asn1_oid</code> member will be used instead.
<code>asn1_oid</code>	An ASN.1 OID to identify an AVA, specified in the standard way as a sequence of integers. For example, the sequence <code>2.5.4.3</code> identifies the Common Name AVA.
<code>tag_name</code>	Reserved for future use by Orbix.

IT_Certificate::ASN1oid Sequence

```
typedef sequence<UShort> ASN1oid;
```

Holds an ASN.1 OID in the standard format, which is a sequence of integers. For example, the sequence `2.5.4.3` identifies the Common Name AVA.

IT_Certificate::Bytes Sequence

```
typedef sequence<octet> Bytes;
```

Holds raw binary data.

IT_Certificate::CertError Exception

```
// IDL
```

```
exception CertError
{
    Error e;
};
```

A certificate-related error.

IT_Certificate::DERData Sequence

```
typedef sequence<octet> DERData;
```

Holds data in distinguished encoding rules (DER) format.

IT_Certificate::Error Structure

```
struct Error
```

```
{
    Error_code err_code;
    string error_message;
};
```

Holds certificate-related error information.

IT_Certificate::Error_code Type

```
typedef short Error_code;
```

Holds the certificate-related error codes.

Values

This type can have one of the following integer constant values:

```
IT_TLS_FAILURE
IT_TLS_UNSUPPORTED_FORMAT
IT_TLS_BAD_CERTIFICATE_DATA
IT_TLS_ERROR_READING_DATA
```

IT_Certificate::Format Structure

//IDL

```
typedef short Format;
```

Specifies a specific format for X.509 certificate data.

Values

This type can have one of the following integer constant values:

IT_FMT_DER	This format corresponds to the DER encoding of the AVA. This option is usually only used by applications that require special processing of the DER data.
IT_FMT_PEM	Privacy enhanced mail (PEM) format certificate format. In this format, the certificate consists of standard ASCII characters that can be safely transmitted as text.

<code>IT_FMT_STRING</code>	This format corresponds to a null-terminated sequence of characters containing the actual data of the AVA. The data is not modified in any way, and can include non-printable characters if present in the actual AVA data. This is a string for normal printable string fields.
<code>IT_FMT_HEX_STRING</code>	This format corresponds to a formatted hexadecimal dump of the DER data of the AVA.

IT_Certificate::OIDTag Type

```
typedef UShort OIDTag;
```

An Orbix-specific tag type that represents an ASN.1 OID. Tags are defined for most of the commonly used AVAs in an X.509 certificate. These tags are provided as a convenient alternative to the standard OID format, `IT_Certificate::ASN1oid`.

Values

This type can have one of the following integer constant values:

IT_OIDT_UNKNOWN
IT_OIDT_RSADSI
IT_OIDT_PKCS
IT_OIDT_MD2
IT_OIDT_MD5
IT_OIDT_RC4
IT_OIDT_RSA_ENCRYPTION
IT_OIDT_MD2_WITH_RSA_ENCRYPTION
IT_OIDT_MD5_WITH_RSA_ENCRYPTION
IT_OIDT_PBE_WITH_MD2_AND_DES_CBC
IT_OIDT_PBE_WITH_MD5_AND_DES_CBC
IT_OIDT_X500
IT_OIDT_X509
IT_OIDT_COMMON_NAME
IT_OIDT_COUNTRY_NAME
IT_OIDT_LOCALITY_NAME
IT_OIDT_STATE_OR_PROVINCE_NAME
IT_OIDT_ORGANIZATION_NAME
IT_OIDT_ORGANIZATIONAL_UNIT_NAME
IT_OIDT_RSA
IT_OIDT_PKCS7
IT_OIDT_PKCS7_DATA
IT_OIDT_PKCS7_SIGNED
IT_OIDT_PKCS7_ENVELOPED
IT_OIDT_PKCS7_SIGNED_AND_ENVELOPED
IT_OIDT_PKCS7_DIGEST
IT_OIDT_PKCS7_ENCRYPTED
IT_OIDT_PKCS3
IT_OIDT_DHKEY_AGREEMENT
IT_OIDT_DES_ECB
IT_OIDT_DES_CFB64
IT_OIDT_DES_CBC
IT_OIDT_DES_EDE
IT_OIDT_DES_EDE3
IT_OIDT_IDEA_CBC
IT_OIDT_IDEA_CFB64
IT_OIDT_IDEA_ECB
IT_OIDT_RC2_CBC
IT_OIDT_RC2_ECB
IT_OIDT_RC2_CFB64
IT_OIDT_RC2_OFB64
IT_OIDT_SHA
IT_OIDT_SHA_WITH_RSA_ENCRYPTION
IT_OIDT_DES_EDE_CBC
IT_OIDT_DES_EDE3_CBC
IT_OIDT_DES_OFB64

IT_OIDT_IDEA_OFB64
IT_OIDT_PKCS9
IT_OIDT_PKCS9_EMAIL_ADDRESS
IT_OIDT_PKCS9_UNSTRUCTURED_NAME
IT_OIDT_PKCS9_CONTENTTYPE
IT_OIDT_PKCS9_MESSAGE_DIGEST
IT_OIDT_PKCS9_SIGNING_TIME
IT_OIDT_PKCS9_COUNTER_SIGNATURE
IT_OIDT_PKCS9_CHALLENGE_PASSWORD
IT_OIDT_PKCS9_UNSTRUCTURED_ADDRESS
IT_OIDT_PKCS9_EXTCERT_ATTRIBUTES
IT_OIDT_NETSCAPE
IT_OIDT_NETSCAPE_CERT_EXTENSION
IT_OIDT_NETSCAPE_DATA_TYPE
IT_OIDT_DES_EDE_CFB64
IT_OIDT_DES_EDE3_CFB64
IT_OIDT_DES_EDE_OFB64
IT_OIDT_DES_EDE3_OFB64
IT_OIDT_SHA1
IT_OIDT_SHA1_WITH_RSA_ENCRYPTION
IT_OIDT_DSA_WITH_SHA
IT_OIDT_DSA_2
IT_OIDT_PBE_WITH_SHA1_AND_RC2_CBC
IT_OIDT_ID_PBKDF2
IT_OIDT_DSA_WITH_SHA1_2
IT_OIDT_NETSCAPE_CERT_TYPE
IT_OIDT_NETSCAPE_BASE_URL
IT_OIDT_NETSCAPE_REVOCATION_URL
IT_OIDT_NETSCAPE_CA_REVOCATION_URL
IT_OIDT_NETSCAPE_RENEWAL_URL
IT_OIDT_NETSCAPE_CA_POLICY_URL
IT_OIDT_NETSCAPE_SSL_SERVER_NAME
IT_OIDT_NETSCAPE_COMMENT
IT_OIDT_NETSCAPE_CERT_SEQUENCE
IT_OIDT_DESX_CBC
IT_OIDT_LD_CE
IT_OIDT_SUBJECT_KEY_IDENTIFIER
IT_OIDT_KEY_USAGE
IT_OIDT_PRIVATE_KEY_USAGE_PERIOD
IT_OIDT_SUBJECT_ALT_NAME
IT_OIDT_ISSUER_ALT_NAME
IT_OIDT_BASIC_CONSTRAINTS
IT_OIDT_CRL_NUMBER
IT_OIDT_CERTIFICATE_POLICIES
IT_OIDT_AUTHORITY_KEY_IDENTIFIER
IT_OIDT_BF_CBC
IT_OIDT_BF_ECB

IT_OIDT_BF_CFB64
IT_OIDT_BF_OFB64
IT_OIDT_MDC2
IT_OIDT_MDC2_WITH_RSA
IT_OIDT_RC4_40
IT_OIDT_RC2_40_CBC
IT_OIDT_GIVEN_NAME
IT_OIDT_SURNAME
IT_OIDT_INITIALS
IT_OIDT_UNIQUEIDENTIFIER
IT_OIDT_CRL_DISTRIBUTION_POINTS
IT_OIDT_MD5_WITH_RSA
IT_OIDT_SERIALNUMBER
IT_OIDT_TITLE
IT_OIDT_DESCRIPTION
IT_OIDT_CAST5_CBC
IT_OIDT_CAST5_ECB
IT_OIDT_CAST5_CFB64
IT_OIDT_CAST5_OFB64
IT_OIDT_PBE_WITH_MD5_AND_CAST5_CBC
IT_OIDT_DSA_WITH_SHA1
IT_OIDT_MD5_SHA1
IT_OIDT_SHA1_WITH_RSA
IT_OIDT_DSA
IT_OIDT_RIPEMD160
IT_OIDT_UNDEF
IT_OIDT_RIPEMD160_WITH_RSA
IT_OIDT_RC5_CBC
IT_OIDT_RC5_ECB
IT_OIDT_RC5_CFB64
IT_OIDT_RC5_OFB64
IT_OIDT_RLE_COMPRESSION
IT_OIDT_ZLIB_COMPRESSION
IT_OIDT_EXT_KEY_USAGE
IT_OIDT_ID_PKIX
IT_OIDT_ID_KP
IT_OIDT_SERVER_AUTH
IT_OIDT_CLIENT_AUTH
IT_OIDT_CODE_SIGN
IT_OIDT_EMAIL_PROTECT
IT_OIDT_TIME_STAMP
IT_OIDT_MS_CODE_IND
IT_OIDT_MS_CODE_COM
IT_OIDT_MS_CTL_SIGN
IT_OIDT_MS_SGC
IT_OIDT_MS_EFS
IT_OIDT_NS_SGC

```

IT_OIDT_DELTA_CRL
IT_OIDT_CRL_REASON
IT_OIDT_INVALIDITY_DATE
IT_OIDT_SXNET
IT_OIDT_PBE_WITH_SHA1_AND_128BITRC4
IT_OIDT_PBE_WITH_SHA1_AND_40BITRC4
IT_OIDT_PBE_WITH_SHA1_AND_3_KEY_TRIPLEDES_CBC
IT_OIDT_PBE_WITH_SHA1_AND_2_KEY_TRIPLEDES_CBC
IT_OIDT_PBE_WITH_SHA1_AND_128BITRC2_CBC
IT_OIDT_PBE_WITH_SHA1_AND_40BITRC2_CBC
IT_OIDT_KEY_BAG
IT_OIDT_PKCS8SHROUDEDKEY_BAG
IT_OIDT_CERT_BAG
IT_OIDT_CRL_BAG
IT_OIDT_SECRET_BAG
IT_OIDT_SAFECONTENTS_BAG
IT_OIDT_FRIENDLY_NAME
IT_OIDT_LOCALKEYID
IT_OIDT_X509CERTIFICATE
IT_OIDT_SDSICERTIFICATE
IT_OIDT_X509CRL
IT_OIDT_PBES2
IT_OIDT_PBMAC1
IT_OIDT_HMAC_WITH_SHA1
IT_OIDT_ID_QT_CPS
IT_OIDT_ID_QT_UNOTICE
IT_OIDT_RC2_64_CBC
IT_OIDT_SMIMECAPABILITIES
IT_OIDT_PBE_WITH_MD2_AND_RC2_CBC
IT_OIDT_PBE_WITH_MD5_AND_RC2_CBC
IT_OIDT_PBE_WITH_SHA1_AND_DES_CBC

```

IT_Certificate::ReplyStatus Type

typedef short ReplyStatus;

Gives the reply status of certain operations in the `IT_Certificate` module.

Values

This type can have the following integer constant values:

```
SUCCESSFUL
AVA_NOT_PRESENT
EXTENSION_NOT_PRESENT
NO_EXTENSIONS_PRESENT
```

See Also `IT_Certificate::AVAList`

```
IT_Certificate::ExtensionList
IT_Certificate::X509Cert
```

`IT_Certificate::ULong` Type

```
typedef unsigned long ULong;
```

An unsigned long integer.

`IT_Certificate::UShort` Type

```
typedef unsigned short UShort;
```

An unsigned short integer.

`IT_Certificate::UTCTime` Type

```
typedef sequence<string> UTCTime;
```

A type used to hold time (and date) information in a certificate.

`IT_Certificate::X509CertChain` Sequence

```
typedef sequence<X509Cert> X509CertChain;
```

A list of `X509Cert` object references.

`IT_Certificate::X509CertList` Sequence

```
typedef sequence<X509Cert> X509CertList;
```

A list of `X509Cert` object references.

IT_Certificate::AVA Interface

IDL

```
// IDL in module IT_Certificate
interface AVA
{
    readonly attribute UShort set;
    readonly attribute ASN_OID oid;
    // raises minor code IT_TLS_UNSUPPORTED_FORMAT
    Bytes convert(in Format f) raises(CertError);
};
```

Individual AVA objects represent an element of the distinguished name such as the common name field (CN) or organization unit (OU). You can retrieve a desired AVA object can using the AVAList class.

AVA objects can be converted to a number of different forms such as string format or DER format.

AVA::convert()

```
// IDL
Bytes convert(in Format f) raises(CertError);
```

Description

This operation returns the contents of the AVA object in the requested data format.

ParametersThis operation takes the following parameter

f

The format of the required conversion. The following Format values are supported:

IT_FMT_DER . This format corresponds to the DER encoding of the AVA. This option is usually only used by applications that require special processing of the DER data.

IT_FMT_STRING . This format corresponds to a null-terminated sequence of characters containing the actual data of the AVA. The data is not modified in any way, and can include non-printable characters if present in the actual AVA data. This is a string for normal printable string fields.

IT_FMT_HEX_STRING . This format corresponds to a formatted hexadecimal dump of the DER data of the AVA.

Exceptions

CertError with error code **IT_TLS_UNSUPPORTED_FORMAT**

An unknown format is specified.

AVA::oid

```
// IDL
readonly attribute ASN_OID oid;
```

Description

Return the ASN.1 OID tag for this AVA object, in the form of an **ASN_OID** structure.

AVA::set

```
// IDL
readonly attribute UShort set;
```

Description

A number that identifies the set to which the AVA belongs. Because a set normally contains just a single AVA, the number returned by the **set** attribute is usually distinct for each AVA.

Theoretically, more than one AVA could belong to the same set, in which case two or more AVAs could share the same `set` number. In practice, this rarely ever happens.

IT_Certificate::AVAList Interface

IDL

```
// IDL in module IT_Certificate
interface AVAList
{
    typedef sequence<AVA> ListOfAVAs;
    readonly attribute ListOfAVAs ava_list;
    UShort get_num_avas();
    // Returns SUCCESSFUL or AVA_NOT_PRESENT
    IT_Certificate::ReplyStatus
    get_ava_by_oid_tag(
        in OIDTag t,
        out AVA a
    ) raises(CertError);
    // Returns SUCCESSFUL or AVA_NOT_PRESENT
    IT_Certificate::ReplyStatus
    get_ava_by_oid(
        in ASN_OID seq,
        in UShort n,
        out AVA a
    ) raises(CertError);
    // raises minor code IT_TLS_UNSUPPORTED_FORMAT
    Bytes convert(
        in Format f
    ) raises(CertError);
};
```

Description

An `AVAList` is an abstraction of a distinguished name from a certificate. An `AVAList` consists of a number of `AVA` objects.

Individual `AVA` objects represent an element of the distinguished name such as the common name field (CN) or organization unit (OU). You can retrieve a desired `AVA` object using the `AVAList`.

`AVA` objects can be converted to a number of different forms such as string format or DER format.

`AVAList::ava_list`

IDL


```
readonly attribute ListOfAVAs ava_list;
```

Description

Returns the AVA list as a sequence of AVA object references.

AVAList::convert()

IDL

```
Bytes convert(in Format f) raises (CertError);
```

Description

This operation converts the AVAList to a specified format.

ParametersThis operation takes the following parameter:

f

The format of the required conversion. The following `Format` values are supported:

`IT_FMT_DER`. This format corresponds to the DER encoding of the AVA. This option is usually only used by applications that require special processing of the DER data.

`IT_FMT_STRING`. This format corresponds to a null-terminated sequence of characters containing the actual data of the AVA. The data is not modified in any way, and can include non-printable characters if present in the actual AVA data. This is a string for normal printable string fields.

`IT_FMT_HEX_STRING`. This format corresponds to a formatted hexadecimal dump of the DER data of the AVA.

Exceptions

`CertError`, error code `IT_TLS_UNSUPPORTED_FORMAT`

An unknown format is specified.

AVAList::get_ava_by_oid_tag()

IDL

```
// Returns SUCCESSFUL or AVA_NOT_PRESENT
IT_Certificate::ReplyStatus
get_ava_by_oid_tag(
    in OIDTag t,
    out AVA a
) raises(CertError);
```

Description

This operation retrieves an AVA object from an `AVAList` according to its OID tag.

Parameters

<code>t</code>	An OID tag
<code>a</code>	The returned AVA object reference.

`AVAList::get_ava_by_oid()`

IDL

```
// Returns SUCCESSFUL or AVA_NOT_PRESENT
IT_Certificate::ReplyStatus
get_ava_by_oid(
    in ASN_OID seq,
    in UShort n,
    out AVA a
) raises(CertError);
```

Description

This operation retrieves an AVA object from an `AVAList`, selected by the specified `ASN_OID` structure.

Parameters

<code>seq</code>	An ASN OID.
<code>n</code>	
<code>a</code>	The returned AVA object reference.

`AVAList::get_num_avas()`

IDL

UShort get_num_avas()

Description

This operation retrieves the number of AVA objects in a `AVAList`.

IT_Certificate::Certificate Interface

IDL

```
// IDL in module IT_Certificate
interface Certificate
{
    readonly attribute DERData encoded_form;
};
```

Description

This is the base interface for security certificate objects.

Certificate::encoded_form

IDL

```
readonly attribute DERData encoded_form;
```

Description

This attribute returns the certificate data encoded in DER format.

IT_Certificate::Extension Interface

IDL

```
// IDL in module IT_Certificate
interface Extension
{
    readonly attribute UShort    critical;
    readonly attribute ASN_OID oid;
    // raises minor code IT_TLS_UNSUPPORTED_FORMAT
    Bytes convert(in Format f) raises(CertError);
};
```

Description

The `Extension` interface provides the developer with an interface to any X.509 version 3.0 extensions that an X.509 certificate can contain.

The `Extension` interface enables you to access the data for one particular extension. Using the `Extension::convert()` operations, the data can be converted into a number of representations.

Extension::convert()

IDL

```
Bytes convert(in Format f) raises(CertError);
```

Description

This operation returns data that corresponds to the contents of the `Extension` object converted to the requested format. The data is converted to the requested format and returned as an array of bytes.

Parameters This operation takes the following parameter:

`f`

The format of the required conversion. The following `Format` values are supported:

`IT_FMT_DER`. This format corresponds to the DER encoding of the extension. This option is usually only used by applications that require special processing of the DER data.

`IT_FMT_STRING`. This format corresponds to a null terminated sequence of characters containing the actual data contained in the extension. This data has not been modified in any way, and may include non printable characters if present in the actual extension data. This is a regular 'C' string for printable string fields.

`IT_FMT_HEX_STRING`. This format contains a formatted hexadecimal dump of the DER data of the extension.

Extension::critical

IDL

```
readonly attribute UShort critical;
```

Description

This attribute returns a non-zero value if the extension is critical; zero if the extension is not critical. A critical extension is an extension that should not be ignored by the authentication code.

Extension::oid

IDL

```
readonly attribute ASN_OID oid;
```

Description

This attribute returns the ASN.1 OID for the extension. Extensions are identified by an ASN.1 OID, just like regular AVAs.

IT_Certificate::ExtensionList Interface

IDL

```
// IDL in module IT_Certificate
interface ExtensionList
{
    typedef sequence<Extension> ListOfExtensions;
    readonly attribute ListOfExtensions ext_list;
    UShort get_num_extensions();
    // Returns SUCCESSFUL or EXTENSION_NOT_PRESENT
    IT_Certificate::ReplyStatus
    get_extension_by_oid_tag(
        in OIDTag t,
        out Extension e
    ) raises(CertError);
    // Returns SUCCESSFUL or EXTENSION_NOT_PRESENT
    IT_Certificate::ReplyStatus
    get_extension_by_oid(
        in ASN_OID seq,
        in UShort n,
        out Extension e
    ) raises(CertError);
    // raises minor code IT_TLS_UNSUPPORTED_FORMAT
    Bytes convert(in Format f) raises(CertError);
};
```

Description

The `Extension` and `ExtensionList` interfaces provide you with access to any X.509 version three extensions.

The `Extension` interface provides an interface to accessing the data for one particular extension.

`ExtensionList::convert()`

IDL

```
Bytes convert(in Format f) raises(CertError);
```

Description

`convert()` returns data in the requested format corresponding to the contents of the `ExtensionList` object. The operation returns this data as an array of bytes, or NULL if the the required conversion is not supported.

Note

Generally `convert()` is called on the individual extensions. This operation is not commonly used.

Parameters This operation takes the following parameter:

`f`

The format of the required conversion. The following `Format` value is supported:

`IT_FMT_DER`. This format corresponds to the DER encoding of the AVA. This option is usually only used by applications that require special processing of the DER data.

`IT_FMT_STRING`. This format corresponds to a null-terminated sequence of characters containing the actual data of the AVA. The data is not modified in any way, and can include non-printable characters if present in the actual AVA data. This is a string for normal printable string fields.

`IT_FMT_HEX_STRING`. This format corresponds to a formatted hexadecimal dump of the DER data of the AVA.

Exceptions

`CertError`, error code `IT_TLS_UNSUPPORTED_FORMAT`

An unknown format is specified.

`ExtensionList::ext_list`

IDL

```
readonly attribute ListOfExtensions ext_list;
```

Description

This attribute returns the complete list of extensions as a sequence of `Extension` objects.

`ExtensionList::get_extension_by_oid()`

IDL


```
IT_Certificate::ReplyStatus  
get_extension_by_oid(  
    in ASN_OID seq,  
    in UShort n,  
    out Extension e  
) raises(CertError);
```

Description

Obtains the Extension element of the `ExtensionList` that has the requested object identifier, `seq`.

If the extension is found, a `SUCCESSFUL` reply status is returned; otherwise an `EXTENSION_NOT_PRESENT` reply status is returned.

Parameters This operation takes the following parameters

<code>seq</code>	An array of integers representing the ASN.1 object identifier.
<code>n</code>	The number of elements in the array.
<code>e</code>	The returned <code>Extension</code> object.

`ExtensionList::get_extension_by_oid_tag()`

IDL

```
IT_Certificate::ReplyStatus  
get_extension_by_oid_tag(  
    in OIDTag t,  
    out Extension e  
) raises(CertError);
```

Description

Obtains the Extension element of the `ExtensionList` that corresponds to the supplied `OIDTag` value, `t`.

If the extension is found, a `SUCCESSFUL` reply status is returned; otherwise an `EXTENSION_NOT_PRESENT` reply status is returned.

Parameters

<code>t</code>	The <code>OIDTag</code> variable that identifies the extension to retrieve.

e	The returned <code>Extension</code> object.

`ExtensionList::get_num_extensions();`

IDL

```
UShort get_num_extensions();
```

Description

This operation returns the number of extensions in the list.

IT_Certificate::X509Cert Interface

IDL

```
// IDL in module IT_Certificate
interface X509Cert : IT_Certificate::Certificate
{
    exception IntegerTooLarge { };
    long    get_version();
    UTCTime get_not_before();
    UTCTime get_not_after();
    ASN_OID get_signature_algorithm_id();
    ULong   get_serial_number()
    raises(
        CertError,
        IntegerTooLarge
    );
    DERData get_der_serial_number() raises (CertError);
    string  get_subject_dn_string() raises (CertError);
    string  get_issuer_dn_string()  raises (CertError);
    string
    get_subject_ava_string(in OIDTag t) raises (CertError);
    string
    get_issuer_ava_string(in OIDTag t)  raises (CertError);
    AVAList get_issuer_avalist()  raises (CertError);
    AVAList get_subject_avalist() raises(CertError);
    // Returns SUCCESSFUL or NO_EXTENSIONS_PRESENT
    IT_Certificate::ReplyStatus
    get_extensions(out ExtensionList el) raises (CertError);
    // raises minor code IT_TLS_UNSUPPORTED_FORMAT
    Bytes convert(in Format f) raises(CertError);
};
```

Description

The `X509Cert` interface provides a high-level interface to an X.509 certificate. A number of operations are provided to obtain information contained in the certificate. This interface, along with other certificate interfaces, shields the developer from having to know about low-level details such as the encoding of X.509 certificates. Access to low-level DER information is, however, also provided.

For example, the `get_issuer_dn_string()`, `get_issuer_ava_string()`, `get_subject_dn_string()`, and `get_subject_ava_string()` provide easy access to the *issuer* and *subject* entries in a certificate. Typical issuer and subject entries have the following form:

```
issuer :/C=IE/ST=Co. Dublin/L=Dublin/O=IONA Technologies/OU=IDD/
CN=IssuerName/Email=IssuerName@iona.com
subject:/C=IE/ST=Co. Dublin/O=IONA Technologies/OU=IDD/CN=SubjectName/
Email=SubjectName@iona.com
```

X509Cert::convert()

IDL

```
Bytes
convert(in Format f) raises (CertError);
```

Description

Converts the certificate to the specified format.

ParametersThis operation takes the following parameter:

`f`

The format of the required conversion. The following `Format` values are supported:

`IT_FMT_DER`. This format corresponds to the DER encoding of the extension. This option is usually only used by applications that require special processing of the DER data.

`IT_FMT_STRING`. This format corresponds to a null terminated sequence of characters containing the actual data contained in the extension. This data has not been modified in any way, and may include non printable characters if present in the actual extension data. This is a regular 'C' string for printable string fields.

`IT_FMT_HEX_STRING`. This format contains a formatted hexadecimal dump of the DER data of the extension.

X509Cert::get_der_serial_number()

IDL

```
DERData
get_der_serial_number() raises (CertError);
```

Description

Obtains the serial number of the certificate and returns it as DERData object.

X509Cert::get_extensions()

IDL

```
IT_Certificate::ReplyStatus
get_extensions(out ExtensionList el) raises (CertError);
```

Description

Obtains the complete extension list, `el`, for this certificate.

If the extensions are found, a `SUCCESSFUL` reply status is returned; otherwise an `NO_EXTENSIONS_PRESENT` reply status is returned.

Parameters

`el`

An out parameter containing the extension list as a sequence of Extension objects.

X509Cert::get_issuer_avalist()

IDL

```
AVAList
get_issuer_avalist() raises (CertError);
```

Description

Retrieves the distinguished name of the certificate issuer as an AVAList instance. Individual components of the distinguished name (for example, the common name or the organization name) can be retrieved from the `AVAList` instance.

X509Cert::get_issuer_ava_string()

IDL

```
string
get_issuer_ava_string(in OIDTag t) raises (CertError);
```

Description

Returns a string representing the AVA field selected by the `OIDTag`, `t`, from the certificate issuer AVA list.

X509Cert::get_issuer_dn_string()

IDL

```
string
get_issuer_dn_string() raises (CertError);
```

Description

Returns a string representing the certificate issuer's distinguished name (DN).

X509Cert::get_not_after()

IDL

```
UTCTime get_not_after();
```

Description

Extracts the `notAfter` field from an X.509 certificate. This field is used to determine the date validity of a certificate in conjunction with the `notBefore` field. A certificate can be specified as not valid until after some point in the future.

X509Cert::get_not_before()

IDL

```
UTCTime get_not_before();
```

Description

Extracts the `notBefore` field from an X.509 certificate. This field is used in determining the date validity of a certificate in conjunction with the `notAfter` field. A certificate can be specified as not valid until some point in the future.

X509Cert::get_serial_number()

IDL

```
DERData
get_der_serial_number() raises (CertError);
```

Description

Returns the serial number of the certificate.

X509Cert::get_signature_algorithm_id()

IDL

```
ASN_OID
get_signature_algorithm_id();
```

Description

This operation returns the ASN.1 OID of the signature algorithm that was used to sign the certificate. For example, MD2, MD5, or SHA.

See Also IT_Certificate::OIDTag

```
IT_Certificate::IT_OIDT_MD2
IT_Certificate::IT_OIDT_MD5
IT_Certificate::IT_OIDT_SHA
```

X509Cert::get_subject_avalist()

IDL

```
AVAList
get_subject_avalist() raises (CertError);
```

Description

Returns the subject of the certificate in the form of an AVAList.

X509Cert::get_subject_ava_string()

IDL

```
string
get_subject_ava_string(in OIDTag t) raises (CertError);
```

Description

Returns a string representing the AVA field selected by the OIDTag, *t*, from the certificate subject AVA list.

X509Cert::get_subject_dn_string()

IDL

```
string
get_subject_dn_string() raises (CertError);
```

Description

Returns a string representing the certificate subject's distinguished name (DN).

X509Cert::get_version()

IDL

```
long get_version();
```

Description

Returns the version minus one for the X.509 standard to which the certificate conforms. Hence, this operation returns 0 for v1, 1 for v2, and 2 for v3 in accordance with ASN.1 conventions. Most certificates conform to v3, which has support for AVA extensions.

X509Cert::IntegerTooLarge Exception

IDL

exception IntegerTooLarge

Description

Exception thrown in the unlikely case that an attempt to convert a DER encoded integer to the `CORBA::ULong` type fails because the specified DER encoded integer corresponds to a value that is too large to be represented by the DER encoded integer. In this unlikely case, the DER data form of the integer would have to be examined directly by the application.

IT_Certificate::X509CertificateFactory Interface

IDL

```
// IDL in module IT_Certificate
interface X509CertificateFactory
{
    // Following function creates x509Cert from DER data.
    // where DERData is a sequence of octets
    //
    // raises minor code IT_TLS_BAD_CERTIFICATE_DATA
    //
    X509Cert
    create_x509_certificate_from_der(
        in DERData der
    ) raises(CertError);
    //
    // Read CertList from a file.
    // raises minor code IT_TLS_BAD_CERTIFICATE_DATA.
    // raises minor code IT_TLS_ERROR_READING_DATA.
    //
    X509CertList
    load_x509_cert_list(
        in string location
    ) raises(CertError);
};
```

Description

This interface is a factory that generates X.509 certificates of IT_Certificate :: X509Cert type.

This interface contains one operation, `create_x509_cert()`, that generates an X.509 certificate on receiving data in the form of DER.

X509CertificateFactory::create_x509_certificate_from_der()

IDL

```

X509Cert
create_x509_certificate_from_der(
    in DERData der
) raises(CertError);

```

Description

Generates an X.509 certificate based on a parameter supplied in DER format, `der`.

ParametersThis operation takes the following parameter:

Parameter	Description
<code>der</code>	The certificate data in DER format (of <code>DERData</code> type).

Exceptions

`CertError`, error code `IT_TLS_BAD_CERTIFICATE_DATA`

The `der` parameter is inconsistent or incorrectly formatted

`X509CertificateFactory::load_x509_cert_list()`

IDL

```

X509CertList
load_x509_cert_list(in string location) raises(CertError);

```

Description

Generates a list of X.509 certificates based on data read from the file specified by `location`. The file must contain a chain of certificates in PEM format.

ParametersThis operation takes the following parameter:

Parameter	Description
<code>location</code>	The absolute path name of the file containing the PEM certificate chain.

Exceptions

Exception	Description
<code>CertError</code> , error code <code>IT_TLS_ERROR_READING_DATA</code>	Orbix cannot read the specified certificate file

CertError, error code

IT_TLS_BAD_CERTIFICATE_DATA

The content of the certificate file is inconsistent or incorrectly formatted.

IT_Config Overview

Every ORB is associated with a configuration domain that provides it with configuration information. The configuration mechanism enables Orbix to get its configuration information from virtually any source including files or configuration repositories. The `IT_Config` module contains the API to both get configuration settings and receive notifications when a particular configuration value changes. The module contains the following interfaces:

- Configuration
- Listener

The `IT_Config` module does not give you a mechanism for changing configurations.

Administrators typically setup and manage a configuration domain using various tools described in the *Application Server Platform Administrator's Guide*. However, applications can locally override a configuration, without changing the configuration domain, by passing in configuration variables in the command line. These configuration variables are processed by CORBA : : ORB_init() where the ORB processes them first before querying the configuration domain.

A single *configuration domain* can hold configuration information for multiple ORBs – each ORB uses its ORB name as a “key” to locate its particular configuration within the domain. Often, an administrator will want to use a default configuration domain for a group of applications, overriding only certain configuration variables for individual applications or ORBs. This might be useful within a hierarchical organization, or where different development groups or applications need slightly different configurations.

A configuration domain can be organized into a hierarchy of nested *configuration scopes* to enable a high degree of flexibility. Each scope within a domain must be uniquely named relative to its containing scope. Scope names consist of any combinations of alphanumeric characters and underscores. Scopes are usually identified by their fully qualified name, which contains the scope name and the names of all parent scopes, separated by a dot (.).

Within each configuration scope, variables are organized into configuration contexts. A *configuration context* is simply a collection of related configuration variables. A context may also contain sub-contexts. You can consider the configuration scope as the root context. Contained in the root context are a number of sub-contexts. For example, there is a plug-ins context and an initial-references context. The initial-references context contains a list of initial-references for the services available to the system. The plug-ins context contains a sub-context for each plug-in, in which it holds its configuration information. This context will have the same name as the plug-in, and will hold information such as the name of the plug-in library and any dependencies the plug-in has, as well as other plug-in-specific settings.

You as a programmer need not worry about this configuration hierarchy set up by your administrator. You simply request configuration values via the `Configuration` interface. See the *Application Server Platform Administrator's Guide* for more on configuration.

IT_Config::ConfigList Sequence

// IDL

```
typedef sequence<string> ConfigList;
```

A list of configuration settings as strings.

EnhancementThis is an Orbix enhancement.

See AlsoIT_Config::Configuration::get_list()

```
IT_Config::Listener::list_changed()
```

IT_Config::ListenerTargetRange Enumeration

// IDL

```
enum ListenerTargetRange {
    OBJECT_ONLY,
    ONELEVEL,
    SUBTREE
};
```

A target scope refers to the extent of a configuration hierarchy that a Listener object monitors.

OBJECT_SCOPE	The Listener is only interested in changes to the specific target variable. For example, a Listener with a target variable of <code>initial_references:Naming:reference</code> and a target scope of <code>OBJECT_SCOPE</code> is informed if that variable changes.
ONELEVEL_SCOPE	The Listener is interested in changes to variables contained in the target, a configuration context, but not the target itself. For example, if the target is <code>plugins:iop</code> , the Listener is informed of any changes to variable in the <code>plugins:iop</code> configuration context.

SUBTREE_S COPE	The Listener is interested in changes to the target and any variables or namespaces in the subtree of the target. For example, if the target is <code>initial_references</code> , the Listener is informed of any changes to anything under the <code>initial_references</code> namespace, including the namespace itself.

EnhancementThis is an Orbix enhancement.

See Also`IT_Config::Configuration::add_listener()`

IT_Config::Configuration Interface

This interface provides access to configuration information. You get a reference to a `Configuration` implementation by calling `ORB::resolve_initial_references()` with the string argument `IT_Configuration`.

In a configuration domain, the ORB name acts as the configuration scope in which to start looking for configuration information. The ORB supplies this information when querying the configuration system for a configuration variable. If the variable cannot be found within that scope or the scope does not exist, the system recursively searches the containing scope. For example, if an ORB with an ORB name of `IONA.ProdDev.TestSuite.TestMgr` requests a variable, the system will first look in the `IONA.ProdDev.TestSuite.TestMgr` scope, then `IONA.ProdDev.TestSuite`, and so on, until it finally looks in the root scope. This allows administrators to place default configuration information at the highest level scope, then override this information in descendant scopes to produce a specific, tailored configuration.

Although there are specific operations such as `get_boolean()` and `get_double()` to retrieve certain types of configuration information, the `Configuration` interface is not strictly typed. This means that when a certain type of variable is requested, an effort is made to convert the retrieved value to the requested type. For example, if you call `get_long()`, and the domain has a string such as "1234", an attempt is made to convert the string to a long. In this case, it can successfully return 1234 as a long. If, however, the value for the requested variable were words such as "A String Value", then it cannot be converted to a long and a `TypeMismatch` exception is thrown.

```
// IDL in module IT_Config
```

```
interface Configuration {
```



```

exception [TypeMismatch](#it_configconfiguration-interface) {};
boolean [get_string](#it_configconfiguration-interface)(
    in string name,
    out string value
) raises (TypeMismatch);
boolean [get_list](#it_configconfiguration-interface)(
    in string name,
    out ConfigList value
) raises (TypeMismatch);
boolean [get_boolean](#it_configconfiguration-interface)(
    in string name,
    out boolean value
) raises (TypeMismatch);
boolean [get_long](#it_configconfiguration-interface)(
    in string name,
    out long value
) raises (TypeMismatch);
boolean [get_double](#it_configconfiguration-interface)(
    in string name,
    out double value
) raises (TypeMismatch);
void [register_listener](#it_configconfiguration-interface)(
    in string target,
    in ListenerTargetRange target_scope,
    in Listener l
);
void [remove_listener](#it_configconfiguration-interface)(
    in Listener l
);
// INTERNAL USE ONLY
//
void [shutdown()](#it_configconfiguration-interface);
};

```

Configuration::register_listener()

// IDL

```
void register_listener(
    in string target,
    in ListenerTargetRange target_scope,
    in Listener l
);
```

Adds a Listener object so your application can be notified of certain configuration changes.

Parameters

<code>target</code>	The target configuration value for the Listener.
<code>target_scope</code>	The scope parameter determines the extent of change that the Listener is told about.
<code>l</code>	The Listener object.

Not all types of configuration domains support change notification.

Enhancement This is an Orbix enhancement.

See Also [IT_Config::ListenerTargetRange](#)

```
IT_Config::Configuration::remove_listener()
```

`Configuration::get_boolean()`

// IDL

```
boolean get_boolean(
    in string name,
    out boolean value
) raises (TypeMismatch);
```

Returns true if the boolean value is successfully retrieved and false if the variable could not be found.

Parameters

<code>name</code>	Name of the variable to retrieve.

value	The value of the variable returned.

EnhancementThis is an Orbix enhancement.

Exceptions

TypeMismatch

The variable exists but is of the wrong type for this operation.

Configuration::get_double()

// IDL

```
boolean get_double(  
    in string name,  
    out double value  
) raises (TypeMismatch);
```

Returns true if the double value is successfully retrieved and false if the variable could not be found.

Parameters

name	Name of the variable to retrieve.
value	The value of the variable returned.

EnhancementThis is an Orbix enhancement.

Exceptions

TypeMismatch

The variable exists but is of the wrong type for this operation.

Configuration::get_list()

// IDL

```
boolean get_list(
    in string      name,
    out ConfigList value
) raises (TypeMismatch);
```

Returns true if the list of configuration settings is successfully retrieved and false if the list could not be found.

Parameters

name	Name of the configuration list to retrieve.
value	The values returned.

EnhancementThis is an Orbix enhancement.

Exceptions

TypeMismatch

The variable exists but is of the wrong type for this operation.

Configuration::get_long()

// IDL

```
boolean get_long(
    in string name,
    out long  value
) raises (TypeMismatch);
```

Returns true if the long value is successfully retrieved and false if the variable could not be found.

Parameters

name	Name of the variable to retrieve.
value	The value of the variable returned.

EnhancementThis is an Orbix enhancement.

Exceptions

TypeMismatch

The variable exists but is of the wrong type for this operation.

Configuration::get_string()

// IDL

```
boolean get_string(
    in string name,
    out string value
) raises (TypeMismatch);
```

Returns true if the string value is successfully retrieved and false if the variable could not be found.

Parameters

name	Name of the variable to retrieve.
value	The value of the variable returned.

EnhancementThis is an Orbix enhancement.

Exceptions

TypeMismatch

The variable exists but is of the wrong type for this operation.

Configuration::remove_listener()

// IDL

```
void remove_listener(
    in Listener l
);
```

Removes a Listener object.

EnhancementThis is an Orbix enhancement.

See AlsoIT_Config::Configuration::add_listener()

Configuration::shutdown()

// IDL

```
void shutdown();
```

 Note

For internal use only

Configuration::TypeMismatch Exception

// IDL

```
exception TypeMismatch {};
```

The type of the configuration variable named in the operation does not match the type required for the operation.

EnhancementThis is an Orbix enhancement.

IT_Config::Listener Interface

You can add a `Listener` object to your application that will be notified of configuration changes that occur. Use `add_listener()` and `remove_listener()` of the Configuration interface to manage a `Listener` object.

```
// IDL in module IT_Config
```

```

interface VariableListener : Listener {
    void variable_added(
        in string name
    );
    void variable_removed(
        in string name
    );
    void [string_changed](#it_configlistener-interface)(
        in string name,
        in string new_value,
        in string old_value
    );
    void [list_changed](#it_configlistener-interface)(
        in string      name,
        in ConfigList new_value,
        in ConfigList old_value
    );
    void [boolean_changed](#it_configlistener-interface)(
        in string name,
        in boolean new_value,
        in boolean old_value
    );
    void [long_changed](#it_configlistener-interface)(
        in string name,
        in long   new_value,
        in long   old_value
    );
    void [double_changed](#it_configlistener-interface)(
        in string name,
        in double new_value,
        in double old_value
    );
};

```

Listener::variable_added()

```

void variable_added(
    in string name;
)

```

The application is notified in a variable is added to the configuration.

Parameters

name

The name of the variable added.

EnhancementThis is an Orbix enhancement.

Listener::variable_removed()

```
void variable_removed(
    in string name;
)
```

The application is notified in a variable is removed from the configuration.

Parameters

name

The name of the variable removed.

EnhancementThis is an Orbix enhancement.

Listener::boolean_changed()

// IDL

```
void boolean_changed(
    in string name,
    in boolean new_value,
    in boolean old_value
);
```

The application is notified if the boolean value changes.

Parameters

name	The name of the variable.
new_value	The value of the variable after the change occurred. If a variable is deleted this value will be NULL.

<code>old_value</code>	The previous value of the variable before the change occurred. If a variable is added this value will be NULL.

EnhancementThis is an Orbix enhancement.

Listener::double_changed()

// IDL

```
void double_changed(
    in string name,
    in double new_value,
    in double old_value
);
```

The application is notified if the double value changes.

Parameters

<code>name</code>	The name of the variable.
<code>new_value</code>	The value of the variable after the change occurred. If a variable is deleted this value will be NULL.
<code>old_value</code>	The previous value of the variable before the change occurred. If a variable is added this value will be NULL.

EnhancementThis is an Orbix enhancement.

Listener::list_changed()

// IDL

```
void list_changed(
    in string      name,
    in ConfigList new_value,
    in ConfigList old_value
);
```

The application is notified if the configuration list changes.

Parameters

<code>name</code>	The name of the variable.
<code>new_value</code>	The value of the variable after the change occurred. If a variable is deleted this value will be NULL.
<code>old_value</code>	The previous value of the variable before the change occurred. If a variable is added this value will be NULL.

EnhancementThis is an Orbix enhancement.

Listener::long_changed()

// IDL

```
void long_changed(
    in string name,
    in long    new_value,
    in long    old_value
);
```

The application is notified if the long value changes.

Parameters

<code>name</code>	The name of the variable.
<code>new_value</code>	The value of the variable after the change occurred. If a variable is deleted this value will be NULL.
<code>old_value</code>	The previous value of the variable before the change occurred. If a variable is added this value will be NULL.

EnhancementThis is an Orbix enhancement.

Listener::string_changed()

// IDL

```
void string_changed(  
    in string name,  
    in string new_value,  
    in string old_value  
);
```

The application is notified if the string value changes.

Parameters

name	The name of the variable.
new_value	The value of the variable after the change occurred. If a variable is deleted this value will be NULL.
old_value	The previous value of the variable before the change occurred. If a variable is added this value will be NULL.

EnhancementThis is an Orbix enhancement.

IT_CORBA Overview

This module contains Orbix enhancements to the CORBA module. The key additional feature is the policy `WellKnownAddressingPolicy`. The classes include:

- `RefCountedLocalObject`
- `RefCountedLocalObjectNC`
- `WellKnownAddressingPolicy`

The IDL code is as follows:

IT_CORBA::WELL_KNOWN_ADDRESSING_POLICY_ID Constant

// IDL in module IT_CORBA

```
const CORBA::PolicyType WELL_KNOWN_ADDRESSING_POLICY_ID =
    IT_PolicyBase::IONA_POLICY_ID + 2;
```

// C++ in namespace IT_CORBA

```
IT_ART_API IT_NAMESPACE_STATIC
    const CORBA::ULong WELL_KNOWN_ADDRESSING_POLICY_ID;
```

Defines a policy ID for well-known addressing.

Enhancement This is an Orbix enhancement to CORBA.

See Also `CORBA::PolicyType`

IT_CORBA::RefCountedLocalObject Class

`RefCountedLocalObject` is an implementation of a `CORBA` local object that automatically handles reference counting in a thread safe manner.

```
// in namespace IT_CORBA
...
class IT_ART_API RefCountedLocalObject :
public CORBA::LocalObject {
public:
    [RefCountedLocalObject()](#it_corbarefcountedlocalobject-class);
    void [_add_ref()](#it_corbarefcountedlocalobjectnc-class);
    void [_remove_ref()](#it_corbarefcountedlocalobjectnc-class);
protected:
    virtual void [_destroy_this()](#it_corbarefcountedlocalobjectnc-class);
private:
    ...
};
```

See Also `IT_CORBA::RefCountedLocalObjectNC`

`RefCountedLocalObject::_add_ref()`

`void _add_ref();`

Increments the reference count.

Enhancement This is an Orbix enhancement to CORBA.

`RefCountedLocalObject::_destroy_this()`

`virtual void _destroy_this();`

Destroys the local object.

Enhancement This is an Orbix enhancement to CORBA.

`RefCountedLocalObject::RefCountedLocalObject()` Constructor

`RefCountedLocalObject();`

The constructor.

Enhancement This is an Orbix enhancement to CORBA.

RefCountedLocalObject::_remove_ref()

void _remove_ref()

Decrements the reference count.

Enhancement This is an Orbix enhancement to CORBA.

IT_CORBA::RefCountedLocalObjectNC Class

`RefCountedLocalObjectNC` is an implementation of a `CORBA` local object that automatically handles reference counting but not in a thread-safe manner as the `RefCountedLocalObject` class does. A `RefCountedLocalObjectNC` object does not protect its reference count with a mutex, making it suitable for lightweight objects such as `CORBA::Request`.

```
// in namespace IT_CORBA
...
class IT_ART_API RefCountedLocalObjectNC :
public CORBA::LocalObject {
public:
    [RefCountedLocalObjectNC()](#it_corbarefcountedlocalobjectnc-class);
    void [_add_ref()](#it_corbarefcountedlocalobjectnc-class);
    void [_remove_ref()](#it_corbarefcountedlocalobjectnc-class);
protected:
    virtual void [_destroy_this()](#it_corbarefcountedlocalobjectnc-class);
private:
    ...
}
```

See Also `IT_CORBA::RefCountedLocalObject`

`RefCountedLocalObjectNC::_add_ref()`

`void _add_ref();`

Increments the reference count.

Enhancement This is an Orbix enhancement to `CORBA`.

`RefCountedLocalObjectNC::_destroy_this()`

`virtual void _destroy_this();`

Destroys the local object.

Enhancement This is an Orbix enhancement to `CORBA`.

`RefCountedLocalObjectNC::RefCountedLocalObjectNC()` Constructor

`RefCountedLocalObjectNC();`

The constructor.

EnhancementThis is an Orbix enhancement to CORBA.

RefCountedLocalObjectNC::_remove_ref()

void _remove_ref();

Decrements the reference count.

EnhancementThis is an Orbix enhancement to CORBA.

IT_CORBA::WellKnownAddressingPolicy Class

This is an interface for a local policy object derived from CORBA :: Policy. You create instances of `WellKnownAddressingPolicy` by calling `CORBA :: ORB :: create_policy()`.

```
// in namespace IT_CORBA
...
class IT_ART_API WellKnownAddressingPolicy :
public virtual ::CORBA::Policy {
public:
    typedef IT_CORBA::WellKnownAddressingPolicy_ptr _ptr_type;
    typedef IT_CORBA::WellKnownAddressingPolicy_var _var_type;
    virtual [~WellKnownAddressingPolicy()]
    (#it_corbawellknownaddressingpolicy-class);
    static WellKnownAddressingPolicy_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static WellKnownAddressingPolicy_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static WellKnownAddressingPolicy_ptr _duplicate(
        WellKnownAddressingPolicy_ptr p
    );
    inline static WellKnownAddressingPolicy_ptr _nil();
    virtual char* [config_scope()](#it_corbawellknownaddressingpolicy-class)
    = 0;
    static const IT_FWString _it_fw_type_id;
};
```

for descriptions of the standard helper functions:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`WellKnownAddressingPolicy::config_scope()`

// C++

```
virtual char* config_scope() = 0;
```

Returns the configuration scope.

EnhancementThis is an Orbix enhancement to CORBA.

WellKnownAddressingPolicy::~~WellKnownAddressingPolicy() Destructor

```
virtual ~WellKnownAddressingPolicy();
```

The destructor for this policy object.

EnhancementThis is an Orbix enhancement to CORBA.

IT_CORBASEC

The IT_CORBASEC Module

A module that gives you read/write access to extended received credentials.

Description

In particular, the IT_CORBASEC::ExtendedReceivedCredentials interface gives you access to the received SSO tokens.

IT_CORBASEC::EXT_ATTR_ERR_ATTR_NOT_PRESENT

Raised by `get_extended_attribute()`, if the requested attribute is not present.

Description

If this exception is raised, it implies that the requested attribute is neither present in the incoming request's service contexts nor has the requested attribute been set by a call to IT_CORBASEC::ExtendedReceivedCredentials::set_extended_attribute().

IT_CORBASEC::EXT_ATTR_ERR_FAILURE_PROCESSING_ATTR

Not used.

IT_CORBASEC::EXT_ATTR_ERR_READ_ONLY_ATTRIBUTE

Raised by `set_extended_attribute()`, if the requested attribute is intended to be read-only.

Description

Specifically, this error is raised if you attempt to set the IT_CORBASEC::EXT_ATTR_CURRENT_SSO_TOKEN attribute directly.

IT_CORBASEC::ExtendedAttributeError

Exception raised by operations from the `IT_CORBASEC::ExtendedReceivedCredentials` interface.

See Also IT_CORBASEC::EXT_ATTR_ERR_ATTR_NOT_PRESENT

```
IT_CORBASEC::EXT_ATTR_ERR_READ_ONLY_ATTRIBUTE
```

IT_CORBASEC::SSOTokenString

Type of an SSO token.

Description

An `SSOTokenString` can be extracted from the `any` returned from a call to `IT_CORBASEC::ExtendedReceivedCredentials::get_extended_attribute()`, if the requested attribute is an SSO token.

An `SSOTokenString` can be inserted into an `any` and passed in a call to `IT_CORBASEC::ExtendedReceivedCredentials::set_extended_attribute()` to set an SSO token attribute.

See also

`IT_CORBASEC::EXT_ATTR_CURRENT_SSO_TOKEN`

`IT_CORBASEC::EXT_ATTR_DELEGATED_SSO_TOKEN`

`IT_CORBASEC::EXT_ATTR_PEER_SSO_TOKEN`

`IT_CORBASEC::EXT_ATTR_CURRENT_SSO_TOKEN`

The attribute type for the current SSO token, which can be either a delegated token or a peer token.

Description

The current SSO token is the token that would be used when making access control decisions for the incoming invocation. The value returned for the current SSO token can be one of the following (in order of priority):

- Delegated SSO token, if it is present, otherwise
- Peer SSO token, if it is present, otherwise
- No value.

See also

`IT_CORBASEC::EXT_ATTR_DELEGATED_SSO_TOKEN`

`IT_CORBASEC::EXT_ATTR_PEER_SSO_TOKEN`

`IT_CORBASEC::EXT_ATTR_DELEGATED_SSO_TOKEN`

The attribute type for a delegated SSO token.

Description

In a multi-tier system (consisting of at least three tiers), a *delegated SSO token* represents a credential that originated at least two steps back in the invocation chain.

Currently, the only security mechanism in Orbix that supports delegation is CSI Identity Assertion.

The delegated token originates from a previous application in the invocation chain and is always copied into the effective credentials for the current execution context. Hence, in a multi-tiered system, the delegated SSO token received from the preceding application would automatically be used as the delegated credentials for the next invocation in the chain.

IT_CORBASEC::EXT_ATTR_PEER_SSO_TOKEN

The attribute type for a peer SSO token.

Description

A *peer SSO token* represents a credential that originates from the preceding application in the invocation chain and is received through the CSI authentication over transport mechanism.

A peer SSO token is available from an incoming request message on the server side, if the following conditions hold:

- Server is configured to use CSI authentication over transport.
- Client is configured to use CSI authentication over transport.
- Client is configured to use *either* username/password-based SSO *or* X.509 certificate-based SSO.

If there are no delegated credentials in the received credentials, the peer SSO token is used as the delegated credential in the current execution context. Hence, in the absence of received delegated credentials, the peer SSO token received from the preceding application is used as the delegated credentials for the next invocation in the chain.

IT_CORBASEC::ExtendedReceivedCredentials

A Rocket Software-specific interface that allows access to additional Rocket Software-specific logical attributes of a received credentials object.

Description

An instance of a received credentials object is obtained by narrowing the received credentials object obtained from security current.

The attribute IDs passed as arguments to the `get_extended_attribute()` and `set_extended_attribute()` operations are assigned by Rocket Software. The range below 10000 is reserved for Rocket Software use. These numbers are unique across all security mechanisms.

C++ implementation

The following code example shows you how to obtain an `ExtendedReceivedCredentials` instance:

```
// C++
CORBA::Object_var obj = orb->resolve_initial_references(
"SecurityCurrent"
);
SecurityLevel2::Current_var sec_current =
SecurityLevel2::Current::_narrow(obj);
SecurityLevel2::ReceivedCredentials_var rec_creds =
sec_current->received_credentials();
IT_CORBASEC::ExtendedReceivedCredentials_var extended_rec_creds =
IT_CORBASEC::ExtendedReceivedCredentials::_narrow(rec_creds);
if (CORBA::is_nil(extended_rec_creds))
{
// Error: Extended creds should be available if GSP is loaded.
}
```

See also

SecurityLevel2::Current

SecurityLevel2::ReceivedCredentials

IT_CORBASEC::ExtendedReceivedCredentials::get_extended_attribute()

Returns the value of a received credentials' extended attribute.

Description

There are two possible origins of an extended attribute:

- From parsing a service context in the incoming request message.
- From a previous call to `set_extended_attribute()`, which set the attribute value on the received credentials object.

C++ implementation

The following example shows how to extract a current SSO token from an extended received credentials object:

```

// C++
CORBA::Any_var token_any;
char * s = 0;
...
// Get current security token from extended credentials.
try {
token_any = extended_rec_creds->get_extended_attribute(
IT_CORBASEC::EXT_ATTR_CURRENT_SSO_TOKEN
);
}
catch(IT_CORBASEC::ExtendedAttributeError e) {
if (e.error_reason == IT_CORBASEC::EXT_ATTR_ERR_ATTR_NOT_PRESENT)
{
// Error: Attribute is not set.
}
}
if (token_any==0)
{
// Error: No token available!
}
if (token_any >= s)
{
cout << "Current SSO token: " << s << endl;
}
else {
// Error: Current SSO Token empty.
}
}

```

Returns The value of an extended attribute contained in an `any`.

Parameters

`req_attribute`

An integer attribute ID, which identifies a particular extended attribute.

Exceptions

`ExtendedAttributeError`

Raised with an `error_reason` of `EXT_ATTR_ERR_ATTR_NOT_PRESENT` if the requested attribute is not set.

`IT_CORBASEC::ExtendedReceivedCredentials::set_extended_attribute()`

Sets the value of a received credentials' extended attribute.

Description

The main purpose of setting an extended attribute is to influence subsequent remote CORBA invocations within the current execution context. The received credentials can affect subsequent

invocations, because Orbix takes received credentials into account when creating the effective credentials for a new invocation.

For example, if a delegated SSO token attribute is set in the received credentials, it would automatically be copied into the effective credentials for a new invocation (by the GSP plug-in).

C++ implementation

The following example shows how to insert a peer SSO token into an extended received credentials object:

```
// C++
CORBA::Any peer_any_val <= "PeerTokenString";
...
try {
    extended_rec_creds->set_extended_attribute(
        IT_CORBASEC::EXT_ATTR_PEER_SSO_TOKEN,
        peer_any_val
    );
}
catch(IT_CORBASEC::ExtendedAttributeError e) {
    if (e.error_reason == IT_CORBASEC::EXT_ATTR_ERR_READ_ONLY_ATTRIBUTE)
    {
        // Error: Attribute is not intended to be settable.
    }
}
```

Parameters

attribute_type

An integer attribute ID, which identifies a particular extended attribute.

any_val

The value of an extended attribute contained in an `any`.

Exceptions

ExtendedAttributeError

Raised with an `error_reason` of `EXT_ATTR_ERR_READ_ONLY_ATTRIBUTE` if the requested attribute is not intended to be settable.

IT_CosTransactions Module

The `IT_CosTransactions` module contains Orbix 2000 enhancements to the standard OTS CosTransactions module. The `IT_CosTransactions` module includes additional values for the `OTSPolicyValue` data type and proprietary extensions to the standard `CosTransactions :: Current` class.

Additional OTSPolicyValues

```
const OTSPolicyValue AUTOMATIC = 4;
const OTSPolicyValue SERVER_SIDE = 5;
```

These additional `OTSPolicyValue`s indicate the following:

<code>AUTOMATIC</code>	The target object depends on the presence of a transaction. If there is no current transaction, a transaction is created for the duration of the invocation.
<code>SERVER_SIDE</code>	The target object is invoked within the current transaction whether there is a transaction or not. This policy depends on just-in-time transaction creation. You can enable just-in-time transactions by setting the following configuration variable to <code>true</code>: <pre>plugins:ots:jit_transactions</pre> If a transaction has begun but is not fully created, the transaction is created before the target object is invoked.

You cannot create a POA that mixes the `AUTOMATIC` or `SERVER_SIDE` `OTSPolicyValue` with the `EITHER` or `UNSHARED` `InvocationPolicyValue`. Attempting to do this results in the `PortableServer :: InvalidPolicy` exception being raised.

See Also `CosTransactions::OTSPolicyValue`

IT_CSI Overview

The `IT_CSI` module defines Orbix-specific policy interfaces that enable you to set CSiv2 policies programmatically. An `IT_CSI::IT_CSI_AUTH_METHOD_USERNAME_PASSWORD` constant is defined that enables you to create credentials on the client side using the `SecurityLevel2::PrincipalAuthenticator`. The module also defines proprietary credentials interfaces (giving you access to CSiv2-related credentials on the server side) and an `AuthenticateGSSUPCredentials` interface that enables you to implement a custom authentication service.

The module contains the following IDL interfaces:

- `IT_CSI::AuthenticateGSSUPCredentials` Interface
- `IT_CSI::AuthenticationServicePolicy` Interface
- `IT_CSI::AttributeServicePolicy` Interface
- `IT_CSI::CSICredentials` Interface
- `IT_CSI::CSIReceivedCredentials` Interface
- `IT_CSI::CSICurrent` Interface

Associated with the CSiv2 policies, the `IT_CSI` module defines the following policy type constants (of `CORBA::PolicyType` type):

```
IT_CSI::CSI_CLIENT_AS_POLICY
IT_CSI::CSI_SERVER_AS_POLICY
IT_CSI::CSI_CLIENT_SAS_POLICY
IT_CSI::CSI_SERVER_SAS_POLICY
```

`IT_CSI::IT_CSI_AUTH_METH_USERNAME_PASSWORD`

```
const Security::AuthenticationMethod IT_CSI_AUTH_METH_USERNAME_PASSWORD =
6;
```

This constant identifies CSiv2 username/password authorization method. When calling the `SecurityLevel2::PrincipalAuthenticator::authenticate()` operation, the `IT_CSI_AUTH_METH_USERNAME_PASSWORD` constant can be passed as the `method` parameter.

See Also `SecurityLevel2::PrincipalAuthenticator`

IT_CSI::GSSUPAuthData

IT_CSI::GSSUPAuthData Structure

```
struct GSSUPAuthData
{
    string password;
    string domain;
};
```

This structure is used to pass the GSSUP password and authentication domain name to the `SecurityLevel12::PrincipalAuthenticator::authenticate()` operation. It is used in combination with the `IT_CSI::IT_CSI_AUTH_METH_USERNAME_PASSWORD` authentication method identifier.

This structure contains the following fields:

<code>password</code>	The GSSUP password for this login.
<code>domain</code>	The CSIv2 authentication domain for this login.

See Also `IT_CSI::IT_CSI_AUTH_METH_USERNAME_PASSWORD`

IT_CSI::CSI_POLICY_BASE

```
const unsigned long CSI_POLICY_BASE = IT_PolicyBase::IONA_POLICY_ID + 11;
```

The base for a range of CSIv2 policy constants.

See Also `IT_CSI::CSI_CLIENT_AS_POLICY`

```
IT_CSI::CSI_SERVER_AS_POLICY
IT_CSI::CSI_CLIENT_SAS_POLICY
IT_CSI::CSI_SERVER_SAS_POLICY
```

IT_CSI::CSI_CLIENT_AS_POLICY

```
const CORBA::PolicyType CSI_CLIENT_AS_POLICY = CSI_POLICY_BASE;
```

The flag identifying the client-side authentication service policy.

See Also `IT_CSI::CSI_SERVER_AS_POLICY`

```
IT_CSI::AuthenticationServicePolicy
```

```
IT_CSI::CSI_SERVER_AS_POLICY
```

```
const CORBA::PolicyType CSI_SERVER_AS_POLICY = CSI_POLICY_BASE+1;
```

The flag identifying the server-side authentication service policy.

See Also `IT_CSI::CSI_CLIENT_AS_POLICY`

```
IT_CSI::AuthenticationServicePolicy
```

```
IT_CSI::CSI_CLIENT_SAS_POLICY
```

```
const CORBA::PolicyType CSI_CLIENT_SAS_POLICY = CSI_POLICY_BASE+2;
```

The flag identifying the client-side attribute service policy.

See Also `IT_CSI::CSI_SERVER_SAS_POLICY`

```
IT_CSI::AttributeServicePolicy
```

```
IT_CSI::CSI_SERVER_SAS_POLICY
```

```
const CORBA::PolicyType CSI_SERVER_SAS_POLICY = CSI_POLICY_BASE+3;
```

The flag identifying the server-side attribute service policy.

See Also `IT_CSI::CSI_CLIENT_SAS_POLICY`

```
IT_CSI::AttributeServicePolicy
```

```
IT_CSI::AuthenticationService Structure
```

```

struct AuthenticationService
{
    // Client and server side.
    CSIIOP::AssociationOptions support;
    // Server side only.
    CSIIOP::AssociationOptions requires;
    string client_authentication_mech;
    string target_name;
    AuthenticateGSSUPCredentials as_object;
};

```

This structure, in conjunction with the `IT_CSI::AuthenticationServicePolicy` interface, provides a programmatic approach to enabling the CSiv2 authentication service policy. This structure has a dual purpose, because it can be used to set both a client-side policy, `IT_CSI::CSI_CLIENT_AS_POLICY`, and a server-side policy, `IT_CSI::CSI_SERVER_AS_POLICY`.

This structure contains the following fields:

<code>support</code>	<i>(Client and server)</i> The list of association options <i>supported</i> by the authentication service policy. Currently, only the <code>CSIIOP::EstablishTrustInClient</code> association option can be included in this list.
<code>requires</code>	<i>(Server only)</i> The list of association options <i>required</i> by the authentication service policy on the server side. Currently, only the <code>CSIIOP::EstablishTrustInClient</code> association option can be included in this list.
<code>client_authentication_mech</code>	<i>(Server only)</i> The authentication mechanism OID, which identifies the mechanism used by CSiv2 authentication. For example, <code>GSSUP::GSSUPMechOID</code> is a valid setting.
<code>target_name</code>	<i>(Server only)</i> The name of the security policy domain (CSiv2 authentication domain) for this authentication service.
<code>as_object</code>	<i>(Server only)</i> A reference to the GSSUP authentication service object that will be used to authenticate GSS username/password combinations on the server side.

See Also `IT_CSI::AuthenticationServicePolicy`

```
IT_CSI::CSI_CLIENT_AS_POLICY
IT_CSI::CSI_SERVER_AS_POLICY
```

IT_CSI::SupportedNamingMechanisms Sequence

```
typedef sequence<string> SupportedNamingMechanisms;
```

The list of naming mechanisms supported by CSIv2. Currently, the only supported naming mechanism is `CSI::GSS_NT_Export_Name_OID`.

See Also `CSI::GSS_NT_Export_Name_OID`

```
IT_CSI::AttributeService
```

IT_CSI::AttributeService Structure

```
struct AttributeService
{
    CSIIOP::AssociationOptions support;
    SupportedNamingMechanisms supported_naming_mechs;
    CSI::IdentityTokenType supported_identity_types;
};
```

This structure, in conjunction with the `IT_CSI::AttributeServicePolicy` interface, provides a programmatic approach to enabling the CSIv2 attribute service policy. This structure has a dual purpose, because it can be used to set both a client-side policy, `IT_CSI::CSI_CLIENT_SAS_POLICY`, and a server-side policy, `IT_CSI::CSI_SERVER_SAS_POLICY`.

This structure contains the following fields:

<code>support</code>	(<i>Client and server</i>) The list of association options <i>supported</i> by the attribute service policy. Currently, only the <code>CSIIOP::IdentityAssertion</code> association option can be included in this list.
<code>supported_naming_mechs</code>	(<i>Server only</i>) A list of GSS naming mechanism OIDs, which identify the formats that may be used in the <code>CSI::ITTPPrincipalName</code> identity token. For example, <code>CSI::GSS_NT_Export_Name_OID</code> is a valid naming mechanism string.

supported_identity_types	<i>(Server only)</i> The bitmapped representation of the set of identity token types supported by the target. In the current implementation of Orbix, the value of this attribute should be <code>0x03</code> (which represents a combination of the <code>ITTAAnonymous</code> flag and the <code>ITTPPrincipalName</code> flag)..

See Also `IT_CSI::AttributeServicePolicy`

```

CSI::GSS_NT_Export_Name_OID
IT_CSI::CSI_CLIENT_SAS_POLICY
IT_CSI::CSI_SERVER_SAS_POLICY

```

`IT_CSI::CSICredentialsType` Enumeration

```

enum CSICredentialsType {
    GSSUPCredentials,
    PropagatedCredentials,
    TransportCredentials
};

```

An enumeration to identify the type of credentials contained in a CSIV2 credentials object. The credentials can be one of the following types:

- `GSSUPCredentials` —a set of GSS username/password credentials (authenticated on the server side), received through the CSIV2 authorization over transport mechanism.
- `PropagatedCredentials` —a set of propagated credentials (not authenticated on the server side), received through the CSIV2 identity assertion mechanism.
- `TransportCredentials` —a set of SSL/TLS credentials (typically containing an X.509 certificate chain), received through the transport layer.

See Also `IT_CSI::CSICredentials`

```

IT_CSI::CSIReceivedCredentials

```


IT_CSI::AttributeServicePolicy Interface

```
// IDL in module IT_CSI
local interface AttributeServicePolicy : CORBA::Policy
{
    // The following attribute, supports, is for client and server
    // side
    readonly attribute CSIIOP::AssociationOptions support;
    // Server specific attributes used in IOR generation
    readonly attribute CSI::OIDList supported_naming_mechanisms;
    readonly attribute CSI::IdentityTokenType
                                supported_identity_types;
    readonly attribute boolean backward_trust_enabled;
    readonly attribute CSIIOP::ServiceConfigurationList
                                privilege_authorities;
};
```

The policy type for the CSIV2 attribute service policy, which is used to enable the CSIV2 *identity assertion* mechanism. This interface, in conjunction with the `IT_CSI::AttributeService` struct, provides a programmatic approach to enabling the CSIV2 attribute service policy. The functionality provided is equivalent to that which is available by setting the following configuration variables:

```
policies:csi:attribute_service:client_supports
policies:csi:attribute_service:target_supports
policies:csi:attribute_service:backward_trust:enabled
```

This `AttributeServicePolicy` interface has a dual purpose. It can represent either a client-side policy, `IT_CSI::CSI_CLIENT_SAS_POLICY`, or a server-side policy, `IT_CSI::CSI_SERVER_SAS_POLICY`.

See Also `IT_CSI::CSI_CLIENT_SAS_POLICY`

```
IT_CSI::CSI_SERVER_SAS_POLICY
IT_CSI::AttributeService
IT_CSI::AuthenticationServicePolicy
```

`AttributeServicePolicy::support`

```
readonly attribute CSIIOP::AssociationOptions support;
```

The list of association options *supported* by the attribute service policy. Currently, only the `CSIIOP::IdentityAssertion` association option can be included in this list.

The effect of including the `CSIIOP::IdentityAssertion` association option in the list depends on whether the `AttributeServicePolicy` is set as a client-side policy (`IT_CSI::CSI_CLIENT_SAS_POLICY`) or as a server-side policy (`IT_CSI::CSI_SERVER_SAS_POLICY`), as follows:

- Client side—supports the propagation of an identity to the server using the CSiv2 identity assertion mechanism. This is equivalent to the `policies:csi:attribute_service:client_supports` configuration variable.
- Server side—supports the receipt of an identity (which is presumed to have been already authenticated) from the client using the CSiv2 identity assertion mechanism. This is equivalent to the `policies:csi:attribute_service:target_supports` configuration variable.

See Also `CSIIOP::IdentityAssertion`

`AttributeServicePolicy::supported_naming_mechanisms`

```
readonly attribute CSI::OIDList supported_naming_mechanisms;
```

A list of GSS naming mechanism OIDs, which identify the formats that may be used in the `CSI::ITTPPrincipalName` identity token. In the current implementation of Orbix, the `supported_naming_mechanisms` list would normally include a binary representation of the `CSI::GSS_NT_Export_Name_OID` naming mechanism OID.

See Also `CSI::ITTPPrincipalName`

```
CSI::GSS_NT_Export_Name_OID
```

`AttributeServicePolicy::supported_identity_types`

```
readonly attribute CSI::IdentityTokenType supported_identity_types;
```

The bitmapped representation of the set of identity token types supported by the target. In the current implementation of Orbix, the value of this attribute would be `0x00000003`, which represents a combination of the `ITTAonymous` flag (`0x01`) and the `ITTPPrincipalName` flag (`0x02`). The `ITTAbsent` identity token is always supported.

The `ITTX509CertChain` identity token and the `ITTDistinguishedName` identity token are *not* supported in the current implementation. Hence, the corresponding flags for these identity tokens cannot be set.

See Also `CSI::ITTAbsent`

```
CSI::ITTAnonymous
CSI::ITTPrincipalName
```

`AttributeServicePolicy::backward_trust_enabled`

```
readonly attribute boolean backward_trust_enabled;
```

Not used in the current implementation.

`AttributeServicePolicy::privilege_authorities`

```
readonly attribute CSIIOP::ServiceConfigurationList privilege_authorities;
```

A list of authorization tokens. This feature is currently not supported by Orbix (that is, it returns an empty list).

IT_CSI::AuthenticateGSSUPCredentials Interface

```
// IDL in module IT_CSI
interface AuthenticateGSSUPCredentials
{
    readonly attribute string authentication_service;
    boolean authenticate (
        in string username,
        in string password,
        in string target_name,
        in string request_name,
        in string object_name,
        out GSSUP::ErrorCode error_code);
};
```

A callback interface that you can optionally implement to provide a custom authentication service for a CSiv2 server. When using the CSiv2 authentication over transport mechanism (enabled by the CSiv2 authentication service policy), the `AuthenticateGSSUPCredentials::authenticate()` operation is invoked for every incoming request from a client. This gives you the opportunity to accept or reject every incoming invocation based on the authentication data provided by the client.

Note that this *stateless* mode of operation (calling `authenticate()` for every invocation) is the only kind of session semantics currently supported by Orbix. The *stateful* mode of operation (calling `authenticate()` once at the beginning of a session) is currently *not* supported.

You can install an implementation of `AuthenticateGSSUPCredentials` in either of the following ways:

- *By configuration*—you can specify the `AuthenticateGSSUPCredentials` implementation class by setting the following configuration variable:

```
policies:csi:auth_over_transport:authentication_service
```

The named class is then loaded and instantiated by the CSiv2 plug-in.

- *By programming*—you can register an instance of the `AuthenticateGSSUPCredentials` implementation class by setting the `as_object` field of the `IT_CSI::AuthenticationServicePolicy`.

See Also `IT_CSI::AuthenticationServicePolicy`

AuthenticateGSSUPCredentials::authentication_service Attribute

```
readonly attribute string authentication_service;
```

The name of the authentication service implementation. There are no particular conditions imposed on the value of this attribute; it is just a short descriptive string.

AuthenticateGSSUPCredentials::authenticate()

```
boolean authenticate (
    in string username,
    in string password,
    in string target_name,
    in string request_name,
    in string object_name,
    out GSSUP::ErrorCode error_code);
```

A callback operation that performs authentication on a GSSUP username/password combination. When CSiv2 authentication over transport is enabled, the `authenticate()` operation is called for every incoming request on the server side. If the return value is TRUE, the request is allowed to proceed; if the return value is FALSE, the request is rejected.

ParametersThe `authenticate()` operation takes the following parameters:

<code>username</code>	The username received from the client through the CSiv2 authentication over transport mechanism.
<code>password</code>	The password received from the client through the CSiv2 authentication over transport mechanism.
<code>target_name</code>	The security policy domain name (CSiv2 authentication domain) received from the client through the CSiv2 authentication over transport mechanism.
<code>request_name</code>	The name of the operation (or attribute accessor/modifier) to be invoked by this request. The format of this argument is the same as the operation name in a GIOP request header. See, for example, the description of <code>GIOP::RequestHeader_1_2::operation</code> in section 15.4.2 of the CORBA 2.4.2 core specification.

<code>object_name</code>	The type identifier for the target of this invocation, expressed as a CORBA repository ID. For example, the <code>CosNaming::NamingContext</code> type would be identified by the <code>IDL:omg.org/CosNaming/NamingContext:1.0</code> repository ID string.
<code>error_code</code>	The returned GSSUP error code (long integer). A non-zero value indicates that an error occurred.

See Also `IT_CSI::AuthenticationServicePolicy`

IT_CSI::AuthenticationServicePolicy Interface

```
// IDL in module IT_CSI
local interface AuthenticationServicePolicy : CORBA::Policy
{
    // The following attribute, supports, is for client and server
    // side
    readonly attribute CSIIOP::AssociationOptions support;
    // Server specific attributes used in IOR generation
    readonly attribute CSIIOP::AssociationOptions target_requires;
    readonly attribute CSI::OID client_authentication_mech;
    readonly attribute CSI::GSS_NT_ExportedName target_name;
    readonly attribute AuthenticateGSSUPCredentials as_object;
};
```

The policy type for the CSiv2 authentication service policy, which is used to enable the CSiv2 *authentication over transport* mechanism. This interface, in conjunction with the `IT_CSI::AuthenticationService` struct, provides a programmatic approach to enabling the CSiv2 authentication service policy. The functionality provided is equivalent to that which is available by setting the following configuration variables:

```
policies:csi:auth_over_transport:client_supports
policies:csi:auth_over_transport:target_supports
policies:csi:auth_over_transport:target_requires
policies:csi:auth_over_transport:server_domain_name
policies:csi:auth_over_transport:authentication_service
```

This `AuthenticationServicePolicy` interface has a dual purpose. It can represent either a client-side authentication policy, `IT_CSI::CSI_CLIENT_AS_POLICY`, or a server-side authentication policy, `IT_CSI::CSI_SERVER_AS_POLICY`.

AuthenticationServicePolicy::support Attribute

```
readonly attribute CSIIOP::AssociationOptions support;
```

The list of association options *supported* by the authentication service policy. Currently, only the `CSIIOP::EstablishTrustInClient` association option can be included in this list.

The `CSIIOP::EstablishTrustInClient` association option can be set either as a client-side policy (`IT_CSI::CSI_CLIENT_AS_POLICY`) or as a server-side policy (`IT_CSI::CSI_SERVER_AS_POLICY`), as follows:

- Client side—supports the propagation of a GSSUP username and password using the CSIV2 authentication mechanism. This is equivalent to the `policies:csi:auth_over_transport:client_supports` configuration variable.
- Server side—supports the authentication of a client's username and password using the CSIV2 authentication mechanism. This is equivalent to the `policies:csi:auth_over_transport:target_supports` configuration variable.

AuthenticationServicePolicy::target_requires Attribute

```
readonly attribute CSIIOP::AssociationOptions target_requires;
```

The list of association options *required* by the authentication service policy on the server side. Currently, only the `CSIIOP::EstablishTrustInClient` association option can be included in this list.

AuthenticationServicePolicy::client_authentication_mech Attribute

```
readonly attribute CSI::OID client_authentication_mech;
```

The authentication mechanism OID, which identifies the mechanism used by CSIV2 authentication on the server side. In the current implementation of Orbix, the only available mechanism is the Generic Security Service username/password (GSSUP) mechanism, represented by `GSSUP::GSSUPMechOID`.

See Also `GSSUP::GSSUPMechOID`

```
CSI::StringOID
```

AuthenticationServicePolicy::target_name Attribute


```
readonly attribute CSI::GSS_NT_ExportedName target_name;
```

The name of the security policy domain (CSIV2 authentication domain) for this authentication service on the server side. In this implementation, a given CSIV2 server can belong to a single security policy domain only. If an incoming client request does not match the server's security policy domain, the client request will be rejected.

AuthenticationServicePolicy::as_object Attribute

```
readonly attribute AuthenticateGSSUPCredentials as_object;
```

A reference to the GSSUP authentication service object that will be used to authenticate GSS username/password combinations on the server side.

IT_CSI::CSICredentials Interface

```
local interface CSICredentials : SecurityLevel2::Credentials
{
    readonly attribute CSICredentialsType csi_credentials_type;
};
```

Rocket Software-specific `CSICredentials` interface that is used as a base interface for CSIv2 credentials. Server implementations may use this interface to determine the clients credentials type—for example, a propagated identity from an intermediary or a username/password.

`CSICredentials::csi_credentials_type` Attribute

```
readonly attribute CSICredentialsType csi_credentials_type;
```

A flag that indicates what type of credentials is returned by the `SecurityLevel2::Current::received_credentials()` operation.

See Also `IT_CSI::CSIReceivedCredentials`

IT_CSI::CSICurrent Interface

```
// IDL in module IT_CSI
local interface CSICurrent : CORBA::Current
{
    boolean set_received_gssup_credentials(in string access_id);
};
```

The operations in this interface are now *deprecated*. Use the `IT_CSI::CSICurrent2` interface instead.

`CSICurrent::set_received_gssup_credentials()`

```
boolean set_received_gssup_credentials(in string access_id);
```

Deprecated. Use `IT_CSI::CSICurrent2::set_received_gssup_credentials_access_id()` instead.

Parameters This operation takes the following parameters:

```
access_id
```

Either the GSSUP username in string format or the common name from an X.509 certificate's subject DN. From the target server, the access ID is made accessible from a `Security::SecAttribute::value` in the form of an `AccessId` encoded as a sequence of octets.

See Also `SecurityLevel2::ReceivedCredentials`

```
SecurityLevel2::Credentials
Security::SecAttribute
```

IT_CSI::CSICurrent2 Interface

```
// IDL in module IT_CSI
local interface CSICurrent2 : CSICurrent
{
    CSIReceivedCredentials
    set_received_gssup_credentials_access_id(
        in string peer_identity
    );
    CSIReceivedCredentials
    set_received_itt_principal_name_identity_token(
        in string asserted_identity
    );
    // RESERVED FOR FUTURE USE
    boolean
    set_csi_received_credentials(
        in CSIReceivedCredentials          rec_creds
    );
};
```

Interface used to set the value of the CSI received credentials in the current execution context. By calling the operations in this interface, you can *simulate* the successfully processed receipt of a CSIV2 asserted identity message and/or the receipt and successful processing of a CSIV2 GSSUP authentication request. These operations should be used only when you do not actually have a CSIV2 execution context; for example, if you were building a bridge between the SOAP protocol and the CORBA GIOP protocol.

Warning

It is critically important to understand that it is *your* responsibility to vet the user identities passed to the `CSICurrent2` operations. If you pass the identity of an unauthorized user into the CSI received credentials object, you could potentially undermine the security of your system completely.

A typical CSIV2 identity assertion scenario involves a client, an intermediate server, and a target server. The client invokes an operation on the intermediate server, with CSIV2 authentication over transport enabled, and the intermediate server invokes an operation on the target server, with CSIV2 identity assertion enabled.

Default values of the CSI received credentials are set automatically by parsing the appropriate GIOP service contexts from the incoming request message. In this case, it is recommended that you do *not* modify the CSI received credentials. The `CSICurrent2` interface is meant to be used *only* to simulate CSI received credentials in a bridging application, not to replace existing credentials.

A programmer can access an `IT_CSI::CSICurrent2` object from within an operation context using the following code:

```
// C++
CORBA::Object_var obj      = orb-
>resolve_initial_references("SecurityCurrent");
IT_CSI::CSICurrent2_var it_csi_current =
IT_CSI::CSICurrent2::_narrow(sec_current);
```

`CSICurrent2::set_received_gssup_credentials_access_id()`

```
CSIReceivedCredentials
set_received_gssup_credentials_access_id(
    in string peer_identity
);
```

Sets the GSSUP username attribute (or access ID, in the terminology of the OMG CORBASEC specification) for the peer identity in the CSI received credentials object, replacing whatever value was previously stored.

The main reason for calling this operation is to simulate the receipt of GSSUP credentials when bridging from a protocol that does not support the CSI authentication over transport mechanism. The next time the application invokes a remote operation within the current execution context, the CSI asserted identity used for the invocation is one of the following:

- The received identity token (set by the `set_received_itt_principal_name_identity_token()` operation), if present, otherwise
- The received GSSUP username (set by the `set_received_gssup_credentials_access_id()` operation), if present.

This operation replaces the deprecated `IT_CSI::CSICurrent::set_received_gssup_credentials()` operation.

Returns a reference to the created or updated CSI received credentials object if the operation is successful; otherwise, returns a nil object reference.

Note

There is no option to set the password and domain name along with the GSSUP username. This is because the received GSSUP credentials are created *after* the GSSUP username has been authenticated. Hence, the password and domain name are not needed at this point and they are not stored in the received credentials.

ParametersThis operation takes the following parameters:

`peer_identity`

A GSSUP username to set or replace the value stored in the CSI received credentials. If present, the original stored value would have been parsed from the incoming request message.

See Also`SecurityLevel2::ReceivedCredentials`

`SecurityLevel2::Credentials`
`Security::SecAttribute`

`CSICurrent2::set_received_itt_principal_name_identity_token()`

```
CSIReceivedCredentials
set_received_itt_principal_name_identity_token(
    in string asserted_identity
);
```

Sets the CSI asserted identity in the CSI received credentials object, replacing whatever value was previously stored and implicitly setting the identity token type to be `ITTPrincipalName`.

The main reason for calling this operation is to simulate the receipt of a CSI identity token when bridging from a protocol that does not support the CSI identity assertion mechanism. The next time the application invokes a remote operation within the current execution context, the CSI identity assertion mechanism uses the identity token set by this operation.

Returns a reference to the created or updated CSI received credentials object if the operation is successful; otherwise, returns a nil object reference.

ParametersThis operation takes the following parameters:

asserted_identity

An asserted identity to set or replace the value stored in the CSI received credentials. If present, the original stored value would have been parsed from the incoming request message.

CSICurrent2::set_csi_received_credentials()

```
boolean
set_csi_received_credentials(
    in CSIReturnedCredentials    rec_creds
);
```

Reserved for future use.

This operation is reserved for future use and potentially provides performance gains by reusing already established `CSIReturnedCredentials` objects. The supplied `CSIReturnedCredentials` would be those that were previously established by the `set_csi_XXX` operations above and these could potentially be stored by the calling code (this would help avoid heap fragmentation).

IT_CSI::CSIReceivedCredentials Interface

```
local interface CSIReceivedCredentials : IT_TLS_API::TLSReceivedCredentials,
CSICredentials
{
    readonly attribute CSICredentials gssup_credentials;
    readonly attribute CSICredentials propagated_identity_credentials;
    readonly attribute SecurityLevel2::Credentials transport_credentials;
};
```

The `CSIReceivedCredentials` interface, which inherits from `IT_TLS_API::TLSReceivedCredentials` and `SecurityLevel2::ReceivedCredentials`. The OMG `SecurityLevel2::Current::received_credentials()` operation returns a single `SecurityLevel2::ReceivedCredentials` object. However a CSIV2 server may received as many as three credentials from a CSI client:

- Transport TLS credentials
- Propagated identity credentials
- Authenticated credentials over the transport.

The `CSIReceivedCredentials` interface provides access to all three credentials.

The `SecurityLevel2::Current::received_credentials()` operation returns the following credentials type

- Propagated identity credentials, if present
- Authenticated credentials over the transport, if present and propagated identity credentials are not.
- Transport TLS credentials, if present and the above two are not.

`CSIReceivedCredentials::gssup_credentials` Attribute

```
readonly attribute CSICredentials gssup_credentials;
```

A reference to the GSSUP credentials received using the CSIV2 *authorization over transport* mechanism; or a nil object reference if no credentials of this type were received. To access the credentials' attributes, use the inherited `SecurityLevel2::Credentials::get_attributes()` operation.

See Also `Security::SecAttribute`

IT_CSI::CSICredentialsType

CSIReceivedCredentials::propagated_identity_credentials Attribute

```
readonly attribute CSICredentials propagated_identity_credentials;
```

A reference to the GSSUP credentials received using the CSIV2 *identity assertion* (principal propagation) mechanism; or a nil object reference if no credentials of this type were received. To access the credentials' attributes, use the inherited `SecurityLevel2::Credentials::get_attributes()` operation.

See Also `Security::SecAttribute`

IT_CSI::CSICredentialsType

CSIReceivedCredentials::transport_credentials Attribute

```
readonly attribute SecurityLevel2::Credentials transport_credentials;
```

A reference to the credentials received through the SSL/TLS transport layer; or a nil object reference if no credentials of this type were received. These credentials normally take the form of an X.509 certificate chain. To access the credentials' attributes, use the `SecurityLevel2::Credentials::get_attributes()` operation.

See Also `Security::SecAttribute`

IT_CSI::CSICredentialsType
IT_Certificate::X509CertChain

IT_EventChannelAdmin Module

Module `IT_EventChannelAdmin` describes extensions to the module `CosEventChannelAdmin`. It defines an interface, `EventChannelFactory`, for creating or discovering `EventChannel` objects.

IT_EventChannelAdmin Data Types

`IT_EventChannelAdmin::ChannelID` Type

```
typedef long ChannelID;
```

The `ChannelID` is used by the event service to track event channels. This number is assigned by the service when a new event channel is created.

`IT_EventChannelAdmin::EventChannelInfo` Structure

```
struct EventChannelInfo
{
    string                name;
    ChannelID             id;
    CosEventChannelAdmin::EventChannel reference;
};
```

The `EventChannelInfo` is the unit of information managed by the `EventChannelFactory` for a given `EventChannel` instance. `name` is used for administrative purposes.

`IT_EventChannelAdmin::EventChannelInfoList` Sequence

```
typedef sequence<EventChannelInfo> EventChannelInfoList;
```

The `EventChannelInfoList` contains a sequence of `EventChannelInfo` and is the unit returned by `EventChannelFactory::list_channels()`.

IT_EventChannelAdmin Exceptions

IT_EventChannelAdmin::ChannelAlreadyExists

exception ChannelAlreadyExists {string name;;}

`ChannelAlreadyExists` is raised when an attempt is made to create an event channel with a name that is already in use. It returns with the name of the channel.

IT_EventChannelAdmin::ChannelNotFound

exception ChannelNotFound {string name;;}

`ChannelNotFound` is raised when a call to either `EventChannelFactory::find_channel()` or `EventChannelFactory::find_channel_by_id()` cannot find the specified channel. It returns with the name of the specified channel.

IT_EventChannelAdmin::EventChannelFactory Interface

```
interface EventChannelFactory : IT_MessagingAdmin::Manager
{
    CosEventChannelAdmin::EventChannel create_channel(
                                    in string      name,
                                    out ChannelID   id)

        raises (ChannelAlreadyExists);
    CosEventChannelAdmin::EventChannel find_channel(
                                    in string      name,
                                    out ChannelID   id)

        raises (ChannelNotFound);
    CosEventChannelAdmin::EventChannel find_channel_by_id(
                                    in ChannelID   id,
                                    out string      name)

        raises (ChannelNotFound);
    EventChannelInfoList list_channels();
};
```

The `EventChannelFactory` interface defines operations for creating and managing untyped event channels. By inheriting from the `Manager` interface, it also has the ability to gracefully shut down the event service.

`EventChannelFactory::create_channel()`

//IDL

```
CosEventChannelAdmin::EventChannel create_channel(
                                    in string      name,
                                    out ChannelID   id)

    raises (ChannelAlreadyExists);
```

Creates a new instance of the event service style event channel

Parameters

name	The name of the channel to be created

<code>id</code>	The id of the created channel

EventChannelFactory::find_channel()

//IDL

```
CosEventChannelAdmin::EventChannel find_channel(
                                in string    name,
                                out ChannelID id)
raises (ChannelNotFound);
```

Returns an `EventChannel` instance specified by the provided `name`.

Parameters

<code>name</code>	The name of the channel
<code>id</code>	The channel id as returned from <code>create_channel()</code>

EventChannelFactory::find_channel_by_id()

//IDL

```
CosEventChannelAdmin::EventChannel find_channel_by_id(
                                in ChannelID id,
                                out string    name)
raises (ChannelNotFound);
```

Returns an `EventChannel` instance specified by the provided `id`.

Parameters

<code>id</code>	The channel id as returned from <code>create_channel()</code>
<code>name</code>	The name of the channel

EventChannelFactory::list_channels()

//IDL

```
EventChannelInfoList list_channels();
```

Return a list of the `EventChannel` instances associated with the event service.

IT_FPS Module

The `IT_FPS` module defines the constants and interface for the `InterdictionPolicy`.

```
const unsigned long FPS_POLICY_BASE = IT_PolicyBase::IONA_POLICY_ID + 40;
const CORBA::PolicyType INTERDICTION_POLICY_ID = FPS_POLICY_BASE;
enum InterdictionPolicyValue
{
    DISABLE,
    ENABLE
};
local interface InterdictionPolicy : CORBA::Policy
{
    readonly attribute InterdictionPolicyValue value;
};
```

FPS_POLICY_BASE Constant

```
const unsigned long FPS_POLICY_BASE = IT_PolicyBase::IONA_POLICY_ID + 40;
```

Specifies the offset used to identify the `InterdictionPolicy`.

INTERDICTION_POLICY_ID Constant

```
const CORBA::PolicyType INTERDICTION_POLICY_ID = FPS_POLICY_BASE;
```

Specifies the ID passed to `create_policy()` when creating an `InterdictionPolicy`.

InterdictionPolicyValue Enum

```
enum InterdictionPolicyValue
{
    DISABLE,
    ENABLE
};
```

Specifies the possible values for the `InterdictionPolicy`. The values are defined as follows:

ENABLE	This is the default behavior of the firewall proxy service plug-in. A POA with its <code>InterdictionPolicy</code> set to <code>ENABLE</code> will be proxified.
DISABLE	This setting tells the firewall proxy service plug-in to not proxify the POA. A POA with its <code>InterdictionPolicy</code> set to <code>DISABLE</code> will not use the firewall proxy service and requests made on objects under its control will come directly from the requesting clients.

IT_FPS::InterdictionPolicy Interface

This is an interface for a local policy object derived from CORBA::Policy. You create instances of `InterdictionPolicy` by calling `CORBA::ORB::create_policy()`. It is used to specify if a POA is to be proxified by the firewall proxy service.

```
local interface InterdictionPolicy : CORBA::Policy
{
    readonly attribute InterdictionPolicyValue value;
};
```

IT_GIOP

The IT_GIOP Module

A Rocket Software proprietary IDL module that is used to describe the properties of GIOP connections.

IT_GIOP::CLIENT_VERSION_CONSTRAINTS_POLICY_ID

Identifies the IT_GIOP::ClientVersionConstraintsPolicy policy.

Description

You can pass this policy ID to the CORBA::ORB::create_policy() operation to create an IT_GIOP::ClientVersionConstraintsPolicy policy instance.

IT_GIOP::CLIENT_CODESET_CONSTRAINTS_POLICY_ID

Identifies the IT_GIOP::ClientCodeSetConstraintsPolicy policy.

Description

You can pass this policy ID to the CORBA::ORB::create_policy() operation to create an IT_GIOP::ClientCodeSetConstraintsPolicy policy instance.

IT_GIOP::VersionSeq

A list of GIOP version numbers.

IT_GIOP::ClientCodeSetConstraintsPolicyValue

A collection of narrow and wide character codesets which the client is restricted to use when opening a new connection.

Description

Rocket Software internal use only.

Interface IT_GIOP::ClientVersionConstraintsPolicy

A policy that limits the GIOP versions a client can use when opening a new connection.

Description

Rocket Software internal use only.

Instead of specifying the client's GIOP version by programming, you can set the relevant configuration variable. To specify the GIOP version, use one of the following configuration variables (`iiop` for insecure IIOP and `iiop_tls` for secure IIOP):

```
plugins:iiop:client_version_policy
plugins:iiop_tls:client_version_policy
```

IT_GIOP::ClientVersionConstraintsPolicy::allowed_versions

Returns the list of GIOP versions that the client is constrained to use by this policy.

Description

Rocket Software internal use only.

Interface IT_GIOP::ClientCodeSetConstraintsPolicy

A policy that limits the character codesets a client can use when opening a new connection.

Description

Rocket Software internal use only.

Instead of specifying the client's codesets by programming, you can set the relevant configuration variables. To specify the native codeset (`ncs`) or conversion codeset (`ccs`) for narrow characters (`char`) or wide characters (`wchar`), use the following configuration variables:

```
plugins:codeset:char:ncs
plugins:codeset:char:ccs
plugins:codeset:wchar:ncs
plugins:codeset:wchar:ccs
```

IT_GIOP::ClientCodeSetConstraintsPolicy::value

Returns the character code sets that the client is constrained to use by this policy.

Description

Rocket Software internal use only.

Interface IT_GIOP::Current

An object that provides access to miscellaneous attributes of a GIOP connection.

Description

On the client side, the `IT_GIOP::Current` object is used to set attributes that affect all of the outgoing connections opened in the current thread.

On the server side, the `IT_GIOP::Current` object is used to access the attributes of the incoming GIOP connection (the attributes are only accessible in an invocation context).

An instance of `IT_GIOP::Current` can be obtained by passing the string, `IT_GIOPCurrent`, to `CORBA::ORB::resolve_initial_references()`.

C++ implementation

To obtain a reference to an `IT_GIOP::Current` object in C++, use the following code:

```
// C++
IT_GIOP::Current_var giop_current;
CORBA::Object_var objref = orb->resolve_initial_references("IT_GIOPCurrent");
giop_current = IT_GIOP::Current::_narrow(objref);
if (CORBA::is_nil(giop_current.in()) ) {
    // Error: Narrow failed...
}
```

IT_GIOP::Current::negotiated_version

Returns the negotiated GIOP version used by the current connection.

Description

Available on the server side only. This property is negotiated per-connection.

IT_GIOP::Current::negotiated_char_codeset

Returns the negotiated narrow character codeset ID used by the current connection.

Description

Available on the server side only. This property is negotiated per-connection.

IT_GIOP::Current::negotiated_wchar_codeset

Returns the negotiated wide character codeset ID used by the current connection.

Description

Available on the server side only. This property is negotiated per-connection. In Orbix, it is possible for this property to be undefined (for example, if an Orbix client is connected and the client has not yet sent any wide characters).

IT_GIOP::Current::local_principal

Sets the CORBA Principal for sending in client requests in an octet sequence format.

Description

The local principal can be set only on the client side (per-thread). It affects only the client invocations made from the current thread, overriding the default value (Orbix uses the operating system user ID for the Principal by default).

The local principal setting has no effect unless the client is configured to use CORBA Principals (that is, `policies:giop:interop_policy:send_principal` must be `true`).

See also

IT_GIOP::Current::local_principal_as_string

IT_GIOP::Current::local_principal_as_string

Sets the CORBA Principal for sending in client requests in a string format.

Description

The `local_principal_as_string` attribute accesses or modifies the local principal value in a string format. When you set this attribute, it is implicitly converted to an octet sequence format (which is also accessible through the `local_principal` attribute).

C++ implementation

The Principal string is returned in ASCII format.

See also

IT_GIOP::Current::local_principal

IT_GIOP::Current::received_principal

Accesses the CORBA Principal received with a client request in an octet sequence format.

Description

The received principal can be accessed only on the server side.

C++ implementation

If the client did not include a Principal in the request message, this attribute returns an empty octet sequence.

See also

IT_GIOP::Current::received_principal_as_string

IT_GIOP::Current::received_principal_as_string

Accesses the CORBA Principal received with a client request in a string format.

Description

The `received_principal_as_string` attribute accesses the received principal value in a string format. When you access this attribute, it is implicitly converted from an octet sequence format (which is also accessible through the `received_principal` attribute).

C++ implementation

The Principal string is returned in ASCII format.

See also

IT_GIOP::Current::received_principal

IT_GIOP::Current::received_request_length

Returns the length of the current received request.

Description

The request length returned by this attribute is equal to the sum of the all the message fragment lengths (the 12-byte GIOP message header is not considered to be part of the message length). For example, if the request consists of just one message (that is, no fragmentation), the returned length is equal to the message body length.

Available on the server side only. You can access this attribute in the servant implementation, assuming there is an invocation context.

C++ implementation

If not all message fragments have been received yet, this attribute raises a `BAD_INV_ORDER` system exception.

`IT_GIOP::Current::sent_reply_length`

Returns the length of the current sent reply.

Description

Rocket Software internal use only. Available on the server side only.

C++ implementation

Accessible from within an `IT_Binding::ServerRequestInterceptor` implementation after the `invoke()` call has returned.

Interface IT_GIOP::Current2

An object that provides access to miscellaneous attributes of a GIOP connection.

Description

On the client side, the `IT_GIOP::Current2` object is used to set attributes that affect all of the outgoing connections opened in the current thread.

On the server side, the `IT_GIOP::Current2` object is used to access the attributes of the incoming GIOP connection (the attributes are only accessible in an invocation context).

An instance of `IT_GIOP::Current2` can be obtained by passing the string, `IT_GIOPCurrent`, to `CORBA::ORB::resolve_initial_references()`.

In a future release, the attributes defined in this interface are likely to be either folded into the base interface, or moved to a more general interface.

C++ implementation

To obtain a reference to an `IT_GIOP::Current2` object in C++, use the following code:

```
// C++
IT_GIOP::Current2_var giop_current2;
CORBA::Object_var objref = orb->resolve_initial_references("IT_GIOPCurrent");
giop_current2 = IT_GIOP::Current2::_narrow(objref);
if (CORBA::is_nil(giop_current2.in()) ) {
    // Error: Narrow failed...
}
```

IT_GIOP::Current2::protocol_name

Returns the name of the transport protocol underlying GIOP over which the current request was received.

Description

Server side only. This readonly attribute can return one of the following string values:

Table 15: Return Values for the Transport Protocol Name

Protocol	C++ Return Value	Java Return Value
IIOP	IIOP	iiop
IIOP/TLS	IIOP_TLS	iiop
EGMIOP	EGMIOP	egmiop
SHMIOP	SHMIOP	N/A

IT_GIOP::Current2::local_address_literal

Returns the local address, in string format, of the GIOP connection over which a request was received.

Description

Server side only. The format of the returned string depends on the specific protocol being used. For IIOP or IIOP/TLS, it consists of the node address, in IPv4 dotted decimal or IPv6 colon-separated hex notation, followed by a dot and then the decimal port number.

For example, an IPv4 address with host, 127.0.0.1, and IP port, 1234, would be returned as the following string:


```
127.0.0.1.1234
```

An IPv6 address with MAC address, `FB:00:5B:97:E5:7D`, and IP port, 1234, would be returned as the following string:

```
FB:00:5B:97:E5:7D.1234
```

See also

`IT_GIOP::Current2::remote_address_literal`

`IT_GIOP::Current2::remote_address_literal`

Returns the remote address, in string format, of the GIOP connection over which a request was received.

Description

Server side only. The format of the returned string depends on the specific protocol being used. For IIOP or IIOP/TLS, it consists of the node address, in IPv4 dotted decimal or IPv6 colon-separated hex notation, followed by a dot and then the decimal port number.

For example, an IPv4 address with host, `127.0.0.1`, and IP port, 1234, would be returned as the following string:

```
127.0.0.1.1234
```

An IPv6 address with MAC address, `FB:00:5B:97:E5:7D`, and IP port, 1234, would be returned as the following string:

```
FB:00:5B:97:E5:7D.1234
```

See also

`IT_GIOP::Current2::local_address_literal`

`IT_GIOP::Current2::local_address`

Returns the local address, in the form of an object, of the GIOP connection over which a request was received.

Description

Rocket Software internal use only.

Server side only. The type of the returned `Object` depends on the specific protocol implementation being used, as follows:

- IIOP protocol—object type is `IT_ATLI2_IP::IPAddress`.
- IIOP/TLS protocol—object type is `IT_ATLI2_IP::IPAddress`.
- SHMIOP protocol—object type is `IT_ATLI2_SHM::SHMAddress`.
- EGMIOP protocol—*not implemented*.

`IT_GIOP::Current2::remote_address`

Returns the remote address, in the form of an object, of the GIOP connection over which a request was received.

Description

Rocket Software internal use only.

Server side only. The type of the returned `Object` depends on the specific protocol implementation being used, as follows:

- IIOP protocol—object type is `IT_ATLI2_IP::IPAddress`.
- IIOP/TLS protocol—object type is `IT_ATLI2_IP::IPAddress`.
- SHMIOP protocol—object type is `IT_ATLI2_SHM::SHMAddress`.
- EGMIOP protocol—*not implemented*.

IT_LoadBalancing Overview

The `IT_LoadBalancing` module provides operations that allow you to organize object references in the naming service into object groups. Object groups provide a means of controlling object load balancing by distributing work across a pool of objects.

- The `ObjectGroup` interface provides operations to update object group members.
- The `ObjectGroupFactory` interface provides operations to create or locate object groups.

The `IT_LoadBalancing` module also uses the following common data types and exceptions.

Table 16: `IT_LoadBalancing` Common Data Types and Exceptions

Common Data Types	Exceptions
<code>MemberId</code>	<code>NoSuchMember</code>
<code>MemberIdList</code>	<code>DuplicateMember</code>
<code>SelectionMethod</code>	<code>DuplicateGroup</code>
<code>Member</code>	<code>NoSuchGroup</code>
<code>GroupId</code>	
<code>GroupList</code>	

`IT_LoadBalancing::MemberId` Data Type

//IDL

```
typedef string MemberId;
```

An identifying string representing an object group member.

When adding a member to an object group, you must specify a string representing the object. The format of the string is left to the developer. Orbix does not interpret them. The only restriction is that member ids must be unique within each object group.

`IT_LoadBalancing::MemberIdList` Data Type

//IDL

```
typedef sequence<MemberId> MemberIdList;
```

A list of member ids that belong to an object group.

`IT_LoadBalancing::SelectionMethod` Data Type

```
//IDL
```

```
enum SelectionMethod { ROUND_ROBIN_METHOD, RANDOM_METHOD, ACTIVE_METHOD };
```

Specifies the algorithm for mapping a name to a member of an object group.

ROUND_ROBIN_METHOD	Sequentially selects objects from the object group to resolve client requests.
RANDOM_METHOD	Randomly selects objects from the object group to resolve client requests.
ACTIVE_METHOD	Uses load information supplied by the server or the system administrator to select the object with the lightest load from the object group to resolve client requests.

IT_LoadBalancing::Member Data Type

```
//IDL
```

```
struct Member
{
    Object obj;
    MemberId id;
};
```

Specifies an object group member.

IT_LoadBalancing::GroupId Data Type

```
// IDL
```

```
typedef string GroupId;
```

A string representing an object group.

When creating an object group, you must specify a string representing the object. The format of the string is left to the developer. Orbix does not interpret them. The only restriction is that group ids must be unique among object groups.

IT_LoadBalancing::GroupList Data Type

```
//IDL
```

```
typedef sequence<GroupId> GroupList;
```

A list of object group ids.

IT_LoadBalancing::NoSuchMember Exception

```
// IDL
exception NoSuchMember{};
```

Raised when the member id passed to an operation does not specify a member in the current object group.

IT_LoadBalancing::DuplicateMember Exception

```
// IDL
exception DupliccateMember{};
```

Raised by IT_LoadBalancing::ObjectGroup::add_member when the member id identifies a member that is already part of the group.

IT_LoadBalancing::DuplicateGroup Exception

Raised by IT_LoadBalancing::ObjectGroupFactory::create_round_robin, IT_LoadBalancing::ObjectGroupFactory::create_random, and IT_LoadBalancing::ObjectGroupFactory::create_active when the group id identifies a preexisting group.

IT_LoadBalancing::NoSuchGroup Exception

Raised when the specified group id does not match any registered group.

IT_LoadBalancing::ObjectGroup Interface

Object groups are controlled by the `ObjectGroup` interface, which defines the operations for manipulating the members of the object group. An `ObjectGroup` is obtained from an `ObjectGroupFactory`.

The `ObjectGroup` interface has the following attributes:

- contains the group's id string specified when the group is created.
- specifies which algorithm is used to resolve client requests

The `ObjectGroup` interface has the following operations:

- `pick` is called by the naming service to map a client request to an active object.
- `add_member()` adds an object's reference to an object group.
- `remove_member()` removes an object's reference from the object group.
- `get_member()` returns the object by its member id.
- `members()` returns a list of all members in the object group.
- `update_member_load()` updates the object's load status.
- `get_member_load()` returns an object's load status.
- `set_member_timeout()` specifies the amount of time between load updates for a specific member. After this time the object will be removed from the group's pool of available objects.
- `get_member_timeout()` returns the member's timeout value.
- `destroy()` removes the object group from the naming service.

The complete `ObjectGroup` interface is as follows:

```

interface ObjectGroup {
    readonly attribute string id;
    attribute SelectionMethod selection_method;
    Object [pick()](#it_loadbalancingobjectgroup-interface);
    void [add_member](#it_loadbalancingobjectgroup-interface) (in Member mem)
        raises (DuplicateMember);
    void [remove_member](#it_loadbalancingobjectgroup-interface) (in MemberId
id)
        raises (NoSuchMember);
    Object [get_member](#it_loadbalancingobjectgroup-interface) (in MemberId
id)
        raises (NoSuchMember);
    MemberIdList [members](#it_loadbalancingobjectgroup-interface)();
    void [update_member_load](#it_loadbalancingobjectgroup-interface) (in
MemberIdList ids, in double curr_load)
        raises (NoSuchMember);
    double [get_member_load](#it_loadbalancingobjectgroup-interface) (in
MemberId id)
        raises (NoSuchMember);
    void [set_member_timeout](#it_loadbalancingobjectgroup-interface) (in
MemberIdList ids, in long timeout_sec)
        raises (NoSuchMember);
    long [get_member_timeout](#it_loadbalancingobjectgroup-interface) (in
MemberId id)
        raises (NoSuchMember);
    void [destroy](#portableserverspoa-interface)();
};

```

ObjectGroup::pick()

```

// IDL
Object pick();

```

Returns an object from the group using the selection algorithm specified when the group was created.

See Also `IT_LoadBalancing::SelectionMethod`,

```

IT_LoadBalancing::ObjectGroupFactory::create_round_robin(),
IT_LoadBalancing::ObjectGroupFactory::create_random(),
IT_LoadBalancing::ObjectGroupFactory::create_active()

```

ObjectGroup::add_member()

```
// IDL
void add_member( in Member mem )
raises (DuplicateMember);
```

Adds a reference to an object to the object group and makes it available for picking.

Parameters

mem

Specifies the object to be added to the object group. It is made up of a `CORBA::Object` and a `MemberId`.

Exceptions

`IT_LoadBalancing::DuplicateMember`

A member with the same `MemberId` is already associated with the object group.

`ObjectGroup::remove_member()`

```
// IDL
void remove_member( in MemberId id )
raises (NoSuchMember);
```

Removes the specified object's reference from the object group. It does not effect any other references to the object stored in the naming service.

Parameters

id

A string that identifies the object within the object group

Exceptions

`IT_LoadBalancing:: NoSuchMember`

The specified member does not exist in the object group.

`ObjectGroup::get_member()`


```
// IDL
Object get_member( in MemberId id )
```

Returns the object specified by `id`.

Parameters

`id`

A string that identifies the object within the object group

Exceptions

`IT_LoadBalancing:: NoSuchMember`

The specified member does not exist in the object group.

`ObjectGroup::members()`

```
// IDL
MemberIdList members();
```

Returns a list containing the ids of all members in the object group.

`ObjectGroup::update_member_load()`

// IDL

```
void update_member_load(in MemberIdList ids, in double curr_load)
raises (NoSuchMember);
```

Specifies the load value used in the ACTIVE_METHOD selection algorithm.

Parameters

<code>ids</code>	A sequence of MemberId values that specify the objects whose load value is being updated.

<code>curr_load</code>	A double that specifies the load on the specified objects. The higher the value, the higher the load. Using the ACTIVE_METHOD members of the group with the lowest load values are picked first.

Exceptions

IT_LoadBalancing:: NoSuchMember

One or more of the specified members do not exist in the object group.

See AlsoIT_LoadBalancing::SelectionMethod,

```
IT_LoadBalancing::ObjectGroupFactory::create_active(),
IT_LoadBalancing::[ObjectGroup](#it_loadbalancingobjectgroup-interface)::
[set_member_timeout()](#it_loadbalancingobjectgroup-interface)
```

ObjectGroup::get_member_load()

```
// IDL
double get_member_load(in MemberId id)
raises (NoSuchMember);
```

Returns the load value for a specified object.

Parameters

`id`

A string that identifies the object within the object group

Exceptions

IT_LoadBalancing:: NoSuchMember

The specified member does not exist in the object group.

See AlsoIT_LoadBalancing::ObjectGroup::update_member_load()

ObjectGroup::set_member_timeout()

```
void set_member_timeout (in MemberIdList ids, in long timeout_sec)
raises (NoSuchMember);
```

Specifies the amount of time, in seconds, that a member has between updates of its load value before it is removed from the list of available objects.

Parameters

<code>ids</code>	A sequence of MemberIds that specify the members whose timeout values are being set.
<code>timeout_sec</code>	A <code>long</code> specifying the number of seconds that an object has between load value updates. After this amount of time has expired the object will be taken off the object groups list of available objects.

Exceptions

```
IT_LoadBalancing::NoSuchMember
```

One or more of the specified members do not exist in the object group.

See Also [IT_LoadBalancing::ObjectGroup::update_member_load\(\)](#)

[ObjectGroup::get_member_timeout\(\)](#)

```
\\ IDL
long get_member_timeout(in MemberId id)
raises (NoSuchMember);
```

Returns the timeout value for the specified object group member.

Parameters

```
id
```

A string that identifies the object within the object group

Exceptions

```
IT_LoadBalancing:: NoSuchMember
```

One or more of the specified members do not exist in the object group.

See Also [IT_LoadBalancing::ObjectGroup::set_member_timeout\(\)](#)

[ObjectGroup::destroy\(\)](#)

```
// IDL  
void destroy()
```

Removes the object group from the naming service. Before calling `destroy()` on an object group, you must first unbind it.

Exceptions

```
CosNaming::NamingContext::NotEmpty
```

The object group is not unbound from the naming service.

See Also [CosNaming::NamingContext::unbind\(\)](#)

IT_LoadBalancing::ObjectGroupFactory Interface

The `ObjectGroupFactory` interface provides methods for creating and locating object groups in the naming service.

The `ObjectGroupFactory` interface has the following methods to create object groups:

- `create_round_robin()` creates an object group that uses the `ROUND_ROBIN_METHOD` selection algorithm for picking objects.
- `create_random()` creates an object group that uses the `RANDOM_METHOD` selection algorithm for picking objects.
- `create_active()` creates an object group that uses the `ACTIVE_METHOD` selection algorithm for picking objects.

The `ObjectGroupFactory` interface has the following methods for locating object groups in the naming service:

- `find_group` returns a specific object group.
- `rr_groups` returns a list of all object groups using the `ROUND_ROBIN_METHOD` selection algorithm.
- `random_groups` returns a list of all object groups using the `RANDOM_METHOD` selection algorithm.
- `active_groups` returns a list of all object groups using the `ACTIVE_METHOD` selection algorithm.

The complete `ObjectGroupFactory` interface is as follows:

```

interface ObjectGroupFactory {
    ObjectGroup [create_round_robin](#it_loadbalancingobjectgroupfactory-
interface) (in GroupId id)
        raises (DuplicateGroup);
    ObjectGroup [create_random](#it_loadbalancingobjectgroupfactory-
interface) (in GroupId id)
        raises (DuplicateGroup);
    ObjectGroup [create_active](#it_loadbalancingobjectgroupfactory-
interface) (in GroupId id)
        raises (DuplicateGroup);
    ObjectGroup [find_group](#it_loadbalancingobjectgroupfactory-interface)
(in GroupId id)
        raises (NoSuchGroup);
    GroupList [rr_groups](#it_loadbalancingobjectgroupfactory-interface)();
    GroupList [random_groups](#it_loadbalancingobjectgroupfactory-interface)
();
    GroupList [active_groups](#it_loadbalancingobjectgroupfactory-interface)
();
};

```

ObjectGroupFactory::create_round_robin()

```

// IDL
ObjectGroup create_round_robin (in GroupId id)
    raises (DuplicateGroup);

```

Creates an object group in the naming service. The new group uses the ROUND_ROBIN_METHOD selection algorithm for picking objects.

Parameters

id

A string identifying the object group. The string must be unique among object groups.

Exceptions

IT_LoadBalancing::
DuplicateGroup

The `id` specified is already in use by another object group.

See Also IT_LoadBalancing::ROUND_ROBIN_METHOD

ObjectGroupFactory::create_random()

```
ObjectGroup create_random (in GroupId id)
    raises (DuplicateGroup);
```

Creates an object group in the naming service. The new group uses the RANDOM_METHOD selection algorithm for picking objects.

Parameters

id

A string identifying the object group. The string must be unique among object groups.

Exceptions

IT_LoadBalancing::DuplicateGroup

The `id` specified is already in use by another object group.

See Also IT_LoadBalancing::RANDOM_METHOD

ObjectGroupFactory::create_active()

```
ObjectGroup create_active (in GroupId id)
    raises (DuplicateGroup);
```

Creates an object group in the naming service. The new group uses the ACTIVE_METHOD selection algorithm for picking objects.

Parameters

id

A string identifying the object group. The string must be unique among object groups.

Exceptions

IT_LoadBalancing::
DuplicateGroup

The `id` specified is already in use by another object group.

See Also IT_LoadBalancing::ACTIVE_METHOD

ObjectGroupFactory::find_group()

```
//IDL
ObjectGroup find_group (in GroupId id)
    raises (NoSuchGroup);
```

Returns the specified object group.

Parameters

id

A string identifying the object group. The string must be unique among object groups.

Exceptions

IT_LoadBalancing::NoSuchGroup

The group specified does not exist.

ObjectGroupFactory::rr_groups()

```
// IDL
GroupList rr_groups();
```

Returns a sequence of GroupId that identify all objects groups in the naming service that use ROUND_ROBIN_METHOD.

ObjectGroupFactory::random_groups()

```
// IDL
GroupList random_groups();
```

Returns a sequence of GroupId that identify all objects groups in the naming service that use RANDOM_METHOD.

ObjectGroupFactory::active_groups()


```
// IDL
GroupList random_groups();
```

Returns a sequence of GroupId that identify all objects groups in the naming service that use ACTIVE_METHOD.

IT_Logging Overview

The `IT_Logging` module is the centralized point for controlling all logging methods.

- The `EventLog` interface controls the reporting of log events.
- The `LogStream` interface controls how and where events are received.

The `IT_Logging` module also uses the following common data types, static method, and macros.

Table 17: IT_Logging Common Data Types, Methods, and Macros

Common Data Types	Methods and Macros
<code>ApplicationId</code>	<code>format_message()</code>
<code>EventId</code>	<code>IT_LOG_MESSAGE()</code>
<code>EventParameters</code>	<code>IT_LOG_MESSAGE_1()</code>
<code>EventPriority</code>	<code>IT_LOG_MESSAGE_2()</code>
<code>SubsystemId</code>	<code>IT_LOG_MESSAGE_3()</code>
<code>Timestamp</code>	<code>IT_LOG_MESSAGE_4()</code>
	<code>IT_LOG_MESSAGE_5()</code>

IT_Logging::ApplicationId Data Type

//IDL

```
typedef string ApplicationId;
```

An identifying string representing the application that logged the event.

For example, a Unix and Windows `ApplicationId` contains the host name and process ID (PID) of the reporting process. Because this value can differ from platform to platform, streams should only use it as informational text, and should not attempt to interpret it.

EnhancementOrbix enhancement to CORBA.

IT_Logging::EventId Data Type

//IDL

```
typedef unsigned long EventId;
```

An identifier for the particular event.

EnhancementOrbix enhancement to CORBA.

IT_Logging::EventParameters Data Type

//IDL

```
typedef CORBA::AnySeq EventParameters;
```

A sequence of locale-independent parameters encoded as a sequence of `Any` values.

EnhancementOrbix enhancement to CORBA.

See AlsoIT_Logging :: format_message()

IT_Logging::EventPriority Data Type

//IDL

```
typedef unsigned short EventPriority;
```

Specifies the priority of a logged event. These can be divided into the following categories of priority.

Information	A significant non-error event has occurred. Examples include server startup/shutdown, object creation/deletion, and information about administrative actions. Informational messages provide a history of events that can be invaluable in diagnosing problems.
Warning	The subsystem has encountered an anomalous condition, but can ignore it and continue functioning. Examples include encountering an invalid parameter, but ignoring it in favor of a default value.
Error	An error has occurred. The subsystem will attempt to recover, but may abandon the task at hand. Examples include finding a resource (such as memory) temporarily unavailable, or being unable to process a particular request due to errors in the request.
Fatal Error	An unrecoverable error has occurred. The subsystem or process will terminate.

The possible values for an `EventPriority` consist of the following:

```

LOG_NO_EVENTS
LOG_ALL_EVENTS
LOG_INFO_LOW
LOG_INFO_MED
LOG_INFO_HIGH
LOG_INFO (LOG_INFO_LOW)
LOG_ALL_INFO
LOG_WARNING
LOG_ERROR
LOG_FATAL_ERROR

```

A single value is used for EventLog operations that report events or LogStream operations that receive events. In filtering operations such as `set_filter()`, these values can be combined as a filter mask to control which events are logged at runtime.

EnhancementOrbix enhancement to CORBA.

IT_Logging::format_message()

// C++

```

static char* format_message(
    const char* description,
    const IT_Logging::EventParameters& params
);

```

Returns a formatted message based on a format description and a sequence of parameters.

ParametersMessages are reported in two pieces for internationalization:

<code>description</code>	A locale-dependent string that describes of how to use the sequence of parameters in <code>params</code> .
<code>params</code>	A sequence of locale-dependent parameters.

`format_message()` copies the `description` into an output string, interprets each event parameter, and inserts the event parameters into the output string where appropriate. Event parameters that are primitive and `SystemException` parameters are converted to strings before insertion. For all other types, question marks (?) are inserted.

EnhancementOrbix enhancement to CORBA.

IT_Logging::SubsystemId Data Type

//IDL

```
typedef string SubsystemId;
```

An identifying string representing the subsystem from which the event originated. The constant `_DEFAULT` may be used to enable all subsystems.

EnhancementOrbix enhancement to CORBA.

IT_Logging::Timestamp Data Type

//IDL

```
typedef unsigned long Timestamp;
```

The time of the logged event in seconds since January 1, 1970.

EnhancementOrbix enhancement to CORBA.

IT_LOG_MESSAGE() Macro

// C++

```
#define IT_LOG_MESSAGE( \
    event_log, \
    subsystem, \
    id, \
    severity, \
    desc \
) ...
```

A macro to use for reporting a log message.

Parameters

<code>event_log</code>	The log (EventLog) where the message is to be reported.
<code>subsystem</code>	The SubsystemId.
<code>id</code>	The EventId.
<code>severity</code>	The EventPriority.
<code>desc</code>	A string description of the event.

EnhancementOrbix enhancement to CORBA.

ExamplesHere is a simple example of usage:

```

...
IT_LOG_MESSAGE(
    event_log,
    IT_IIOP_Logging::SUBSYSTEM,
    IT_IIOP_Logging::SOCKET_CREATE_FAILED,
    IT_Logging::LOG_ERROR,
    SOCKET_CREATE_FAILED_MSG
);

```

IT_LOG_MESSAGE_1() Macro

// C++

```

#define IT_LOG_MESSAGE_1( \
    event_log, \
    subsystem, \
    id, \
    severity, \
    desc, \
    param0 \
) ...

```

A macro to use for reporting a log message with one event parameter.

Parameters

<code>event_log</code>	The log (EventLog) where the message is to be reported.
<code>subsystem</code>	The SubsystemId.
<code>id</code>	The EventId.
<code>severity</code>	The EventPriority.
<code>desc</code>	A string description of the event.
<code>param0</code>	A single parameter for an EventParameters sequence.

EnhancementOrbix enhancement to CORBA.

See AlsoIT_Logging::IT_LOG_MESSAGE()

IT_LOG_MESSAGE_2() Macro

// C++

```
#define IT_LOG_MESSAGE_2( \
    event_log, \
    subsystem, \
    id, \
    severity, \
    desc, \
    param0, \
    param1 \
) ...
```

A macro to use for reporting a log message with two event parameters.

Parameters

<code>event_log</code>	The log (EventLog) where the message is to be reported.
<code>subsystem</code>	The SubsystemId.
<code>id</code>	The EventId.
<code>severity</code>	The EventPriority.
<code>desc</code>	A string description of the event.
<code>param0</code>	The first parameter for an EventParameters sequence.
<code>param1</code>	The second parameter for an EventParameters sequence.

EnhancementOrbix enhancement to CORBA.

See Also`IT_Logging::IT_LOG_MESSAGE()`

`IT_LOG_MESSAGE_3()` Macro

// C++

```
#define IT_LOG_MESSAGE_3( \
    event_log, \
    subsystem, \
    id, \
    severity, \
    desc, \
    param0, \
    param1, \
    param2 \
) ...
```

A macro to use for reporting a log message with three event parameters.

Parameters

<code>event_log</code>	The log (EventLog) where the message is to be reported.
<code>subsystem</code>	The SubsystemId.
<code>id</code>	The EventId.
<code>severity</code>	The EventPriority.
<code>desc</code>	A string description of the event.
<code>param0</code>	The first parameter for an EventParameters sequence.
<code>param1</code>	The second parameter for an EventParameters sequence.
<code>param2</code>	The third parameter for an EventParameters sequence.

EnhancementOrbix enhancement to CORBA.

See Also`IT_Logging::IT_LOG_MESSAGE()`

`IT_LOG_MESSAGE_4()` Macro

// C++


```
#define IT_LOG_MESSAGE_4( \
    event_log, \
    subsystem, \
    id, \
    severity, \
    desc, \
    param0, \
    param1, \
    param2, \
    param3 \
) ...
```

A macro to use for reporting a log message with four event parameters.

Parameters

<code>event_log</code>	The log (EventLog) where the message is to be reported.
<code>subsystem</code>	The SubsystemId.
<code>id</code>	The EventId.
<code>severity</code>	The EventPriority.
<code>desc</code>	A string description of the event.
<code>param0</code>	The first parameter for an EventParameters sequence.
<code>param1</code>	The second parameter for an EventParameters sequence.
<code>param2</code>	The third parameter for an EventParameters sequence.
<code>param3</code>	The forth parameter for an EventParameters sequence.

EnhancementOrbix enhancement to CORBA.

See Also`IT_Logging::IT_LOG_MESSAGE()`

`IT_LOG_MESSAGE_5()` Macro

// C++

```
#define IT_LOG_MESSAGE_5( \
    event_log, \
    subsystem, \
    id, \
    severity, \
    desc, \
    param0, \
    param1, \
    param2, \
    param3, \
    param4 \
) ...
```

A macro to use for reporting a log message with five event parameters.

Parameters

<code>event_log</code>	The log (EventLog) where the message is to be reported.
<code>subsystem</code>	The SubsystemId.
<code>id</code>	The EventId.
<code>severity</code>	The EventPriority.
<code>desc</code>	A string description of the event.
<code>param0</code>	The first parameter for an EventParameters sequence.
<code>param1</code>	The second parameter for an EventParameters sequence.
<code>param2</code>	The third parameter for an EventParameters sequence.
<code>param3</code>	The forth parameter for an EventParameters sequence.
<code>param4</code>	The fifth parameter for an EventParameters sequence.

EnhancementOrbix enhancement to CORBA.

See Also`IT_Logging::IT_LOG_MESSAGE()`

IT_Logging::EventLog Interface

Logging is controlled with the `EventLog` interface, which defines operations to register interfaces for receiving notification of logged events, report logged events, and filter logged events. Each ORB maintains its own `EventLog` instance, which applications obtain by calling `resolve_initial_references()` with the string argument `IT_EventLog`.

The `EventLog` interface has the following operations:

- `register_stream()` registers the receivers of log events. `report_event()` reports log events and `report_message()` reports messages to receivers.
- `get_filter()`, `set_filter()`, `expand_filter()`, and `clear_filter()` set filters for which log events are reported.

An `EventLog` has several operations for controlling which events are logged at runtime. A filter has an `EventPriority` that describes the types of events that are reported. Every subsystem is associated with a filter that controls which events are allowed for that subsystem. A default filter is also associated with the entire `EventLog`.

The complete `EventLog` interface is as follows:

```
// IDL in module IT_Logging
interface EventLog {
    void [register_stream](#it_loggingeventlog-interface)(
        in LogStream the_stream
    );
    void [report_event](#it_loggingeventlog-interface)(
        in SubsystemId    subsystem,
        in EventId        event,
        in EventPriority   priority,
        in any             event_data
    );
    void [report_message](#it_loggingeventlog-interface)(
        in SubsystemId    subsystem,
        in EventId        event,
        in EventPriority   priority,
        in string          description,
        in EventParameters parameters
    );
    EventPriority [get_filter](#it_loggingeventlog-interface)(
        in SubsystemId subsystem
    );
    void [set_filter](#it_loggingeventlog-interface)(
        in SubsystemId    subsystem,
        in EventPriority   filter_mask
    );
    void [expand_filter](#it_loggingeventlog-interface)(
        in SubsystemId    subsystem,
        in EventPriority   filter_mask
    );
    void [clear_filter](#it_loggingeventlog-interface)(
        in SubsystemId subsystem
    );
    ...
};
```

EventLog::clear_filter()

// IDL

```
void clear_filter(
    in SubsystemId subsystem
);
```

Removes an explicitly configured subsystem filter, causing the subsystem to revert to using the default filter.

EnhancementOrbix enhancement to CORBA.

See AlsoIT_Logging :: EventLog :: get_filter()

EventLog::expand_filter()

// IDL

```
void expand_filter(
    in SubsystemId subsystem,
    in EventPriority filter_mask
);
```

Adds to a subsystem filter by combining the new filter mask with the existing subsystem filter.

Parameters

<code>subsystem</code>	The name of the subsystem for which the filter applies.
<code>filter_mask</code>	A value representing the types of events to be reported.

EnhancementOrbix enhancement to CORBA.

See AlsoIT_Logging :: EventLog :: set_filter()

```
IT_Logging::EventLog::clear_filter()
```

EventLog::get_filter()

// IDL

```
EventPriority get_filter(
    in SubsystemId subsystem
);
```

Returns a sub-system's filter priorities.

Parameters

```
subsystem
```

The name of the subsystem for which the filter applies.

EnhancementOrbix enhancement to CORBA.

See Also `IT_Logging :: EventLog :: get_filter()`

`EventLog::register_stream()`

// IDL

```
void register_stream(
    in LogStream the_stream
);
```

Explicitly registers a LogStream.

Parameters

`the_stream`

The stream to register.

Log events “flow” to receivers on streams, thus streams must be registered with the `EventLog`. Once registered, the stream will receive notification of logged events.

An `EventLog` can have multiple streams registered at one time, and it can have a single stream registered more than once.

Enhancement Orbix enhancement to CORBA.

See Also `IT_Logging :: LogStream`

`EventLog::report_event()`

// IDL

```
void report_event(
    in SubsystemId    subsystem,
    in EventId        event,
    in EventPriority   priority,
    in any             event_data
);
```

Reports an event and its event-specific data.

Parameters

<code>subsystem</code>	The name of the subsystem reporting the event.
<code>event</code>	The unique ID defining the event.

<code>priority</code>	The event priority.
<code>event_data</code>	Event-specific data.

EnhancementOrbix enhancement to CORBA.

See Also`IT_Logging :: EventLog::report_message()`

`EventLog::report_message()`

// IDL

```
void report_message(
    in SubsystemId    subsystem,
    in EventId        event,
    in EventPriority   priority,
    in string          description,
    in EventParameters parameters
);
```

Reports an event and message.

Parameters

<code>subsystem</code>	The name of the subsystem reporting the event.
<code>event</code>	The unique ID defining the event.
<code>priority</code>	The event priority.
<code>description</code>	A string describing the format of <code>parameters</code> .
<code>parameters</code>	A sequence of parameters for the log.

EnhancementOrbix enhancement to CORBA.

See Also`IT_Logging :: EventLog::report_event()`

`EventLog::set_filter()`

// IDL

```
void set_filter(  
    in SubsystemId subsystem,  
    in EventPriority filter_mask  
);
```

Sets a filter for a given subsystem. This operation overrides the subsystem's existing filter.

Parameters

<code>subsystem</code>	The name of the subsystem for which the filter applies.
<code>filter_mask</code>	A value representing the types of events to be reported.

A subsystem will use the default filter if its filter has not been explicitly configured by a call to `set_filter()`.

EnhancementOrbix enhancement to CORBA.

See Also`IT_Logging :: EventLog :: get_filter()`

IT_Logging::LogStream Interface

The `LogStream` interface allows an application to intercept events and write them to some concrete location via a stream. `IT_Logging :: EventLog` objects maintain a list of `LogStream` objects. You register a `LogStream` object from an `EventLog` using `register_stream()`. The complete `LogStream` interface is as follows:

```
// IDL in module IT_Logging
interface LogStream {
    void [report_event](#it_loggingeventlog-interface)(
        in ApplicationId    application,
        in SubsystemId      subsystem,
        in EventId          event,
        in EventPriority     priority,
        in Timestamp        event_time,
        in any               event_data
    );
    void [report_message](#it_loggingeventlog-interface)(
        in ApplicationId    application,
        in SubsystemId      subsystem,
        in EventId          event,
        in EventPriority     priority,
        in Timestamp        event_time,
        in string            description,
        in EventParameters  parameters
    );
};
```

These operations are described in detail as follows:

`LogStream::report_event()`

// IDL

```

void report_event(
    in ApplicationId    application,
    in SubsystemId     subsystem,
    in EventId          event,
    in EventPriority    priority,
    in Timestamp        event_time,
    in any              event_data
);

```

Reports an event and its event-specific data to the log stream.

Parameters

<code>application</code>	An ID representing the reporting application.
<code>subsystem</code>	The name of the subsystem reporting the event.
<code>event</code>	A unique ID defining the event.
<code>priority</code>	The event priority.
<code>event_time</code>	The time when the event occurred.
<code>event_data</code>	Event-specific data.

EnhancementOrbix enhancement to CORBA.

See AlsoIT_Logging :: EventLog::report_event()

```
IT_Logging::LogStream::report_message()
```

LogStream::report_message()

// IDL

```

void report_message(
    in ApplicationId    application,
    in SubsystemId     subsystem,
    in EventId          event,
    in EventPriority    priority,
    in Timestamp        event_time,
    in string           description,
    in EventParameters parameters
);

```

Reports an event and message to the log stream.

Parameters

<code>application</code>	An ID representing the reporting application.
<code>subsystem</code>	The name of the subsystem reporting the event.
<code>event</code>	The unique ID defining the event.
<code>priority</code>	The event priority.
<code>event_time</code>	The time when the event occurred.
<code>description</code>	A string describing the format of <code>parameters</code> .
<code>parameters</code>	A sequence of parameters for the log.

EnhancementOrbix enhancement to CORBA.

See Also`IT_Logging :: EventLog::report_message()`

```
IT_Logging::LogStream::report_event()
```

IT_MessagingAdmin Module

Module `IT_MessagingAdmin` describes the administrative interface for the Event service.

IT_MessagingAdmin::Manager Interface

The `Manager` interface provides administrative operations on an event service.

```
//IDL
interface Manager
{
    readonly attribute string  name;
    readonly attribute string  host;
    void shutdown();
};
};
```

`Manager::shutdown()`

```
//IDL
```

```
void shutdown();
```

Shuts down an event service.

IT_MessagingBridge Module

`IT_MessagingBridge` defines the data types, exceptions, and interfaces used to establish and manage the endpoints of a bridge. The following interfaces are defined in `IT_MessagingBridge`:

- [IT_MessagingBridge::Endpoint Interface](#)
- [IT_MessagingBridge::SinkEndpoint Interface](#)
- [IT_MessagingBridge::SourceEndpoint Interface](#)
- [IT_MessagingBridge::EndpointAdmin Interface](#)

IT_MessagingBridge Data Types

`IT_MessagingBridge::BridgeName`

```
typedef string BridgeName;
```

`BridgeName` specifies the unique identifier of a bridge.

`IT_MessagingBridge::BridgeNameSeq`

```
typedef sequence<BridgeName> BridgeNameSeq;
```

`BridgeNameSeq` contains a list of bridge names and is the type returned by

```
IT_MessagingBridgeAdmin::BridgeAdmin::list_all_bridges().
```

`IT_MessagingBridge::EndpointName`

```
typedef string EndpointName;
```

`EndpointName` uniquely identifies the name of the messaging object with which the endpoint is associated. For example, the `EndpointName` could be the name of a notification channel, a JMS topic, or a JMS queue.

`IT_MessagingBridge::EndpointType`

```
typedef short EndpointType;
```

```
const EndpointType JMS_TOPIC = 1;
const EndpointType JMS_QUEUE = 2;
const EndpointType NOTIFY_CHANNEL = 3;
```

`EndpointType` specifies what type of messaging object to which the endpoint is going to connect. It can take one of three constant values:

Table 18: EndpointTypes and the associated messaging objects

EndpointType	Messaging Object
JMS_TOPIC	JMS Topic
JMS_QUEUE	JMS Queue
NOTIFY_CHANNEL	Notification Channel

IT_MessagingBridge::EndpointTypeSeq

```
typedef sequence<EndpointType> EndpointTypeSeq;
```

`EndpointTypeSeq` specifies a list of endpoint types.

IT_MessagingBridge::EndpointAdminName

```
typedef string EndpointAdminName;
```

`EndpointAdminName` specifies the unique identifier assigned to an endpoint admin object.

IT_MessagingBridge::InvalidEndpointCode

```
typedef short InvalidEndpointCode;
const InvalidEndpointCode INVALID_TYPE = 1;
const InvalidEndpointCode INVALID_NAME = 2;
const InvalidEndpointCode UNSUPPORTED_TYPE = 3;
const InvalidEndpointCode INCOMPATIBLE_TYPE = 4;
const InvalidEndpointCode SAME_AS_PEER = 5;
const InvalidEndpointCode DOES_NOT_EXIST = 6;
```

`InvalidEndpointCode` specifies the return code of the `InvalidEndpoint` exception.

IT_MessagingBridge Exceptions

IT_MessagingBridge::InvalidEndpoint

```
exception InvalidEndpoint {InvalidEndpointCode code;;}
```

`InvalidEndpoint` is raised when an endpoint is incorrectly specified. Its return code specifies the reason the endpoint is invalid. The return code will be one of the following:

Table 19: InvalidEndpoint return codes and their explanation

InvalidEndpointCode	Explanation
INVALID_TYPE	The <code>EndpointType</code> was not recognized.
INVALID_NAME	The <code>EndpointName</code> is not valid for the specified <code>EndpointType</code> .
UNSUPPORTED_TYPE	The <code>EndpointAdmin</code> does not support the specified type of endpoint.
INCOMPATIBLE_TYPE	The <code>EndpointType</code> of the endpoints being connected are incompatible. For example a <code>JMS_TOPIC</code> cannot be connected to a <code>JMS_QUEUE</code> .
SAME_AS_PEER	The <code>EndpointType</code> of the endpoint being connected to is the same as the current endpoint.
DOES_NOT_EXIST	The endpoint specified by <code>EndpointName</code> does not exist.

IT_MessagingBridge::EndpointAlreadyConnected

```
exception EndpointAlreadyConnected {};
```

`EndpointAlreadyConnected` is raised when an attempt is made to connect an endpoint that is already connected to a peer.

IT_MessagingBridge::BridgeNameNotFound

```
exception BridgeNameNotFound {};
```

`BridgeNameNotFound` is raised when the bridge with the specified name is not found.

IT_MessagingBridge::BridgeNameAlreadyExists

```
exception BridgeNameAlreadyExists {};
```


`BridgeNameAlreadyExists` is raised when an attempt to create a bridge with a name already in use is made.

IT_MessagingBridge::Endpoint Interface

```
interface Endpoint
{
    readonly attribute BridgeName bridge_name;
    readonly attribute EndpointType type;
    readonly attribute EndpointName name;
    readonly attribute EndpointAdmin admin;
    readonly attribute Endpoint peer;
    readonly attribute boolean connected;
    void connect(in Endpoint peer)
    raises (InvalidEndpoint, EndpointAlreadyConnected);
    void destroy();
};
```

Endpoint is a generic interface used to specify a bridge endpoint. This is recommended interface for developers to use when working with bridge endpoints. Defines the attributes used to specify the type of endpoint, the bridge it is associated with, and if the endpoint is actively in use by a bridge. The interface also specifies an operation for connecting an endpoint to a peer endpoint and an operation for releasing the resources used by an endpoint. In general, the connection of endpoints to peers and the destructions of specific endpoints is handled by the bridge service when a bridge is created or destroyed.

Endpoint::bridge_name

readonly attribute BridgeName bridge_name;

bridge_name specifies the name of the bridge with which the endpoint is associated.

Endpoint::type

readonly attribute EndpointType type;

type specifies the type of messaging object to which the endpoint is connected.

Endpoint::name

readonly attribute EndpointName name;

name specifies the unique identifier of the endpoint.

Endpoint::admin

readonly attribute EndpointAdmin admin;

`admin` is a reference to the `EndpointAdmin` associated with the endpoint.

Endpoint::peer

readonly attribute Endpoint peer;

`peer` is a reference to the endpoint on the other end of the bridge. If the endpoint is not connected to a peer, this reference is `null`.

Endpoint::connected

readonly attribute boolean connected;

`connected` specifies if the endpoint is actively connected to a peer endpoint.

Endpoint::connect()

void connect(in Endpoint peer)

```
raises (InvalidEndpoint, EndpointAlreadyConnected);
```

`connect()` creates a connection between the current endpoint and the endpoint passed into the operation. This operation is called by the bridge service when a bridge is create.

Parameters

`peer`

Specifies the endpoint that is being connected to.

Exceptions

<code>InvalidEndpoint</code>	The specified endpoint is invalid. The return code provides the details explaining the reason.
<code>EndpointAlreadyConnected</code>	One of the endpoints is already connected to a peer endpoint.

Endpoint::destroy()

void destroy();

Destroys the endpoint and releases all resources used to support it.

IT_MessagingBridge::SinkEndpoint Interface

```
interface SinkEndpoint : Endpoint
{
};
```

`SinkEndpoint` is a specialization of the generic `IT_MessagingBridge::Endpoint` interface. It is used to specify an endpoint that receives messages from the bridge and forward the messages onto the receiving service. It defines no specific operations.

IT_MessagingBridge::SourceEndpoint Interface

```
interface SourceEndpoint : Endpoint
{
    void start();
    void suspend();
    void stop();
};
```

`SourceEndpoint` is a specialization of the generic `IT_MessagingBridge::Endpoint` interface. It is used to specify an endpoint that takes messages from the forwarding service and passes the messages into the bridge. It defines three operations for controlling the flow of messages through the endpoint.

`SourceEndpoint::start()`

`void start();`

`start()` begins the flow of messages to the bridge.

`SourceEndpoint::suspend()`

`void suspend();`

`suspend()` stops the flow of messages to the bridge, but causes the endpoint to queue any incoming messages for delivery. Once the flow of messages is restarted, the queued messages will be pass to the bridge.

`SourceEndpoint::stop()`

`void stop();`

`stop()` completely stops the flow of messages to the bridge.

IT_MessagingBridge::EndpointAdmin Interface

```
interface EndpointAdmin
{
    readonly attribute EndpointAdminName name;
    readonly attribute EndpointTypeSeq supported_types;
    SinkEndpoint create_sink_endpoint(in BridgeName bridge_name,
                                     in EndpointType type,
                                     in EndpointName name)
    raises (InvalidEndpoint, BridgeNameAlreadyExists);
    SourceEndpoint create_source_endpoint(in BridgeName bridge_name,
                                         in EndpointType type,
                                         in EndpointName name)
    raises (InvalidEndpoint, BridgeNameAlreadyExists);
    SinkEndpoint get_sink_endpoint(in BridgeName bridge_name)
    raises (BridgeNameNotFound);
    SourceEndpoint get_source_endpoint(in BridgeName bridge_name)
    raises (BridgeNameNotFound);
    BridgeNameSeq get_all_sink_endpoints();
    BridgeNameSeq get_all_source_endpoints();
};
```

`EndpointAdmin` defines the factory operations to create and discover endpoints. There is one `EndpointAdmin` object for each messaging service that can participate in bridging.

`EndpointAdmin::name`

readonly attribute `EndpointAdminName` `name`;

`name` specifies the unique identifier of the endpoint admin object.

`EndpointAdmin::supported_types`

readonly attribute `EndpointTypeSeq` `supported_types`;

`supported_types` specifies the types of endpoint that the admin object can support. For example, the `EndpointAdmin` for JMS can support endpoints of type `JMS_TOPIC` and `JMS_QUEUE`.

`EndpointAdmin::create_sink_endpoint()`

`SinkEndpoint` `create_sink_endpoint(in BridgeName bridge_name,`

```

                                in EndpointType type,
                                in EndpointName name)
raises (InvalidEndpoint, BridgeNameAlreadyExists);

```

`create_sink_endpoint()` creates a new `SinkEndpoint` of the specified type and associates it with the specified bridge name.

Parameters

<code>bridge_name</code>	The name of the bridge with which to associate the endpoint.
<code>type</code>	The <code>EndpointType</code> of the new endpoint.
<code>name</code>	The unique identifier to use for the endpoint.

Exceptions

<code>InvalidEndpoint</code>	The <code>type</code> or the <code>name</code> specified are incorrect. The return code will contain the details.
<code>BridgeNameAlreadyExists</code>	

`EndpointAdmin::create_source_endpoint()`

`SourceEndpoint create_source_endpoint(in BridgeName bridge_name,`

```

                                in EndpointType type,
                                in EndpointName name)
raises (InvalidEndpoint, BridgeNameAlreadyExists);

```

`create_source_endpoint()` creates a new `SourceEndpoint` of the specified type and associates it with the specified bridge name.

Parameters

<code>bridge_name</code>	The name of the bridge with which to associate the endpoint.
<code>type</code>	The <code>EndpointType</code> of the new endpoint.

<code>name</code>	The unique identifier to use for the endpoint.

Exceptions

<code>InvalidEndpoint</code>	The <code>type</code> or the <code>name</code> specified are incorrect. The return code will contain the details.
<code>BridgeNameAlreadyExists</code>	

EndpointAdmin::get_sink_endpoint()

SinkEndpoint get_sink_endpoint(in BridgeName bridge_name)

```
raises (BridgeNameNotFound);
```

`get_sink_endpoint()` returns a reference to the sink endpoint of the specified bridge.

Parameters

`bridge_name`

The name of the bridge from which to get the sink endpoint.

Exceptions

`BridgeNameNotFound`

No bridges with the specified name exist.

EndpointAdmin::get_source_endpoint()

SourceEndpoint get_source_endpoint(in BridgeName bridge_name)

```
raises (BridgeNameNotFound);
```

`get_source_endpoint()` returns a reference to the source endpoint of the specified bridge.

Parameters

bridge_name

The name of the bridge from which to get the source endpoint.

Exceptions

BridgeNameNotFound

No bridges with the specified name exist.

EndpointAdmin::get_all_sink_endpoints()

BridgeNameSeq get_all_sink_endpoints();

`get_all_sink_endpoints()` returns a list of the names of all bridges that have sink endpoints associated with them.

EndpointAdmin::get_all_source_endpoints()

BridgeNameSeq get_all_source_endpoints();

`get_all_source_endpoints()` returns a list of the names of all the bridges that have source endpoints associated with them.

IT_MessagingBridgeAdmin Module

`IT_MessagingBridgeAdmin` defines the data, exceptions, and interfaces to create and manage bridges. It defines the following interfaces:

- [IT_MessagingBridgeAdmin::Bridge Interface](#)
- [IT_MessagingBridgeAdmin::BridgeAdmin Interface](#)

IT_MessagingBridgeAdmin Data Types

`IT_MessagingBridgeAdmin::BridgeName`

typedef [IT_MessagingBridge::BridgeName](#) BridgeName;

`BridgeName` specifies the unique identifier for a bridge object.

`IT_MessagingBridgeAdmin::BridgeNameSeq`

typedef [IT_MessagingBridge::BridgeNameSeq](#) BridgeNameSeq;

`BridgeNameSeq` contains a list of `BridgeName`. It is returned by

`IT_MessagingBridgeAdmin::BridgeAdmin::get_all_bridges()`.

`IT_MessagingBridgeAdmin::InvalidEndpointCode`

typedef [IT_MessagingBridge::InvalidEndpointCode](#) InvalidEndpointCode;

`InvalidEndpointCode` specifies the reason for an `InvalidEndpoint` exception.

`IT_MessagingBridgeAdmin::EndpointInfo`

struct EndpointInfo

```
{
  IT_MessagingBridge::EndpointAdmin admin;
  [IT_MessagingBridge::EndpointType] (#it_messagingbridge-data-types)  type;
  [IT_MessagingBridge::EndpointName] (#it_messagingbridge-data-types)  name;
};
```

`EndpointInfo` encapsulated the information needed to specify and endpoint to a bridge. It has the following fields:

<code>admin</code>	A reference to the <code>EndpointAdmin</code> associated with the endpoint. For more information, see IT_MessagingBridge::EndpointAdmin Interface .
<code>type</code>	Specifies the endpoint's type. This correlates to the messaging service to which the endpoint is attached. For more information, see IT_MessagingBridge::EndpointType .
<code>name</code>	Specifies the unique identifier of the endpoint.

IT_MessagingBridgeAdmin Exceptions

`IT_MessagingBridgeAdmin::CannotCreateBridge`

exception `CannotCreateBridge {}`;

`CannotCreateBridge` is raised when there is an error creating a bridge.

`IT_MessagingBridgeAdmin::BridgeNotFound`

exception `BridgeNotFound {}`;

`BridgeNotFound` is raised when the bridge specified in either `get_bridge()` or `find_bridge()` does not exist.

`IT_MessagingBridgeAdmin::BridgeAlreadyExists`

exception `BridgeAlreadyExists {BridgeName bridge_name;}`;

`BridgeAlreadyExists` if the endpoints specified in `create_bridge()` are already connected to form a bridge. It returns the name of the bridge connecting the endpoints.

`IT_MessagingBridgeAdmin::BridgeNameAlreadyExists`

exception `BridgeNameAlreadyExists {}`;

`BridgeNameAlreadyExists` is raised when the bridge name specified in `create_bridge()` is already in use.

`IT_MessagingBridgeAdmin::InvalidEndpoint`

exception `InvalidEndpoint`

```
{  
    EndpointInfo endpoint;  
    InvalidEndpointCode code;  
};
```

`InvalidEndpoint` is raised when one of the endpoints specified in `create_bridge()` is invalid. The first return value is a reference to the invalid endpoint and the second return value specifies why the endpoint is invalid.

IT_MessagingBridgeAdmin::Bridge Interface

```
interface Bridge
{
    readonly attribute BridgeName name;
    readonly attribute EndpointInfo source;
    readonly attribute EndpointInfo sink;
    void start();
    void suspend();
    void stop();
    void destroy();
};
```

Bridge specifies the attributes and operations of a uni-directional bridge between two endpoints. The bridge maintains a reference for each of its endpoints and provides the operations that control the flow of messages accross the bridge. It is recomendaded that developers use the operation defined on the bridge object as opposed to the operations specified by the [IT_MessagingBridge::SourceEndpoint Interface](#).

Bridge::name

readonly attribute BridgeName name;

name specifies the identifier for the bridge.

Bridge::source

readonly attribute EndpointInfo source;

source specifies the endpoint from which the bridge recieves messages.

Bridge::sink

readonly attribute EndpointInfo sink;

sink specifies the endpoint to which the bridge forwards messages.

Bridge::start()

void start();

start() signals the source endpoint to begin delivering messages to the bridge. Once the bridge begins recieving messages it fowards them the the sink endpoint.

Bridge::suspend()

void suspend();

`suspend()` signals the source endpoint to suspend the flow of messages. The bridge will not forward any messages while it is suspended, but the source endpoint will continue to queue messages for delivery to the bridge. Once `start()` has been called, the queued messages are forwarded.

Bridge::stop()

void stop();

`stop()` signals the source endpoint to completely halt the delivery of messages. No messages are queued for later delivery.

Bridge::destroy()

void destroy();

`destroy()` destroys the bridge and cleans up all the resources associated with it, including the bridge endpoints.

IT_MessagingBridgeAdmin::BridgeAdmin Interface

```
interface BridgeAdmin
{
    Bridge create_bridge(in BridgeName  bridge_name,
                        in EndpointInfo source,
                        in EndpointInfo sink)
    raises (InvalidEndpoint, BridgeAlreadyExists,
           BridgeNameAlreadyExists, CannotCreateBridge);
    Bridge get_bridge(in BridgeName bridge_name)
    raises (BridgeNotFound);
    Bridge find_bridge(in  EndpointInfo source,
                      in  EndpointInfo sink,
                      out BridgeName bridge_name)
    raises (BridgeNotFound);
    BridgeNameSeq get_all_bridges();
};
```

`BridgeAdmin` defines the factory operation for `Bridge` objects. It also defines two operations to discover active bridges and one operation to list the bridges in the service. Developers get a reference to the `BridgeAdmin` by using the initial reference key `"IT_Messaging"`.

`BridgeAdmin::create_bridge()`

`Bridge create_bridge(in BridgeName bridge_name,`

```
                        in EndpointInfo source,
                        in EndpointInfo sink)
    raises (InvalidEndpoint, BridgeAlreadyExists,
           BridgeNameAlreadyExists, CannotCreateBridge);
```

`create_bridge()` creates a new uni-directional bridge between two endpoints and returns a reference to the bridge.

Parameters

<code>bridge_name</code>	Specifies the unique identifier for the bridge.

<code>source</code>	Specifies the endpoint from which the bridge will receive messages.
<code>sink</code>	Specifies the endpoint to which the bridge will forward messages.

Exceptions

<code>InvalidEndpoint</code>	One of the specified endpoints is not a valid endpoint for the new bridge.
<code>BridgeAlreadyExists</code>	A bridge connecting the two endpoints already exists.
<code>BridgeNameAlreadyExists</code>	The name specified for the bridge is already in use.
<code>CannotCreateBridge</code>	An unspecified error occurred while creating the bridge.

BridgeAdmin::get_bridge()

Bridge get_bridge(in BridgeName bridge_name)

```
raises (BridgeNotFound);
```

get_bridge() returns a reference to the specified bridge.

Parameters

bridge_name

Specifies the name of the bridge to get.

Exceptions

BridgeNotFound

The specified bridge does not exist.

BridgeAdmin::find_bridge()

Bridge find_bridge(in EndpointInfo source,

```
        in EndpointInfo sink,  
        out BridgeName bridge_name)  
raises (BridgeNotFound);
```

`find_bridge()` returns a reference to the bridge linking the specified endpoints. The name of the bridge is returned as a parameter to the operation.

Parameters

<code>source</code>	Specifies the endpoint from which the bridge receives messages.
<code>sink</code>	Specifies the endpoint to which the bridge forwards messages.
<code>bridge_name</code>	Specifies the name of the returned bridge.

Exceptions

`BridgeNotFound`

The specified bridge does not exist.

`BridgeAdmin::get_all_bridges()`

`BridgeNameSeq get_all_bridges();`

`get_all_bridges()` returns a list containing the names of all existing bridges.

IT_NotifyBridge Module

`IT_NotifyBridge` defines an extension of `IT_MessagingBridge::SinkEndpoint`. This extension provides the method used by a bridge to forward notification events.

IT_NotifyBridge Exceptions

`IT_NotifyBridge::MappingFailure`

exception `MappingFailure` {};

`MappingFailure` is raised when the bridge is unable to properly map messages to a notification event.

`IT_NotifyBridge::EndpointNotConnected`

exception `EndpointNotConnected` {};

`EndpointNotConnected` is raised when an attempt to receive messages through a `SinkEndpoint` that is not connected to a `SourceEndpoint` is made.

IT_NotifyBridge::SinkEndpoint Interface

```
interface SinkEndpoint : IT_MessagingBridge::SinkEndpoint
{
    void send_events(in CosNotification::EventBatch events)
    raises (MappingFailure, EndpointNotConnected);
};
```

`IT_NotifyBridge::SinkEndpoint` extends the functionality of `IT_MessagingBridge::SinkEndpoint` to include the ability to receive notification style events. Due to the inheritance from `IT_MessagingBridge::SinkEndpoint`, it retains all of the functionality of a generic endpoint. `IT_NotifyBridge::SinkEndpoint` receives a batch of notification events using the `CosNotification::EventBatch` structure.

`SinkEndpoint::send_events()`

`void send_events(in CosNotification::EventBatch events)`

```
raises (MappingFailure, EndpointNotConnected);
```

`send_events()` receives a batch of notification events from a bridge and passes them into the receiving messaging service.

Parameters

events

A group of notification events packaged into a `CosNotification::EventBatch`.

Exceptions

<code>MappingFailure</code>	The bridge encountered an error mapping the JMS messages to notification events.
<code>EndpointNotConnected</code>	The <code>SinkEndpoint</code> is not connected to a <code>SourceEndpoint</code> .

IT_NamedKey

The IT_NamedKey Module

Defines interfaces related to managing named keys (which appear as object identifiers in `corbaloc:` URLs).

Description

The named key registry is implemented by the Orbix locator service. Servers register key/object reference associations in the named key registry and clients use these keys to retrieve the associated object references. In practice, this module is intended to facilitate defining `corbaloc:` URLs that are human-readable.

See also

IT_PlainTextKey

IT_NamedKey::NamedKeyList

A list of named key strings.

Description

This type is used for the return value of the IT_NamedKey::NamedKeyRegistry::list_text_keys() operation.

IT_NamedKey::NAMED_KEY_REGISTRY

A string used by the locator to identify the named key registry service.

See also

IT_Location::Locator::resolve_service()

IT_NamedKey::NamedKeyRegistry

Defines operations to register, de-register, and lookup named keys in the named key registry.

Description

Named keys are used in conjunction with `corbaloc:` URLs to provide a simple way for clients to access CORBA services. A typical `corbaloc:` URL has the following format:

```
corbaloc:iiop:*GIOPVersion*:*Host*:*Port*/*Key*
```

This format can be explained as follows:

- *GIOPVersion*—the version of GIOP used on the connection. Can be either `1.0`, `1.1`, or `1.2`.
- *Host:Port*—the hostname, *Host*, and IP port, *Port*, of the Orbix locator service (indirect persistence).
- *Key*—a key string previously registered either with the named key registry or with the `plain_text_key` plug-in.

To register an object reference with the named key registry, the server must first obtain an `IT_Location::Locator` instance by passing the string, `IT_Locator`, to `CORBA::ORB::resolve_initial_references()`. Call the operation, `IT_Location::Locator::resolve_service()`, passing the argument, `IT_NamedKey::NAMED_KEY_REGISTRY`, to obtain an `IT_NamedKey::NamedKeyRegistry` instance. The server can then register one or more named keys by calling the `add_text_key()` operation on `IT_NamedKey::NamedKeyRegistry`.

Note

The named key string format used in this interface does *not* support URL escape sequences (the `%` character followed by two hexadecimal digits).

C++ implementation

The following C++ code example shows how to obtain a reference to the named key registry and invoke some operations on the registry.

```

// C++
...
// Get the Locator
CORBA::Object_var objref =
orb->resolve_initial_references("IT_Locator");
IT_Location::Locator_var locator =
IT_Location::Locator::_narrow(objref);
// Get the Named Key registry
objref = locator->resolve_service(IT_NamedKey::NAMED_KEY_REGISTRY);
IT_NamedKey::NamedKeyRegistry_var registry =
IT_NamedKey::NamedKeyRegistry::_narrow(objref);
// Invoke some operations on the registry
try
{
registry->add_text_key("MyNamedKey", MyCORBAObjectRef);
objref = registry->find_text_key("MyNamedKey");
registry->remove_text_key("MyNamedKey");
}
catch (const IT_NamedKey::NamedKeyRegistry::EntryAlreadyExists& ex)
{
cerr << "ERROR: Unable to add an IMR entry for key: "
<< ex.name << endl;
}
catch (const IT_NamedKey::NamedKeyRegistry::EntryNotFound & ex)
{
cerr << "ERROR: IMR entry not found: " << ex.name << endl;
}

```

See also

[IT_PlainTextKey::Forwarder](#)

[IT_NamedKey::NamedKeyRegistry::EntryAlreadyExists](#)

Raised if you attempt to add a named key that clashes with an existing named key in the registry.

Description

The exception's `name` element contains the string value of the existing named key in the registry.

See also

[IT_NamedKey::NamedKeyRegistry::add_text_key\(\)](#)

[IT_NamedKey::NamedKeyRegistry::EntryNotFound](#)

Raised if a named key could not be found in the registry.

Description

The exception's `name` element contains the string value of the named key that you were attempting to find.

See also

`IT_NamedKey::NamedKeyRegistry::remove_text_key()`

`IT_NamedKey::NamedKeyRegistry::add_text_key()`

Adds a new entry to the named key registry.

Description

The specified object reference, `the_object`, is keyed by the named key parameter, `name`.

Internally, the named key registry converts the named key string into an octet sequence and stores the value as an octet sequence (as required by the GIOP specification).

Parameters

`name`

A named key in string format (URL escape sequences not supported).

`the_object`

The object reference associated with the named key.

Exceptions

`EntryAlreadyExists`

Raised if the registry already contains an entry with the given `name`.

`IT_NamedKey::NamedKeyRegistry::remove_text_key()`

Removes a named key from the registry.

Parameters

`name`

A named key in string format (URL escape sequences not supported).

Exceptions

`EntryNotFound`

Raised if the specified key, `name`, does not exist in the registry.

`IT_NamedKey::NamedKeyRegistry::find_text_key()`

Finds the registry entry for a particular named key (in string format).

Returns Returns the object reference associated with the specified key.

Parameters

`name`

A named key in string format (URL escape sequences not supported).

IT_NamedKey::NamedKeyRegistry::find_octets_key()

Finds the registry entry for a particular named key (in octets format).

Description

According to the CORBA specification, the native format of a named key is a sequence of octets (binary 8-bit format). This operation enables you look up the registry by specifying the named key in this native format.

Returns Returns the object reference associated with the specified key.

Parameters

octets

A named key in octets format.

IT_NamedKey::NamedKeyRegistry::list_text_keys()

Lists all of the keys currently stored in the named key registry.

Returns A sequence of strings containing all of the named keys currently in the registry.

IT_Naming Module

The `IT_Naming` module contains a single interface, `IT_NamingContextExt`, which provides the method used to bind an object group into the naming service.

`IT_NamingContextExt` extends `CosNaming::NamingContextExt` and provides the method `bind_object_group` which binds an object group to a Rocket Software proprietary naming service.

IT_Naming::IT_NamingContextExt Interface

The complete `IT_NamingContextExt` is as follows:

```
// IDL in Module IT_Naming
Interface IT_NamingContextExt : CosNaming::NamingContextExt
{
    readonly attribute IT_LoadBalancing::ObjectGroupFactory og_factory;
    readonly attribute IT_NamingAdmin::NamingAdmin admin;
    void bind_object_group(
        in CosNaming::Name n,
        in IT_LoadBalancing::ObjectGroup obj_gp )
    raises (CosNaming::NamingContext::NotFound,
           CosNaming::NamingContext::CannotProceed,
           CosNaming::NamingContext::InvalidName,
           CosNaming::NamingContext::AlreadyBound);
};
```

IT_Naming::IT_NamingContextExt::bind_object_group() Method

Binds an object group to an entry in the naming service.

Parameters

<code>n</code>	A <code>CosNaming::Name</code> specifying the naming service node to bind the object group to.
<code>obj_gp</code>	The object group to bind into the naming service.

EnhancementOrbix enhancement to CORBA.

Exceptions

<code>NamingContext::NotFound</code>	<code>n</code> did not point to a valid entry in the naming service.
<code>NamingContext::CannotProceed</code>	The call failed due an internal error.
<code>NamingContext::InvalidName</code>	<code>n</code> has a sequence length of zero.
<code>NamingContext::AlreadyBound</code>	<code>obj_gp</code> is already bound into the naming service

IT_NotifyChannelAdmin Module

Rocket Software proprietary versions of some of the interfaces from `CosNotifyChannelAdmin`.

IT_NotifyChannelAdmin::GroupProxyPushSupplier Interface

```
interface GroupProxyPushSupplier :
    CosNotifyChannelAdmin::ProxyPushSupplier
{
    void [connect_group_any_push_consumer]
    (#it_notifychanneladmingroupproxypushsupplier-interface)(
        in IT_NotifyComm::GroupPushConsumer group_push_consumer)
        raises(CosEventChannelAdmin::AlreadyConnected,
            CosEventChannelAdmin::TypeError);
};
```

The `GroupProxyPushSupplier` interface supports connections to the channel by endpoint groups receiving events from the channel as untyped `Anys`. Note that such endpoint groups are functionally similar to OMG Event Service push-style consumers of untyped events. The `GroupProxyPushSupplier` interface defined here, however, supports event filtering and configuration of QoS properties in addition to taking advantage of the IP/Multicast message transport.

Through inheritance of the `ProxyPushSupplier` interface, the `GroupProxyPushSupplier` interface supports administration of QoS properties, administration of a list of associated filter, mapping filters for event priority and lifetime, and a read-only attribute containing a reference to the `ConsumerAdmin` that created it. This inheritance implies that a `GroupProxyPushSupplier` instance supports an operation that returns the list of event types that the proxy supplier can supply, and an operation that returns information about the group's ability to accept a QoS request. The `GroupProxyPushSupplier` interface also inherits a pair of operations that suspend and resume the connection between a `GroupProxyPushSupplier` instance and its associated endpoint group. During the time a connection is suspended, the `GroupProxyPushSupplier` accumulates events destined for the endpoint group but does not transmit them until the connection is resumed.

The `GroupProxyPushSupplier` interface inherits the `NotifySubscribe` interface defined in `CosNotifyComm`, enabling it to be notified whenever its associated endpoint group changes the list of event types it is interested in receiving.

The `GroupProxyPushSupplier` interface also inherits from the `PushSupplier` interface defined in `CosEventComm`. This interface supports the operation to disconnect the `GroupProxyPushSupplier` from its associated endpoint group.

The `GroupProxyPushSupplier` interface defines the operation to establish the connection over which the consumer's endpoint group receives events from the channel.

`GroupProxyPushSupplier::connect_group_any_push_consumer()`

```
void connect_group_any_push_consumer(
    in IT_NotifyComm::GroupPushConsumer group_push_consumer)
raises(CosEventChannelAdmin::AlreadyConnected,
       CosEventChannelAdmin::TypeError);
```

Establishes a connection between an endpoint group of consumers expecting events in the form of `Anys`, and an event. Once the connection is established, the `GroupProxyPushSupplier` sends events to the endpoint group by invoking `push()` on the connected consumer.

Parameters

`group_push_consumer`

The reference to an object supporting the `GroupPushConsumer` interface defined in `IT_NotifyComm`. This reference is that of a consumer connecting to the channel for the members of an endpoint group.

Exceptions

<code>AlreadyConnected</code>	Raised if the target object of this operation is already connected to a push consumer object.
<code>TypeError</code>	An implementation of the GroupProxyPushSupplier interface may impose additional requirements on the interface supported by the push consumers in a group (for example, it may be designed to invoke some operation other than <code>push</code> in order to transmit events). If the consumers in the group being connected do not meet those requirements, this operation raises the <code>TypeError</code> exception.

IT_NotifyChannelAdmin:GroupSequenceProxyPushSupplier Interface

```
interface GroupSequenceProxyPushSupplier :
    CosNotifyChannelAdmin::SequenceProxyPushSupplier
{
    void [connect_group_sequence_push_consumer]
    (#it_notifychanneladmingroupsequenceproxypushsupplier-interface)(
        in IT_NotifyComm::GroupSequencePushConsumer
        group_push_consumer)
    raises(CosEventChannelAdmin::AlreadyConnected,
        CosEventChannelAdmin::TypeError);
};
```

The `GroupSequenceProxyPushSupplier` interface supports connections to the channel by endpoint groups that receive sequences of structured events from the channel.

Through inheritance of `SequenceProxyPushSupplier`, the `GroupSequenceProxyPushSupplier` interface supports administration of QoS properties, administration of a list of associated filter objects, and a read-only attribute containing a reference to the `ConsumerAdmin` that created it. This inheritance also implies that a `GroupSequenceProxyPushSupplier` instance supports an operation that returns the list of event types that the proxy supplier can supply, and an operation that returns information about the endpoint group's ability to accept a QoS request. The `GroupSequenceProxyPushSupplier` interface also inherits a pair of operations which suspend and resume the connection between a `GroupSequenceProxyPushSupplier` instance and its associated endpoint group. During the time a connection is suspended, the `GroupSequenceProxyPushSupplier` accumulates events destined for the endpoint group but does not transmit them until the connection is resumed.

The `GroupSequenceProxyPushSupplier` interface also inherits from the `SequencePushSupplier` interface defined in `CosNotifyComm`. This interface supports the operation to close the connection from the endpoint group to the `GroupSequenceProxyPushSupplier`. Since the `SequencePushSupplier` interface inherits from `NotifySubscribe`, a `GroupSequenceProxyPushSupplier` can be notified whenever the list of event types that its associated endpoint group is interested in receiving changes.

The `GroupSequenceProxyPushSupplier` interface defines the operation to establish the connection over which the endpoint group receives events from the channel.

`GroupSequenceProxyPushSupplier::connect_group_sequence_push_consumer()`

```
void connect_group_sequence_push_consumer(
    in IT_NotifyComm::GroupSequencePushConsumer
    group_push_consumer)
raises(CosEventChannelAdmin::AlreadyConnected,
    CosEventChannelAdmin::TypeError);
```

Establishes a connection between an endpoint group of consumers expecting sequences of structured events and an event channel. Once the connection is established, the `GroupSequenceProxyPushSupplier` sends events to its endpoint group by invoking `push_structured_events()` on the connected consumer.

Parameters

`group_push_consumer`

A reference to an object supporting the `GroupSequencePushConsumer` interface defined in `IT_NotifyComm`. This reference is that of a consumer connecting to the channel for the members of an endpoint group.

Exceptions

<code>AlreadyConnected</code>	Raised if the target object of this operation is already connected to a push consumer.
<code>TypeError</code>	An implementation of the <code>GroupSequenceProxyPushSupplier</code> interface may impose additional requirements on the interface supported by an endpoint group (for example, it may be designed to invoke some operation other than <code>push_structured_events</code> in order to transmit events). If the members of the endpoint group being connected do not meet those requirements, this operation raises the <code>TypeError</code> exception.

IT_NotifyChannelAdmin::GroupStructuredProxyPushSupplier Interface

```
interface GroupStructuredProxyPushSupplier :
    CosNotifyChannelAdmin::StructuredProxyPushSupplier
{
    void [connect_group_structured_push_consumer]
    (#it_notifychanneladmingroupstructuredproxypushsupplier-interface)(
        in IT_NotifyComm::GroupStructuredPushConsumer
        group_push_consumer)
    raises(CosEventChannelAdmin::AlreadyConnected,
        CosEventChannelAdmin::TypeError);
};
```

The `GroupStructuredProxyPushSupplier` interface supports connections to the channel by endpoint groups that receive structured events from the channel.

Through inheritance of `StructuredProxyPushSupplier`, the `GroupStructuredProxyPushSupplier` interface supports administration of QoS properties, administration of a list of associated filters, mapping filters for event priority and lifetime, and a read-only attribute containing a reference to the `ConsumerAdmin` that created it. This inheritance implies that a `GroupStructuredProxyPushSupplier` instance supports an operation that returns the list of event types that the proxy supplier can supply, and an operation that returns information about the group's ability to accept a QoS request. The `GroupStructuredProxyPushSupplier` interface also inherits a pair of operations to suspend and resume the connection between a `GroupStructuredProxyPushSupplier` instance and its associated endpoint group. During the time a connection is suspended, the `GroupStructuredProxyPushSupplier` accumulates events destined for the endpoint group but does not transmit them until the connection is resumed.

The `GroupStructuredProxyPushSupplier` interface also inherits from the `StructuredPushSupplier` interface defined in `CosNotifyComm`. This interface defines the operation to disconnect the `GroupStructuredProxyPushSupplier` from its associated endpoint group. In addition, the `GroupStructuredProxySupplier` interface inherits from `NotifySubscribe`, enabling it to be notified whenever its associated endpoint group changes the list of event types it is interested in receiving.

The `GroupStructuredProxyPushSupplier` interface defines the operation to establish the connection over which the consumer's endpoint group receives events from the channel.

`GroupStructuredProxyPushSupplier::connect_group_structured_push_consumer()`

```
void connect_group_group_structured_push_consumer(
    in IT_NotifyComm::GroupStructuredPushConsumer
    group_push_consumer)
raises(CosEventChannelAdmin::AlreadyConnected,
    CosEventChannelAdmin::TypeError );
```

Establishes a connection between an endpoint group of consumers expecting structured events and an event channel. Once the connection is established, the `GroupStructuredProxyPushSupplier` sends events to the endpoint group invoking `push_structured_event()` on the connected consumer.

Parameters

`group_push_consumer`

A reference to an object supporting the `GroupStructuredPushConsumer` interface defined in `IT_NotifyComm`. This reference is that of a consumer connecting to the channel for the members of an endpoint group.

Exceptions

<code>AlreadyConnected</code>	Raised if the target object of this operation is already connected to a push consumer.
<code>TypeError</code>	An implementation of the <code>GroupStructuredProxyPushSupplier</code> interface may impose additional requirements on the interface supported by an endpoint group (for example, it may be designed to invoke some operation other than <code>push_structured_event</code> to transmit events). If the members of the endpoint group being connected do not meet those requirements, this operation raises the <code>TypeError</code> exception.

IT_NotifyComm Module

A module that defines Rocket Software proprietary versions of some interfaces from `CosNotifyComm`.

IT_NotifyComm::GroupNotifyPublish Interface

```
interface GroupNotifyPublish
{
    oneway void [offer_change](#cosnotifycommnotifypublish-interface)(
        in CosNotification::EventTypeSeq added,
        in CosNotification::EventTypeSeq removed);
};
```

The `GroupNotifyPublish` interface supports an operation allowing a supplier to announce, or publish, the names of the types of events it supplies. It is an abstract interface which is inherited by all group consumer interfaces, and enables suppliers to inform consumers supporting this interface of the types of events they intend to supply.

When implemented by a group consumer, it allows the consumer to modify its subscription list accordingly.

`GroupNotifyPublish::offer_change()`

```
oneway void offer_change(
    in CosNotification::EventTypeSeq added,
    in CosNotification::EventTypeSeq removed);
```

Allows a supplier of notifications to announce, or publish, the names of the types of events it supplies to consumers using IP/Multicast.

Note

Each event type name consists of two components: the name of the domain in which the event type has meaning, and the name of the actual event type. Either component of a type name may specify a complete domain/event type name, a domain/event type name containing the wildcard '*' character, or the special event type name "%ALL".

Parameters

added	Sequence of event type names specifying the event types the supplier is adding to the list of event types it plans to supply.
removed	Sequence of event type names specifying the event types which the supplier no longer plans to supply.

IT_NotifyComm::GroupPushConsumer Interface

```
interface GroupPushConsumer : [GroupNotifyPublish](../
it_notifycommgroupnotifypublish_interface/
it_notifycommgroupnotifypublish_interface.md)
{
    oneway void push(in any data);
    oneway void [disconnect_push_consumer](#it_notifycommgrouppushconsumer-
interface)();
};
```

The `GroupPushConsumer` interface supports an operation enabling group consumers to receive unstructured events by the push model. It also defines an operation to disconnect the consumer's endpoint group from its associated proxy supplier. In addition, the `GroupPushConsumer` interface inherits `GroupNotifyPublish` which enables a supplier to inform an instance supporting this interface whenever there is a change to the types of events it intends to produce.

Note

An object supporting the `GroupPushConsumer` interface can receive all events that are supplied to its associated channel. How events supplied to the channel in other forms are internally mapped into an unstructured event for delivery to a `GroupPushConsumer` is summarized in the *CORBA Notification Service Guide*.

`GroupPushConsumer::push()`

```
oneway void push(in any data);
```

Receives unstructured events by the push model. The implementation of `push()` is application specific, and is supplied by application developers.

Parameters

data

A parameter of type `CORBA::Any`. Upon invocation, this parameter contains an unstructured event being delivered to the group.

`GroupPushConsumer::disconnect_push_consumer()`

```
oneway void disconnect_push_consumer();
```

Terminates a connection between the target `GroupPushConsumer` and its associated group proxy supplier. The result of this operation is that the target `GroupPushConsumer` releases all resources allocated to support the connection and disposes of the groups object reference. It also disconnects all other members of the target `GroupPushConsumer`'s endpoint group.

IT_NotifyComm::GroupSequencePushConsumer Interface

```
interface GroupSequencePushConsumer : [GroupNotifyPublish](../
it_notifycommgroupnotifypublish_interface/
it_notifycommgroupnotifypublish_interface.md)
{
    oneway void [push_structured_events]
    (#it_notifycommgroupsequencepushconsumer-interface)(
        in CosNotification::EventBatch notifications);
    oneway void [disconnect_sequence_push_consumer]
    (#it_notifycommgroupsequencepushconsumer-interface)();
};
```

The `GroupSequencePushConsumer` interface supports an operation enabling group consumers to receive sequences of structured events using the push model. It also defines an operation to disconnect the consumer's endpoint group from its associated proxy supplier. The `GroupSequencePushConsumer` interface inherits `GroupNotifyPublish` which enabling a supplier to inform an instance supporting this interface whenever there is a change to the types of events it intends to produce.

Note

An object supporting the `GroupSequencePushConsumer` interface can receive all events which were supplied to its associated channel, including events supplied in a form other than a sequence of structured events. How events supplied to the channel in other forms are internally mapped into a sequence of structured events for delivery to a `GroupSequencePushConsumer` is summarized in the *CORBA Notification Service Guide*.

`GroupSequencePushConsumer::push_structured_events()`

```
oneway void push_structured_events(
    in CosNotification::EventBatch notifications);
```

Receive sequences of structured events by the push model. The implementation of `push_structured_events` is application specific, and is supplied by application developers.

The maximum number of events that are transmitted within a single invocation of this operation, along with the amount of time a supplier of a sequence of structured events accumulates individual events into the sequence before invoking this operation are controlled by QoS property settings as described in the *CORBA Notification Service Guide*.

Parameters

notifications

A parameter of type EventBatch as defined in CosNotification. Upon invocation, this parameter contains a sequence of structured events being delivered to the group.

GroupSequencePushConsumer::disconnect_sequence_push_consumer()

```
oneway void disconnect_sequence_push_consumer();
```

Terminates a connection between the target `GroupSequencePushConsumer` and its associated group proxy supplier. The result of this operation is that the target `GroupSequencePushConsumer` releases all resources allocated to support the connection and disposes of the groups object reference. This also disconnects all other members of the target `GroupSequencesPushConsumer`'s endpoint group.

IT_NotifyComm::GroupStructuredPushConsumer Interface

```
interface GroupStructuredPushConsumer : [GroupNotifyPublish](../
it_notifycommgroupnotifypublish_interface/
it_notifycommgroupnotifypublish_interface.md)
{
    oneway void [push_structured_event](#cosnotifycommstructuredpushconsumer-
interface)(
        in CosNotification::StructuredEvent notification);
    oneway void [disconnect_structured_push_consumer]
(#cosnotifycommstructuredpushconsumer-interface)();
};
```

The `GroupStructuredPushConsumer` interface supports an operation enabling group consumers to receive structured events by the push model. It also defines an operation to disconnect the push consumer's endpoint group from its associated proxy supplier. In addition, the `GroupStructuredPushConsumer` interface inherits `GroupNotifyPublish` which enables a supplier to inform an instance supporting this interface whenever there is a change to the types of events it intends to produce.

Note

An object supporting the `GroupStructuredPushConsumer` interface can receive all events that were supplied to its associated channel, including events supplied in a form other than a structured event. How events supplied to the channel in other forms are internally mapped into a structured event for delivery to a `GroupStructuredPushConsumer` is summarized in the *CORBA Notification Service Guide*.

`GroupStructuredPushConsumer::push_structured_event();`

```
oneway void push_structured_event(
    in CosNotification::StructuredEvent notification);
```

Receives structured events by the push model. The implementation of `push_structured_event()` is application specific, and is supplied by application developers.

Parameters

notification

A parameter of type StructuredEvent as defined in CosNotification. Upon invocation, this parameter contains a structured event being delivered to the group.

GroupStructuredPushConsumer::disconnect_structured_push_consumer()

```
oneway void disconnect_structured_push_consumer();
```

Terminates a connection between the target `GroupStructuredPushConsumer` and its associated group proxy supplier. The result of this operation is that the target `GroupStructuredPushConsumer` releases all resources allocated to support the connection and disposes of the groups object reference. This also disconnects all other members of the target `GroupStructuredPushConsumer`'s endpoint group.

IT_NotifyLogAdmin Module

This module extends the OMG specified NotifyLog and NotifyLogFactory interfaces to support event subscription and publication. Also provides access to a default filter factory.

IT_NotifyLogAdmin::NotifyLog Interface

This interface provides Rocket Software specific extensions to DsNotifyLogAdmin::NotifyLog to support notification style event publication and subscription.

```
interface NotifyLog :DsNotifyLogAdmin::NotifyLog
{
    CosNotification::EventTypeSeq [obtain_offered_types()]
    (#it_notifylogadminnotifylog-interface);
    CosNotification::EventTypeSeq [obtain_subscribed_types()]
    (#it_notifylogadminnotifylog-interface);
};
```

NotifyLog::obtain_offered_types()

CosNotification::EventTypeSeq obtain_offered_types();

Allows event consumers to ascertain what events are being advertised by event suppliers.

NotifyLog::obtain_subscribed_types()

CosNotification::EventTypeSeq obtain_subscribed_types();

Allows event suppliers to ascertain which events the event consumers in the channel are interested in receiving.

IT_NotifyLogAdmin::NotifyLogFactory Interface

Extends DsNotifyLogAdmin::NotifyLogFactory to include a link to the notification channel's default filter factory and a link to the telecom logging service's manager.

```
interface NotifyLogFactory :DsNotifyLogAdmin::NotifyLogFactory
{
  readonly attribute CosNotifyFilter::FilterFactory [default_filter_factory]
  (#it_notifylogadminnotifylogfactory-interface);
  readonly attribute IT_LogAdmin::Manager [manager]
  (#it_notifylogadminnotifylogfactory-interface);
};
```

NotifyLogFactory::default_filter_factory Attribute

readonly attribute CosNotifyFilter::FilterFactory default_filter_factory;

Provides a reference to the notification channel's default filter factory, which is used to create new filter objects for `NotifyLog` objects.

NotifyLogFactory::manager Attribute

readonly attribute IT_LogAdmin::Manager manager;

Provides a link to the telecom logging service's manager.

IT_PlainTextKey

The IT_PlainTextKey Module

IT_PlainTextKey

Defines the interface that accesses the `plain_text_key` plug-in.

Description

This module is intended to facilitate defining `corbaloc` URLs that are human-readable. The `plain_text_key` plug-in (part of the `it_art` library) stores a transient list of key/object reference associations and makes this list accessible through the `IT_PlainTextKey::Forwarder` interface.

The `plain_text_key` plug-in is intended to be used in conjunction with *direct persistence* (that is, a server that embeds its own address details into an IOR, so that client connections are made directly to the server, bypassing the locator). By registering a key with the `plain_text_key` plug-in, you can alias a GIOP object ID with a human-readable key. The key can then be used to construct a human-readable `corbaloc` URL.

See also

`IT_NamedKey`

IT_PlainTextKey::Forwarder

Defines an operation to register a key/object reference entry with the `plain_text_key` plug-in.

Description

Plain text keys (or named keys) are used in conjunction with `corbaloc:` URLs to provide a simple way for clients to access CORBA services. A typical `corbaloc:` URL has the following format:

```
corbaloc:iiop:*GIOPVersion*:*Host*:*Port*/*Key*
```

This format can be explained as follows:

- *GIOPVersion*—the version of GIOP used on the connection. Can be either `1.0`, `1.1`, or `1.2`.

- *Host:Port*—the hostname, *Host*, and IP port, *Port*, of the CORBA service (direct persistence).
- *Key*—a key string previously registered either with the `plain_text_key` plug-in or with the named key registry.

To register an object reference with the `plain_text_key` plug-in, the server must obtain an `IT_PlainTextKey::Forwarder` instance by passing the string, `IT_PlainTextKeyForwarder`, to `CORBA::ORB::resolve_initial_references()`. The server can then register one or more named keys by calling the `add_plain_text_key()` operation on the `IT_PlainTextKey::Forwarder` instance.

Note

The key string format used in this interface does *not* support URL escape sequences (the % character followed by two hexadecimal digits).

Note

The `plain_text_key` plug-in is intended for use with *direct persistence* (that is, a server that embeds its own address details into an IOR, so that client connections are made directly to the server, bypassing the locator).

C++ implementation

The following C++ code shows how to obtain a reference to a plain text key forwarder object and add a new entry.

```
// C++
CORBA::Object_var objref = the_orb->resolve_initial_references(
    "IT_PlainTextKeyForwarder"
);
IT_PlainTextKey::Forwarder_var forwarder =
    IT_PlainTextKey::Forwarder::_narrow(objref);
forwarder->add_plain_text_key(
    "MyPlainTextKey",
    MyCORBAObjectReference
);
```

See also

`IT_NamedKey::NamedKeyRegistry`

`IT_PlainTextKey::Forwarder::add_plain_text_key()`

Adds a key/object reference association to a list maintained by the `plain_text_key` plug-in.

Description

The specified object reference, `the_object`, is keyed by the key parameter, `object_name`.

Internally, the `plain_text_key` plug-in converts the named key string into an octet sequence and stores the value as an octet sequence (as required by the GIOP specification).

Parameters

`object_name`

A key in string format (URL escape sequences not supported).

`the_object`

The object reference associated with the key.

See also

`IT_NamedKey::NamedKeyRegistry::add_text_key()`

IT_PortableServer Overview

This module contains Orbix policy enhancements to the `PortableServer` module. The `IT_PortableServer` policies are:

- `ObjectDeactivationPolicy`
- `PersistenceModePolicy`
- `DispatchWorkQueuePolicy`

The `IT_PortableServer` module also contains the following common data structures and constants related to the policies:

- `OBJECT_DEACTIVATION_POLICY_ID`
- `ObjectDeactivationPolicyValue`
- `PERSISTENCE_MODE_POLICY_ID`
- `PersistenceModePolicyValue`
- `DISPATCH_WORKQUEUE_POLICY_ID`

`IT_PortableServer::OBJECT_DEACTIVATION_POLICY_ID` Constant

// IDL

```
const CORBA::PolicyType OBJECT_DEACTIVATION_POLICY_ID =
IT_PolicyBase::IONA_POLICY_ID + 1;
```

// C++

```
IT_POA_API IT_NAMESPACE_STATIC const
CORBA::ULong OBJECT_DEACTIVATION_POLICY_ID;
```

Defines a policy ID for object deactivation.

Enhancement This is an Orbix enhancement.

`IT_PortableServer::ObjectDeactivationPolicyValue` Enumeration

```
// IDL
enum ObjectDeactivationPolicyValue {
    DISCARD,
    DELIVER,
    HOLD
};
// C++
enum ObjectDeactivationPolicyValue {
    DISCARD,
    DELIVER,
    HOLD,
    _dummy_ObjectDeactivationPolicyValue = 0x80000000
};
```

An object deactivation policy value. Valid values consist of:

```
DISCARD
DELIVER
HOLD
```

EnhancementThis is an Orbix enhancement.

See AlsoIT_PortableServer::ObjectDeactivationPolicy

IT_PortableServer::PERSISTENCE_MODE_POLICY_ID Constant

```
// IDL
```

```
const CORBA::PolicyType PERSISTENCE_MODE_POLICY_ID =
IT_PolicyBase::IONA_POLICY_ID + 3;
```

```
// C++
```

```
IT_POA_API IT_NAMESPACE_STATIC const
    CORBA::ULong PERSISTENCE_MODE_POLICY_ID;
```

Defines a policy ID for the mode of object persistence.

EnhancementThis is an Orbix enhancement.

IT_PortableServer::PersistenceModePolicyValue Enumeration

```
// IDL
```

```
enum PersistenceModePolicyValue {
    DIRECT_PERSISTENCE,
    INDIRECT_PERSISTENCE
};
```

```
enum PersistenceModePolicyValue {
```

```
    DIRECT_PERSISTENCE,
    INDIRECT_PERSISTENCE,
    _dummy_PersistenceModePolicyValue = 0x80000000
};
```

A persistence mode policy value. Valid values consist of:

```
DIRECT_PERSISTENCE
INDIRECT_PERSISTENCE
```

EnhancementThis is an Orbix enhancement.

See AlsoIT_PortableServer::PersistenceModePolicy

IT_PortableServer::DISPATCH_WORKQUEUE_POLICY_ID Constant

```
const CORBA::PolicyType DISPATCH_WORKQUEUE_POLICY_ID = IT_PolicyBase::IONA_POLICY_ID +
42;
```

```
// C++
```

```
IT_POA_API IT_NAMESPACE_STATIC const
    CORBA::ULong DISPATCH_WORKQUEUE_POLICY_ID;
```

Defines the policy ID for using WorkQueues to process ORB requests.

EnhancementThis is an Orbix enhancement.

IT_PortableServer::DispatchWorkQueuePolicy Interface

This is policy used to specify a `WorkQueue` to process ORB requests. It is derived from `CORBA::Policy`. You create instances of the policy by calling `CORBA::ORB::create_policy()`.

```
//IDL
local interface DispatchWorkQueuePolicy : CORBA::Policy
{
    readonly attribute IT_WorkQueue::WorkQueue workqueue;
}
```

IT_PortableServer::ObjectDeactivationPolicy Class

This is an interface for a local policy object derived from CORBA :: Policy. You create instances of `ObjectDeactivationPolicy` by calling `CORBA :: ORB :: create_policy()`.

```
// IDL
interface ObjectDeactivationPolicy : CORBA::Policy {
    readonly attribute ObjectDeactivationPolicyValue value;
};
```

// C++ in namespace IT_PortableServer

```
class IT_POA_API ObjectDeactivationPolicy :
    public virtual ::CORBA::Policy {
public:
    typedef IT_PortableServer::ObjectDeactivationPolicy_ptr
        _ptr_type;
    typedef IT_PortableServer::ObjectDeactivationPolicy_var
        _var_type;
    virtual [~ObjectDeactivationPolicy()]
    (#it_portableserverobjectdeactivationpolicy-class);
    static ObjectDeactivationPolicy_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static ObjectDeactivationPolicy_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static ObjectDeactivationPolicy_ptr _duplicate(
        ObjectDeactivationPolicy_ptr p
    );
    inline static ObjectDeactivationPolicy_ptr _nil();
    virtual ObjectDeactivationPolicyValue [value()]
    (#it_portableserverobjectdeactivationpolicy-class) = 0;
    static const IT_FWString _it_fw_type_id;
};
```

for descriptions of the standard helper functions:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`ObjectDeactivationPolicy::~~ObjectDeactivationPolicy()` Destructor

// C++

```
virtual ~ObjectDeactivationPolicy();
```

The destructor.

EnhancementThis is an Orbix enhancement.

`ObjectDeactivationPolicy::value()`

// C++

```
virtual ObjectDeactivationPolicyValue value() = 0;
```

// Java

```
public ObjectDeactivationPolicyValue value()
```

Returns the value of this object deactivation policy.

EnhancementThis is an Orbix enhancement.

IT_PortableServer::PersistenceModePolicy Class

This is an interface for a local policy object derived from CORBA :: Policy. You create instances of `PersistenceModePolicy` by calling `CORBA :: ORB :: create_policy()`.

```
// IDL
interface PersistenceModePolicy : CORBA::Policy {
    readonly attribute PersistenceModePolicyValue value;
};
// C++ in namespace IT_PortableServer
class IT_POA_API PersistenceModePolicy :
    public virtual ::CORBA::Policy {
public:
    typedef IT_PortableServer::PersistenceModePolicy_ptr _ptr_type;
    typedef IT_PortableServer::PersistenceModePolicy_var _var_type;
    virtual ;
    static PersistenceModePolicy_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static PersistenceModePolicy_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static PersistenceModePolicy_ptr _duplicate(
        PersistenceModePolicy_ptr p
    );
    inline static PersistenceModePolicy_ptr _nil();
    virtual PersistenceModePolicyValue [value()]
    (#it_portableserverobjectdeactivationpolicy-class) = 0;
    static const IT_FWString
        _it_fw_type_id;
};
```

for descriptions of the standard helper functions:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

PersistenceModePolicy::~PersistenceModePolicy() Destructor

```
virtual ~PersistenceModePolicy();
```

The destructor.

EnhancementThis is an Orbix enhancement.

PersistenceModePolicy::value()

// C++

```
virtual PersistenceModePolicyValue value() = 0;
```

Returns the value of this persistent mode policy.

EnhancementThis is an Orbix enhancement.

IT_TLS Overview

The `IT_TLS` module defines a single IDL interface, as follows:

- `IT_TLS::CertValidator`

The following data types are defined in the scope of `IT_TLS` to describe certificate validation errors:

- `IT_TLS::CertChainErrorCode` enumeration
- `IT_TLS::CertChainErrorInfo` structure.

`IT_TLS::CACHE_NONE` Constant

```
const SessionCachingMode CACHE_NONE = 0;
```

A flag that specifies no caching.

See Also `IT_TLS_API::SessionCachingPolicy`

`IT_TLS::CACHE_SERVER` Constant

```
const SessionCachingMode CACHE_SERVER = 0x01;
```

A flag that specifies server-side caching only.

See Also `IT_TLS_API::SessionCachingPolicy`

`IT_TLS::CACHE_CLIENT` Constant

```
const SessionCachingMode CACHE_CLIENT = 0x02;
```

A flag that specifies client-side caching only.

See Also `IT_TLS_API::SessionCachingPolicy`

`IT_TLS::CACHE_SERVER_AND_CLIENT` Constant

```
const SessionCachingMode CACHE_SERVER_AND_CLIENT = 0x04;
```

A flag that specifies both server-side and client-side caching.

See Also `IT_TLS_API::SessionCachingPolicy`

`IT_TLS::CertChainErrorCode` Enumeration

//IDL

```
enum CertChainErrorCode
{
    CERTIFICATE_UNKNOWN,
    CERTIFICATE_DECODE_ERROR,
    CERTIFICATE_SIGNED_BY_UNKNOWN_CA,
    UNSUPPORTED_CERTIFICATE,
    CERTIFICATE_EXPIRED,
    CERTIFICATE_NOT_YET_VALID,
    CERTIFICATE_REVOKED,
    BAD_CERTIFICATE,
    CERTIFICATE_SIGNED_BY_NON_CA_CERTIFICATE,
    CERTIFICATE_CHAIN_TOO_LONG,
    CERTIFICATE_FAILED_CONSTRAINTS_VALIDATION,
    CERTIFICATE_FAILED_APPLICATION_VALIDATION,
    CERTIFICATE_SUBJECT_ISSUER_MISMATCH
};
```

An Orbix-specific error code that gives the reason why a certificate failed to validate.

IT_TLS::CertChainErrorInfo Structure

//IDL

```
struct CertChainErrorInfo
{
    short      error_depth;
    string      error_message;
    CertChainErrorCode error_reason;
    // If this field is true then the two subsequent field may be
    // examined to get more detail from the underlying toolkit if
    // required. These are non portable values and are only ever
    // likely to be used for diagnostic purposes.
    boolean    external_error_set;
    short      external_error_depth;
    long       external_error;
    string     external_error_string;
};
```

This structure is initialized with error information if a certificate chain fails the validation checks made by Orbix. Two different levels of error information are generated by the Orbix runtime:

- Error information generated by Orbix—provided by the `error_depth`, `error_message`, and `error_reason` members.
- Error information generated by an underlying third-party toolkit—provided by the `external_error_depth`, `external_error`, and `external_error_string` members.

The structure contains the following elements:

<code>error_depth</code>	A positive integer that indexes the chain depth of the certificate causing the error. Zero indicates the peer certificate.
<code>error_message</code>	A descriptive error string (possibly from the lower level toolkit).
<code>error_reason</code>	An Orbix-specific error code.
<code>external_error_set</code>	If TRUE, external error details are provided by the underlying toolkit in the member variables following this one.
<code>external_error_depth</code>	The index of the certificate that caused the error, as counted by the underlying toolkit.
<code>external_error</code>	The error code from the underlying toolkit.
<code>external_error_string</code>	A descriptive error string from the underlying toolkit.

IT_TLS::CipherSuite Type

```
typedef unsigned long CipherSuite;
```

A type that identifies a cipher suite.

Values

The following constants of `IT_TLS::CipherSuite` type are defined in `IT_TLS :`

```

TLS_RSA_WITH_NULL_MD5
TLS_RSA_WITH_NULL_SHA
TLS_RSA_EXPORT_WITH_RC4_40_MD5
TLS_RSA_WITH_RC4_128_MD5
TLS_RSA_WITH_RC4_128_SHA
TLS_RSA_EXPORT_WITH_RC2_CBC_40_MD5
TLS_RSA_WITH_IDEA_CBC_SHA
TLS_RSA_EXPORT_WITH_DES40_CBC_SHA
TLS_RSA_WITH_DES_CBC_SHA
TLS_RSA_WITH_3DES_EDE_CBC_SHA
TLS_DH_DSS_EXPORT_WITH_DES40_CBC_SHA
TLS_DH_DSS_WITH_DES_CBC_SHA
TLS_DH_DSS_WITH_3DES_EDE_CBC_SHA
TLS_DH_RSA_EXPORT_WITH_DES40_CBC_SHA
TLS_DH_RSA_WITH_DES_CBC_SHA
TLS_DH_RSA_WITH_3DES_EDE_CBC_SHA
TLS_DHE_DSS_EXPORT_WITH_DES40_CBC_SHA
TLS_DHE_DSS_WITH_DES_CBC_SHA
TLS_DHE_DSS_WITH_3DES_EDE_CBC_SHA
TLS_DHE_RSA_EXPORT_WITH_DES40_CBC_SHA
TLS_DHE_RSA_WITH_DES_CBC_SHA
TLS_DHE_RSA_WITH_3DES_EDE_CBC_SHA
TLS_DH_ANON_EXPORT_WITH_RC4_40_MD5
TLS_DH_ANON_WITH_RC4_128_MD5
TLS_DH_ANON_EXPORT_WITH_DES40_CBC_SHA
TLS_DH_ANON_WITH_DES_CBC_SHA
TLS_DH_ANON_WITH_3DES_EDE_CBC_SHA
TLS_FORTEZZA_DMS_WITH_NULL_SHA
TLS_FORTEZZA_DMS_WITH_FORTEZZA_CBC_SHA

```

IT_TLS::CipherSuiteList Sequence

```
typedef sequence<CipherSuite> CipherSuiteList;
```

A list of cipher suites.

IT_TLS::SessionCachingMode Type

```
typedef unsigned short SessionCachingMode;
```

A type that holds a session caching mode flag.

See Also IT_TLS_API::SessionCachingPolicy

IT_TLS::CertValidator Interface

IDL

```
// IDL in module IT_TLS
interface CertValidator
{
    boolean
    validate_cert_chain(
        in boolean                chain_is_valid,
        in IT_Certificate::X509CertChain cert_chain,
        in CertChainErrorInfo      error_info
    );
};
```

Description

The `CertValidator` interface is a callback interface that can be used to check the validity of a certificate chain. A developer can provide custom validation for secure associations by implementing the `CertValidator` interface, defining the `validate_cert_chain()` operation to do the checking. The developer then creates an instance of the custom `CertValidator` and registers the callback by setting an `IT_TLS_API::TLS_CERT_VALIDATOR_POLICY` policy.

`CertValidator::validate_cert_chain()`

IDL

```
boolean
validate_cert_chain(
    in boolean                chain_is_valid,
    in IT_Certificate::X509CertChain cert_chain,
    in CertChainErrorInfo      error_info
);
```

Description

Returns TRUE if the implementation of `validate_cert_chain()` considers the certificate chain to be valid; otherwise returns FALSE.

Parameters

<code>chain_is_valid</code>	TRUE if the certificate chain has passed the validity checks made automatically by the Orbix toolkit; otherwise FALSE.
<code>cert_chain</code>	The X.509 certificate chain to be checked.
<code>error_info</code>	If the certificate chain has failed the validity checks made by Orbix, this parameter provides details of the error in the certificate chain.

IT_TLS_API Overview

The `IT_TLS_API` module defines Orbix-specific security policies and an interface, `TLS`, that acts as a factory for certain kinds of security policy. This module contains the following IDL interfaces:

- `CertConstraintsPolicy` Interface
- `CertValidatorPolicy` Interface
- `MaxChainLengthPolicy` Interface
- `SessionCachingPolicy` Interface
- `TrustedCAListPolicy` Interface
- `TLS` Interface
- `TLSCredentials` Interface
- `TLSReceivedCredentials` Interface
- `TLSTargetCredentials` Interface

Associated with each of the security policies, the `IT_TLS_API` module defines the following policy type constants (of `CORBA::PolicyType` type):

```
IT_TLS_API::TLS_CERT_CONSTRAINTS_POLICY
IT_TLS_API::TLS_CERT_VALIDATOR_POLICY
IT_TLS_API::TLS_MAX_CHAIN_LENGTH_POLICY
IT_TLS_API::TLS_SESSION_CACHING_POLICY
IT_TLS_API::TLS_TRUSTED_CA_LIST_POLICY
```

The `IT_TLS_API` module also defines IDL structures that are used to supply authentication information to the `PrincipalAuthenticator::authenticate()` operation, depending on the authentication method used. The following structures are defined:

- `PasswordAuthData`
- `PEMCertChainFileAuthData`
- `PKCS12DERAuthData`
- `PKCS12FileAuthData`
- `X509CertChainAuthData`
- `PKCS11AuthData`

Associated with each of the authentication structures, the `IT_TLS_API` module defines the following authentication method constants (of `Security::AuthenticationMethod` type):

Table 20: Authentication Method Constants and Authentication Structures

Authentication Method Constant	Authentication Structure
IT_TLS_AUTH_METH_PASSWORD	PasswordAuthData
IT_TLS_AUTH_METH_CERT_CHAIN_FILE	PEMCertChainFileAuthData
IT_TLS_AUTH_METH_PKCS12_DER	PKCS12DERAuthData
IT_TLS_AUTH_METH_PKCS12_FILE	PKCS12FileAuthData
IT_TLS_AUTH_METH_CERT_CHAIN	X509CertChainAuthData
IT_TLS_AUTH_METH_PKCS11	PKCS11AuthData

IT_TLS_API::CertConstraints Sequence

```
typedef sequence<string> CertConstraints;
```

Holds a list of certificate constraints for a certificate constraints policy.

See Also IT_TLS_API::CertConstraintsPolicy

IT_TLS_API::PasswordAuthData

```
struct PasswordAuthData {
    string password;
};
```

Supplies only a password as authentication data.

Note

Reserved for future use.

IT_TLS_API::PEMCertChainFileAuthData

```
struct PEMCertChainFileAuthData {
    string    password;
    string    filename;
};
```

Supplies a password and the file name of a privacy-enhanced mail (PEM) encrypted X.509 certificate chain.

Note

Reserved for future use.

IT_TLS_API::PKCS12DERAuthData

```
struct PKCS12DERAuthData {
    string    password;
    IT_Certificate::DERData cert_chain;
};
```

Supplies a password and a certificate chain in DER format.

Note

Reserved for future use.

IT_TLS_API::PKCS12FileAuthData

```
struct PKCS12FileAuthData {
    string password;
    string filename;
};
```

Supplies a password and the file name of a PKCS#12 encrypted X.509 certificate chain. The file name should be an absolute path name.

IT_TLS_API::X509CertChainAuthData

```
struct X509CertChainAuthData {  
    IT_Certificate::DERData    private_key;  
    IT_Certificate::X509CertChain cert_chain;  
};
```

Supplies an asymmetric private key and an X.509 certificate chain.

IT_TLS_API::PKCS11AuthData

```
struct PKCS11AuthData {  
    string                provider;  
    string                slot;  
    string                pin;  
};
```

Supplies the provider name, slot number, and PIN for a smart card that is accessed through a PKCS #11 interface. In this case, the user's private key and certificate chain are stored on the smart card. The PIN is used to gain access to the smart card.

IT_TLS_API::CertConstraintsPolicy Interface

```
// IDL in module IT_TLS_API
local interface CertConstraintsPolicy : CORBA::Policy
{
    readonly attribute CertConstraints cert_constraints;
};
```

This policy defines a list of constraints to be applied to certificates. This policy type is identified by the `IT_TLS_API::TLS_CERT_CONSTRAINTS_POLICY` policy type constant.

CertConstraintsPolicy::cert_constraints Attribute

```
readonly attribute CertConstraints cert_constraints;
```

Holds the list of certificate constraints as a sequence of strings, of `IT_TLS_API::CertConstraints` type.

IT_TLS_API::CertValidatorPolicy Interface

```
// IDL in module IT_TLS_API
local interface CertValidatorPolicy : CORBA::Policy
{
    readonly attribute IT_TLS::CertValidator    cert_validator;
};
```

This policy can be used to register a customized certificate callback object, of IT_TLS :: CertValidator type. This policy type is identified by the IT_TLS_API :: **TLS_CERT_VALIDATOR_POLICY** policy type constant.

CertValidatorPolicy::cert_validator Attribute

```
readonly attribute IT_TLS::CertValidator    cert_validator;
```

Holds the customized certificate callback object, of IT_TLS :: CertValidator type

IT_TLS_API::MaxChainLengthPolicy Interface

```
// IDL in module IT_TLS_API
local interface MaxChainLengthPolicy : CORBA::Policy
{
    readonly attribute unsigned short max_chain_length;
};
```

This is a simple integer-based policy that controls the maximum certificate chain length permitted. The policy is applicable to servers and clients. This policy type is identified by the `IT_TLS_API::TLS_MAX_CHAIN_LENGTH_POLICY` policy type constant.

Note

Default is 2.

MaxChainLengthPolicy::max_chain_length Attribute

```
readonly attribute unsigned short max_chain_length;
```

Holds the maximum chain length value.

IT_TLS_API::SessionCachingPolicy Interface

```
// IDL in module IT_TLS_API
local interface SessionCachingPolicy : CORBA::Policy{
    readonly attribute unsigned short cache_mode;
};
```

An Orbix-specific policy to specify the caching mode. This policy applies to clients and servers. This policy type is identified by the `IT_TLS_API :: TLS_SESSION_CACHING_POLICY` policy type constant.

Session caching is an Orbix-specific feature that enables secure associations (for example, over TCP/IP connections) to be re-established more quickly after being closed.

To enable session caching for a client-server connection, the client must support client-side caching (`CACHE_CLIENT` or `CACHE_SERVER_AND_CLIENT` policy) and the server must support server-side caching (`CACHE_SERVER` or `CACHE_SERVER_AND_CLIENT` policy). The first time a secure association is established between the client and the server, session information is cached at both ends of the association. If the association is subsequently closed and re-established (as can happen when Automatic Connection Management is enabled), the reconnection occurs more rapidly because some of the steps in the security handshake can be skipped.

The caching optimization is effective only if both client and server are running continuously between the closing and the re-establishment of the connection. Session caching data is not stored persistently and is, therefore, not available to restarted applications.

Each TLS listener uses a separate session cache. For example, if you have two POAs with different `InvocationCredentialsPolicy` values, Orbix creates a TLS listener and session cache for each POA.

A client will not offer a cached session for reuse to a server if the session was initially created with different effective security policies.

SessionCachingPolicy::cache_mode Attribute

```
readonly attribute unsigned short cache_mode;
```

Holds the client caching mode. The default value is `IT_TLS :: CACHE_NONE`.

The values for this policy are as follows:

IT_TLS::CACHE_NONE	No caching.
IT_TLS::CACHE_SERVER	Perform server-side caching only.
IT_TLS::CACHE_CLIENT	Perform client-side caching only.
IT_TLS::CACHE_SERVER_AND_CLIENT	Perform both server-side and client-side caching.

IT_TLS_API::TLS Interface

```
// IDL in module IT_TLS_API
local interface TLS {
    SecurityLevel2::MechanismPolicy
    create_mechanism_policy(
        in IT_TLS::CipherSuiteList ciphersuite_list
    );
};
```

This interface provides helper operations for the TSL module.

TLS::create_mechanism_policy()

```
SecurityLevel2::MechanismPolicy
create_mechanism_policy(
    in IT_TLS::CipherSuiteList ciphersuite_list
);
```

Creates a SecurityLevel2 :: MechanismPolicy object from a list of ciphersuites, `ciphersuite_list`.

See AlsoIT_TLS::CipherSuite

IT_TLS_API::TLSCredentials Interface

// IDL

```
local interface TLSCredentials : SecurityLevel2::Credentials
{
    IT_Certificate::X509Cert get_x509_cert();
    IT_Certificate::X509CertChain get_x509_cert_chain_nc();
    IT_Certificate::X509CertChain get_x509_cert_chain();
};
```

This interface is the base interface for the `IT_TLS_API::TLSReceivedCredentials` and the `IT_TLS_API::TLSTargetCredentials` interfaces. The interface defines operations to retrieve an X.509 certificate chain from the credentials.

TLSCredentials::get_x509_cert()

// IDL

```
IT_Certificate::X509Cert get_x509_cert();
```

Returns a reference to the X.509 peer certificate (first certificate in the chain) contained in the credentials.

TLSCredentials::get_x509_cert_chain()

// IDL

```
IT_Certificate::X509CertChain get_x509_cert_chain();
```

Returns a copy of the X.509 certificate chain contained in the credentials. In C++ applications it is preferable to use the non-copying operation `get_x509_cert_chain_nc()` for greater efficiency.

TLSCredentials::get_x509_cert_chain_nc()

// IDL

```
IT_Certificate::X509CertChain get_x509_cert_chain_nc();
```

Returns a reference to the X.509 certificate chain contained in the credentials. In C++, the mapped function, `get_x509_cert_chain_nc()`, does not make a deep copy of the certificate sequence. The returned X.509 certificate chain can only be used while the credential from which it was obtained remains in memory.

IT_TLS_API::TLSReceivedCredentials Interface

```
local interface TLSReceivedCredentials :  
    TLSCredentials,  
    SecurityLevel2::ReceivedCredentials  
{  
};
```

The interface of an Orbix-specific received credentials object, which inherits from the standard `SecurityLevel2::ReceivedCredentials` interface. `TLSReceivedCredentials` provides extra operations (inherited from `IT_TLS_API::TLSCredentials`) to extract the X.509 certificate chain from the credentials.

An instance of a `TLSReceivedCredentials` object can be obtained by narrowing the `SecurityLevel2::ReceivedCredentials` object reference obtained from the `SecurityLevel2::Current::received_credentials` attribute.

IT_TLS_API::TLSTargetCredentials Interface

```
local interface TLSTargetCredentials :  
    TLSCredentials,  
    SecurityLevel2::TargetCredentials  
{  
};
```

The interface of an Orbix-specific target credentials object, which inherits from the standard `SecurityLevel2::TargetCredentials` interface. `TLSTargetCredentials` provides extra operations (inherited from `IT_TLS_API::TLSCredentials`) to extract the X.509 certificate chain from the credentials.

An instance of a `TLSTargetCredentials` object can be obtained by narrowing the `SecurityLevel2::TargetCredentials` object reference returned from the `SecurityLevel2::SecurityManager::get_target_credentials()` operation.

IT_TLS_API::TrustedCAListPolicy Interface

```
local interface TrustedCAListPolicy : CORBA::Policy
{
    readonly attribute IT_Certificate::X509CertList
        trusted_ca_list;
};
```

This policy specifies a list of trusted CA certificates. The policy is applicable to both servers and clients. This policy type is identified by the IT_TLS_API:: **TLS_TRUSTED_CA_LIST_POLICY** policy type constant.

TrustedCAListPolicy::trusted_ca_list Attribute

```
readonly attribute IT_Certificate::X509CertList trusted_ca_list;
```

Holds the list of trusted CA certificates.

IT_TypedEventChannelAdmin Module

Module `IT_TypedEventChannelAdmin` describes extensions to the module `CosTypedEventChannelAdmin`. It defines an interface, `TypedEventChannelFactory`, for creating or discovering `TypedEventChannel` objects.

IT_TypedEventChannelAdmin Data Types

`IT_TypedEventChannelAdmin::TypedEventChannelInfo` Structure

```
struct TypedEventChannelInfo
{
    string                                name;
    IT_EventChannelAdmin::ChannelID      id;
    string                                interface_id;
    CosTypedEventChannelAdmin::TypedEventChannel reference;
};
```

The `TypedEventChannelInfo` is the unit of information managed by the `TypedEventChannelFactory` for a given `TypedEventChannel` instance.

`IT_TypedEventChannelAdmin::TypedEventChannelInfoList` Sequence

```
typedef sequence<TypedEventChannelInfo> TypedEventChannelInfoList;
```

The `TypedEventChannelInfoList` contains a sequence of `TypedEventChannelInfo` and is the unit returned by `TypedEventChannelFactory::list_typed_channels()`.

IT_TypedEventChannelAdmin::TypedEventChannelFactory Interface

```
interface TypedEventChannelFactory : IT_MessagingAdmin::Manager
{
    CosTypedEventChannelAdmin::TypedEventChannel
    create_typed_channel(in string name,
                        out IT_EventChannelAdmin::ChannelID id)
    raises (IT_EventChannelAdmin::ChannelAlreadyExists);
    CosTypedEventChannelAdmin::TypedEventChannel
    find_typed_channel(in string name,
                     out IT_EventChannelAdmin::ChannelID id)
    raises (IT_EventChannelAdmin::ChannelNotFound);
    CosTypedEventChannelAdmin::TypedEventChannel
    find_typed_channel_by_id(in IT_EventChannelAdmin::ChannelID id,
                          out string name)
    raises (IT_EventChannelAdmin::ChannelNotFound);
    TypedEventChannelInfoList list_typed_channels();
};
```

The `TypedEventChannelFactory` interface defines operations for creating and managing typed event channels. By inheriting from the `IT_MessagingAdmin::Manager` interface, it also has the ability to gracefully shut down the event service.

`TypedEventChannelFactory::create_typed_channel()`

//IDL

```
CosTypedEventChannelAdmin::TypedEventChannel
    create_typed_channel(in string name,
                      out IT_EventChannelAdmin::ChannelID id)
    raises (IT_EventChannelAdmin::ChannelAlreadyExists);
```

Creates a new instance of a typed event channel

Parameters

name	The name of the channel to be created

<code>id</code>	The id of the created channel

TypedEventChannelFactory::find_typed_channel()

//IDL

```
CosTypedEventChannelAdmin::TypedEventChannel
  find_type_channel(in string                name,
                    out IT_EventChannelAdmin::ChannelID id)
  raises (IT_EventChannelAdmin::ChannelNotFound);
```

Returns n `TypedEventChannel` instance specified by the provided `name`.

Parameters

<code>name</code>	The name of the channel
<code>id</code>	The channel id as returned from <code>create_typed_channel()</code>

TypedEventChannelFactory::find_typed_channel_by_id()

//IDL

```
CosTypedEventChannelAdmin::TypedEventChannel
  find_typed_channel_by_id(in IT_EventChannelAdmin::ChannelID id,
                           out string                          name)
  raises (IT_EventChannelAdmin::ChannelNotFound);
```

Returns an `TypedEventChannel` instance specified by the provided `id`.

Parameters

<code>id</code>	The channel id as returned from <code>create_typed_channel()</code>
<code>name</code>	The name of the channel

TypedEventChannelFactory::list_typed_channels()

//IDL

```
TypedEventChannelInfoList list_typed_channels();
```

Return a list of the `TypedEventChannel` instances associated with the event service.

IT_WorkQueue Module

The `IT_WorkQueue` module defines the interfaces needed to create and manage user defined work queues.

IT_WorkQueue::AutomaticWorkQueue Interface

```
// IDL
interface AutomaticWorkQueue : [WorkQueue](../
it_workqueueworkqueue_interface/it_workqueueworkqueue_interface.md)
{
    readonly attribute unsigned long threads_total;
    readonly attribute unsigned long threads_working;
    attribute long [high_water_mark](#it_workqueueautomaticworkqueue-
interface);
    attribute long [low_water_mark](#it_workqueueautomaticworkqueue-
interface);
    void [shutdown](#it_workqueueautomaticworkqueue-interface)(in boolean
process_remaining_jobs);
};
```

The `AutomaticWorkQueue` interface specifies the method used to shutdown an automatic work queue. It also specifies the attributes that limit the size of the queue's thread pool and monitor thread usage.

`threads_total` Attribute

readonly attribute unsigned long threads_total;

The total number of threads in the `AutomaticWorkQueue` which can process work items. This will indicate how many threads the workqueue currently has if it has been configured to dynamically create and destroy threads as the workload changes.

`threads_working` Attribute

readonly attribute unsigned long threads_working;

Indicates the total number of threads that are busy processing work items at that point in time. This value will vary as the workload of the server changes.

`high_water_mark` Attribute

attribute long high_water_mark;

Specifies the maximum number of threads an `AutomaticWorkQueue` instance can have in its active thread pool.

low_water_mark Attribute

attribute long low_water_mark;

Specifies the minimum number of threads available to an `AutomaticWorkQueue` instance.

`AutomaticWorkQueue::shutdown()`

`void shutdown(in boolean process_remaining_jobs);`

Deactivates the queue and releases all resources associated with it.

Parameters

`process_remaining_jobs`

`TRUE` specifies that any items in the queue should be processed before shutting down the queue.

`FALSE` specifies that any items in the queue should be flushed.

IT_WorkQueue::AutomaticWorkQueueFactory Interface

```
// IDL
local interface AutomaticWorkQueueFactory
{
    [AutomaticWorkQueue](../it_workqueueautomaticworkqueue_interface/
it_workqueueautomaticworkqueue_interface.md) [create_work_queue]
(#it_workqueueautomaticworkqueuefactory-interface)(
    in long          max_size,
    in unsigned long initial_thread_count,
    in long          [high_water_mark](#it_workqueueautomaticworkqueue-
interface),
    in long          [low_water_mark](#it_workqueueautomaticworkqueue-
interface));
    [AutomaticWorkQueue](../it_workqueueautomaticworkqueue_interface/
it_workqueueautomaticworkqueue_interface.md)
[create_work_queue_with_thread_stack_size]
(#it_workqueueautomaticworkqueuefactory-interface)(
    in long          max_size,
    in unsigned long initial_thread_count,
    in long          [high_water_mark](#it_workqueueautomaticworkqueue-
interface),
    in long          [low_water_mark](#it_workqueueautomaticworkqueue-
interface),
    in long          thread_stack_size);
};
```

The `AutomaticWorkQueueFactory` interface specifies two methods for obtaining an [AutomaticWorkQueue](#).

The `AutomaticWorkQueueFactory` is obtained by calling

```
resolve_initial_references("IT-AutomaticWorkQueueFactory").
```

`AutomaticWorkQueueFactory::create_work_queue()`

[AutomaticWorkQueue](#) `create_work_queue()`

```

        in long          max_size,
        in unsigned long initial_thread_count,
        in long          [high_water_mark](#it_workqueueautomaticworkqueue-
interface),
        in long          [low_water_mark](#it_workqueueautomaticworkqueue-
interface));

```

Creates an [AutomaticWorkQueue](#).

Parameters

<code>max_size</code>	The maximum number of items the queue can hold.
<code>initial_thread_count</code>	The initial number of threads the queue has available for processing work items.
<code>high_water_mark</code>	The maximum number of threads the queue can generate to process work items.
<code>low_water_mark</code>	The minimum number of threads the queue can have available to process work items.

`AutomaticWorkQueueFactory::create_work_queue_with_thread_stack_size()`

[AutomaticWorkQueue](#) `create_work_queue_with_thread_stack_size(`

```

        in long          max_size,
        in unsigned long initial_thread_count,
        in long          [high_water_mark](#it_workqueueautomaticworkqueue-
interface),
        in long          [low_water_mark](#it_workqueueautomaticworkqueue-
interface),
        in long          thread_stack_size);

```

Creates an [AutomaticWorkQueue](#) and specify the size of the thread stack.

Parameters

<code>max_size</code>	The maximum number of items the queue can hold.

<code>initial_thread_count</code>	The initial number of threads the queue has available for processing work items.
<code>high_water_mark</code>	The maximum number of threads the queue can generate to process work items.
<code>low_water_mark</code>	The minimum number of threads the queue can have available to process work items.
<code>thread_stack_size</code>	The size, in bytes, of the thread stack used by the queue.

IT_WorkQueue::ManualWorkQueue Interface

```
// IDL
interface ManualWorkQueue : [WorkQueue](../it_workqueueworkqueue_interface/
it_workqueueworkqueue_interface.md)
{
    boolean [dequeue](#it_workqueuemanualworkqueue-interface)(out [WorkItem]
(..it_workqueueworkitem_interface/it_workqueueworkitem_interface.md) work,
in long timeout);
    boolean [do_work](#it_workqueuemanualworkqueue-interface)(in long
number_of_jobs, in long timeout);
    void [shutdown](#it_workqueuemanualworkqueue-interface)(in boolean
process_remaining_jobs);
};
```

The `ManualWorkQueue` interface specifies the methods for managing a manual work queue.

`ManualWorkQueue::dequeue()`

`boolean dequeue(out WorkItem work, in long timeout);`

Removes a single [WorkItem](#) from the head of the queue. You must explicitly call `execute()` on the [WorkItem](#) to process the request using this method.

Parameters

<code>work</code>	The WorkItem returned by <code>dequeue()</code> . If the call is unsuccessful, <code>work</code> will be <code>NULL</code> .
<code>timeout</code>	The maximum amount of time the call will block before returning <code>NULL</code> .

`ManualWorkQueue::do_work()`

`boolean do_work(in long number_of_jobs, in long timeout);`

Removes the specified number of requests from the queue and processes them. If there are less than the specified number of items on the queue, `do_work()` will block for a specified amount of time to wait for items to be queued.

Parameters

<code>number_of_jobs</code>	The maximum number of items to process.
<code>timeout</code>	The maximum amount of time the call will block before returning.

ManualWorkQueue::shutdown()

void shutdown(in boolean process_remaining_jobs);

Deactivates the queue and releases all resources associated with it.

Parameters

`process_remaining_jobs`

`TRUE` specifies that any items in the queue should be processed before shutting down the queue.

`FALSE` specifies that any items in the queue should be flushed.

IT_WorkQueue::ManualWorkQueueFactory Interface

```
// IDL
local interface ManualWorkQueueFactory
{
    [ManualWorkQueue](../it_workqueuemanualworkqueue_interface/
it_workqueuemanualworkqueue_interface.md) [create_work_queue]
(#it_workqueuemanualworkqueuefactory-interface)(in long max_size);
};
```

Defines the method used to obtain a [ManualWorkQueue](#). The `ManualWorkQueueFactory` is obtained by calling `resolve_initial_references("IT_ManualWorkQueueFactory")`.

`ManualWorkQueueFactory::create_work_queue()`

[ManualWorkQueue](#) `create_work_queue(in long max_size);`

Creates a [ManualWorkQueue](#) object.

Parameters

`max_size`

Specifies the maximum number of work items the queue can hold.

IT_WorkQueue::WorkItem Interface

```
// IDL
enum WorkItemStatus
{
    STOP_WORKING,
    CONTINUE_WORKING
};
interface WorkItem
{
    WorkItemStatus [execute()](#it_workqueueworkitem-interface);
    void [destroy()](#portableserverpoa-interface);
};
```

The `WorkItem` interface defines requests placed on the work queue. For most purposes, you do not need to implement this interface. The ORB will place requests on the queue and execute them under the covers. You can implement this interface if you want to have additional processing done by the work queues thread pool.

`WorkItem::execute()`

`execute();`

Processes the request encapsulated in the [WorkItem](#) object. The only times you need to call this method, is when using a [ManualWorkQueue](#) and removing items from the queue using [dequeue\(\)](#). Also, if you have made a custom [WorkItem](#), you will need to implement this method.

`WorkItem::Destroy`

`void destroy();`

Releases the resources for the current [WorkItem](#) object.

IT_WorkQueue::WorkQueue Interface

```
// IDL
interface WorkQueue
{
    readonly attribute long [max_size](#it_workqueueworkqueue-interface);
    readonly attribute unsigned long count;
    boolean [enqueue](#it_workqueueworkqueue-interface)(in [WorkItem](../it_workqueueworkitem_interface/it_workqueueworkitem_interface.md) work, in long timeout);
    boolean [enqueue_immediate](#it_workqueueworkqueue-interface)(in [WorkItem](../it_workqueueworkitem_interface/it_workqueueworkitem_interface.md) work);
    boolean [is_full](#it_workqueueworkqueue-interface)();
    boolean [is_empty](#it_workqueueworkqueue-interface)();
    boolean [activate](#it_workqueueworkqueue-interface)();
    boolean [deactivate](#it_workqueueworkqueue-interface)();
    void [flush](#it_workqueueworkqueue-interface)();
    boolean [owns_current_thread](#it_workqueueworkqueue-interface)();
};
```

The `WorkQueue` interface defines the base functionality for the [ManualWorkQueue](#) interface and the [AutomaticWorkQueue](#) interface.

`max_size` attribute

readonly attribute long `max_size`;

Specifies the maximum number of [WorkItems](#) a queue can hold before it is full.

`WorkQueue::enqueue()`

boolean `enqueue`(in [WorkItem](#) `work`, in long `timeout`);

Places work items into the queue for processing. For CORBA requests, the ORB takes care of placing items into the queue. For custom work items that you wish to handle in the queue, you must explicitly place them on the queue.

Parameters

<code>work</code>	The WorkItem to be placed into the queue.

<code>timeout</code>	The time in seconds that the item will be valid on the queue.

`WorkQueue::enqueue_immediate()`

`boolean enqueue_immediate()`

Returns `TRUE` and places the work item onto the queue for processing if the work queue is not full and the number of threads is below the high water mark. Effectively, this causes the work item to be processed immediately with out waiting for any current thread to complete. Returns `FALSE` if the work item cannot immediately placed on the work queue.

Parameters

`work`

The [WorkItem](#) to be placed into the queue.

`WorkQueue::is_full()`

`boolean is_full();`

Returns `TRUE` if the [WorkQueue](#) has reached `max_size`. Returns `FALSE` otherwise.

`WorkQueue::is_empty()`

`boolean is_empty();`

Returns `TRUE` if the [WorkQueue](#) is empty. Returns `FALSE` otherwise.

`WorkQueue::activate()`

`boolean activate();`

Puts the queue into a state where it is ready to receive and process work requests.

`WorkQueue::deactivate()`

`boolean deactivate();`

Puts the queue into a state where it will no longer process work requests.

`WorkQueue::owns_current_thread()`

`boolean owns_current_thread();`

Returns `TRUE` if the thread making the call is managed by the work queue.

WorkQueue::flush()

void flush();

Removes all of the items from the queue without processing them.

IT_WorkQueue::WorkQueuePolicy Interface

```
// IDL
local interface WorkQueuePolicy : CORBA::Policy
{
    readonly attribute [WorkQueue](../it_workqueueworkqueue_interface/
it_workqueueworkqueue_interface.md) work_queue;
};
```

The `WorkPolicy` interface is the object you pass to `create_policy()` when associating you [WorkQueue](#) with a POA.

IT_ZIOP

The IT_ZIOP Module

Defines interfaces, exceptions, types and values for the Rocket Software ZIOP Compression plug-in.

Description

This plug-in provides optional compression of all types of GIOP messages through a message-level interceptor that is installed between the GIOP interceptor and the transport interceptor (that is, IIOP, IIOP_TLS, etc). This module defines the plug-in interfaces that register compression algorithms, define the ZIOP IOR Component, and define the Policies associated with compression.

IT_ZIOP::CompressionException

Thrown when an error occurs during a compress or decompress operation.

Fields

reason

Exception details.

IT_ZIOP::FactoryAlreadyRegistered

Thrown if a `CompressorFactory` with the same `CompressorId` is already registered with the `CompressionManager`.

IT_ZIOP::UnknownCompressorId

Thrown if a `CompressorId` is not known.

IT_ZIOP::CompressorId

Defines the `CompressorId` type.

Description

The `CompressorId` is a unique ID that identifies a particular compression algorithm. Three compression algorithms are defined by the standard ZIOP plug-in:

- `gzip` —for which ID = 1.
- `pkzip` —for which ID = 2.
- `bzip2` —for which ID = 3.

IT_ZIOP::CompressorFactorySeq

A list of `CompressorFactory` objects.

`IT_ZIOP::TAG_IONA_ZIOP_COMPONENT`

The ZIOP IOR component tag.

Description

Identifies the ZIOP IOR component, which contains a `ComponentId`.

`IT_ZIOP::COMPRESSION_ENABLING_POLICY_ID`

The policy ID for the `IT_ZIOP::CompressionEnablingPolicy` policy.

Description

This constant can be passed as the first argument to the `CORBA::ORB::create_policy()` operation to create a `CompressionEnablingPolicy` instance.

`IT_ZIOP::COMPRESSOR_ID_POLICY_ID`

The policy ID for the `IT_ZIOP::CompressorIdPolicy` policy.

Description

This constant can be passed as the first argument to the `CORBA::ORB::create_policy()` operation to create a `CompressorIdPolicy` instance.

IT_ZIOP::Compressor

Implements a compression algorithm.

Description

The key operations of the `Compressor` interface are the `compress()` and `decompress()` operations. Implementing these operations is somewhat complicated by the use of segmented buffers (of `IT_Buffer::Buffer` type).

To give you some idea of how to manipulate a segmented buffer, here is an outline of the steps you would perform to iterate over the bytes in a pre-existing buffer:

- Call `IT_Buffer::Buffer::rewind()` to reset the buffer to the first segment.
- Call `IT_Buffer::Buffer::next_segment()` to get a reference to the first segment in the buffer (of `IT_Buffer::Segment` type).
- Iterate over each byte in the segment (bytes within a segment are contiguous). The first byte of the segment is given by `IT_Buffer::Segment::data + IT_Buffer::Segment::offset`. The last byte of the segment is given by `IT_Buffer::Segment::data + IT_Buffer::Segment::offset + IT_Buffer::Segment::length - 1`.

- Move on to the next segment by calling `IT_Buffer::Buffer::next_segment()`.
- When the last segment is reached, `next_segment()` returns a `null` pointer.

The `Compressor` object simply performs compression/decompression unconditionally. The logic that determines whether or not it is appropriate to compress/decompress a particular message (based on the effective compression policies) is already built-in to the ZIOP plug-in.

`IT_ZIOP::Compressor::compressor_factory`

The `IT_ZIOP::CompressorFactory` associated with this `Compressor`.

`IT_ZIOP::Compressor::compression_level`

The implementation- and algorithm-specific compression level associated with this `Compressor`.

`IT_ZIOP::Compressor::compress()`

Compresses data from the source `Buffer` into the target `Buffer`.

Parameters

`source`

An `IT_Buffer::Buffer` object, which contains the data to compress.

`target`

A non-nil `IT_Buffer::Buffer` object, which should be empty.

Exceptions

`IT_ZIOP::CompressionException`

Raised if an error occurs during compression.

`IT_ZIOP::Compressor::decompress()`

Operation that decompresses data from the source `Buffer` into the target `Buffer`.

Parameters

`source`

An `IT_Buffer::Buffer` object, which contains the data to decompress.

`target`

A non-nil `IT_Buffer::Buffer` object, which should be empty.

Exceptions

`IT_ZIOP::CompressionException`

Raised if an error occurs during decompression.

IT_ZIOP::CompressorFactory

A factory for `Compressor` instances with a particular implementation- and algorithm-specific compression level.

Description

IT_ZIOP::CompressorFactory::compressor_id

The `CompressorId` associated with this `CompressorFactory`.

Description

The compressor ID is a unique identifier for a particular compression algorithm.

IT_ZIOP::CompressorFactory::compressed_bytes

The total number of compressed bytes read and written by IT_ZIOP::Compressor instances created by this `CompressorFactory`.

Description

That is, this value represents the sum of the lengths of all the `target` arguments of `IT_ZIOP::Compressor::compress()` and all of the `source` arguments of `IT_ZIOP::Compressor::decompress()`.

IT_ZIOP::CompressorFactory::uncompressed_bytes

The total number of uncompressed bytes read and written by IT_ZIOP::Compressor instances created by this `CompressorFactory`.

Description

That is, this value represents the sum of the lengths of all the `source` arguments of `IT_ZIOP::Compressor::compress()` and all of the `target` arguments of `IT_ZIOP::Compressor::decompress()`.

IT_ZIOP::CompressorFactory::average_compression

The average compression ratio achieved by the IT_ZIOP::Compressors instances created by this `CompressorFactory`.

Description

The compression ratio is defined as the number of compressed bytes divided by the number of uncompressed bytes (usually a value between 0 and 1).

IT_ZIOP::CompressorFactory::get_compressor()

Creates a new `Compressor` instance or else returns a reference to a pre-existing `Compressor` instance with the given compression level.

Returns A new or pre-existing `Compressor` instance that has the same compressor ID as the `CompressorFactory` and a compression level specified by the `compression_level` parameter.

Parameters

`compression_level`

An arbitrary parameter that affects the compression algorithm. The interpretation of the `compression_level` parameter is specific to each `Compressor`. In some cases, it might be ignored.

`IT_ZIOP::CompressorFactory::add_sample()`

Add a sample of compressed and uncompressed bytes.

Description

Called internally to record the volumes of compressed data and uncompressed data passing through the `Compressor`.

Parameters

`compressed_bytes`

The length of the compressed data from the most recently compressed/decompressed message.

`uncompressed_bytes`

The length of the uncompressed data from the most recently compressed/decompressed message.

IT_ZIOP::CompressionManager

Per-ORB interface to register and unregister `IT_ZIOP::CompressorFactory` objects.

Description

To obtain a reference to the `CompressionManager` instance, call the `CORBA::ORB::resolve_initial_references()` operation with the `IT_CompressionManager` initial reference string as its argument.

`IT_ZIOP::CompressionManager::register_factory()`

Register a new `CompressorFactory` instance.

C++ implementation

For example, in C++ you can register a compressor factory as follows:

```
// C++
IT_ZIOP::CompressionManager_var compression_manager;
CORBA::Object_var objref =
orb->resolve_initial_references("IT_CompressionManager");
if (CORBA::is_nil(objref))
{
cerr << "Could not resolve reference" << endl;
return 1;
}
compression_manager = IT_ZIOP::CompressionManager::_narrow(objref);
if (CORBA::is_nil(compression_manager))
{
cerr << "Could not _narrow object to type IT_ZIOP::CompressionManager" <<
endl;
return 1;
}
cout << "Registering DemoCompressorFactory with Compression Manager" << endl;
compression_manager->register_factory(new DemoCompressorFactory(100));
```

Parameters

compressor_factory

The compressor factory to register.

Exceptions

IT_ZIOP::FactoryAlreadyRegistered

Raised if a factory with the same compressor ID has already been registered with this

CompressionManager.

IT_ZIOP::CompressionManager::unregister_factory()

Unregister a IT_ZIOP::CompressorFactory with the given CompressorId from the CompressionManager.

Parameters

compressor_id

The compressor ID that identifies the factory to unregister.

Exceptions

IT_ZIOP::UnknownCompressorId

Raised if no factory with the specified compressor ID is registered with the `CompressionManager`.

`IT_ZIOP::CompressionManager::get_factory()`

Retrieve an `IT_ZIOP::CompressorFactory` with the given `CompressorId` from the `CompressionManager`.

Returns A reference to the `CompressorFactory` instance with the specified compressor ID.

Parameters

`compressor_id`

The compressor ID that identifies the factory to retrieve.

Exceptions

`IT_ZIOP::UnknownCompressorId`

Raised if no factory with the specified compressor ID is registered with the `CompressionManager`.

`IT_ZIOP::CompressionManager::get_compressor()`

Creates a new, or returns a pre-existing, `IT_ZIOP::Compressor` instance.

Returns A `Compressor` instance with the specified compressor ID and compression level.

Parameters

`compressor_id`

The compressor ID of the `Compressor` instance to retrieve.

`compression_level`

The compressor level of the `Compressor` instance to retrieve.

Exceptions

`IT_ZIOP::UnknownCompressorId`

Raised if no factory with the specified compressor ID is registered with the `CompressionManager`.

`IT_ZIOP::CompressionManager::get_factories()`

Returns a list of all the registered `CompressorFactory` instances.

Returns A sequence of `IT_ZIOP::CompressorFactory` object references.

IT_ZIOP::CompressionComponent

The ZIOP IOR Component. Has a `CompressorId` attribute that indicates the compression algorithm supported by the server side.

IT_ZIOP::CompressionComponent::compressor_id

The compressor ID value from the ZIOP IOR component.

IT_ZIOP::CompressionComponentFactory

The factory for ZIOP IOR components.

IT_ZIOP::CompressionComponentFactory::get_compression_component()

Creates ZIOP IOR components for inclusion in server-generated IORs.

Returns A new (or flyweighted) IT_ZIOP::CompressionComponent object.

Parameters

compressor_id

The compressor ID to embed in the ZIOP IOR component.

IT_ZIOP::CompressionEnablingPolicy

Policy to enable compression using the ZIOP plug-in.

Description

This policy has a single boolean attribute, indicating if compression is enabled or not.

When the compression enabling policy is set on the *server side*, the server embeds a ZIOP component in the IORs it generates. The presence of a ZIOP component in the IOR indicates to clients that the server is capable of receiving compressed messages. You can set server-side policies at any of the following levels:

- ORB.
- POA.

When the compression enabling policy is set on the *client side*, the client checks IORs for the presence of a ZIOP component. If a ZIOP component is present, the client will attempt to send compressed messages to the server. You can set client-side policies at any of the following levels:

- ORB.
- Thread.
- Object (client proxy).

IT_ZIOP::CompressionEnablingPolicy::compression_enabled

Indicates whether this policy enables (`true`) or disables (`false`) compression.

IT_ZIOP::CompressorIdPolicy

Policy to specify the compressor ID.

Description

The compressor ID indicates which compression algorithm to use (internally, the compressor ID selects a particular implementation of the `IT_ZIOP::Compressor` interface).

The compressor ID policy can *only* be set on the server side. The server embeds the compressor ID in a ZIOP component in the IORs that it generates. You can set server-side policies at any of the following levels:

- ORB.
- POA.

IT_ZIOP::CompressorIdPolicy::compressor_id

Returns the value of the compressor ID represented by this policy instance.

Messaging Overview

CORBA provides synchronous and deferred synchronous modes of invocations. The Messaging module provides the additional asynchronous mode, also known here as *Asynchronous Method Invocation (AMI)*. The Messaging module includes the following base classes, value types, policy classes, common data structures, and constants:

Table 21: The Messaging Module

Base Classes and Value Types	Common Structures and Constants	QoS Policy Classes
ExceptionHolder ReplyHandler	INVOCATION_POLICIES RebindMode RoutingType RoutingTypeRange SyncScope TAG_POLICIES	RebindPolicy RoutingPolicy SyncScopePolicy

With synchronous invocations, the client program, or thread, blocks when a remote invocation is made and waits until the results arrive. With deferred synchronous invocations, the client thread continues processing, subsequently polling to see if results are available. Within the CORBA module, the deferred synchronous model is only available when using the Dynamic Invocation Interface.

Many applications require some way of managing remote requests within an asynchronous, event-driven environment in which callbacks are invoked to handle events. Sophisticated applications often need to manage several activities simultaneously, making overlapping remote requests to many objects. This can be achieved using a separate thread for each invocation, but the use of threads considerably raises the application's complexity and the probability of programming errors. The use of threads also creates a resource and synchronization problem in addition to the memory management problem inherent in asynchronous communications.

Messaging provides the *callback model* in which the client passed a callback object reference as part of the invocation. When the reply is available, that callback object is invoked with the data of the reply. The callback model uses a ReplyHandler, which is a CORBA object, implemented by the client application. The ReplyHandler is passed to an asynchronous method invocation. The ReplyHandler is invoked when the reply to that request is available.

The Messaging module also provides a QoS property to help obtain asynchronous behavior. The Messaging QoS includes some CORBA `::Policy` derived interfaces for client-side policies to control the behavior of requests and replies. Note however that QoS for method invocations applies to both asynchronous and synchronous invocations. See also the discussion [Quality of Service Framework](#).

The following constants and types are available for messaging.

Messaging::INVOCATION_POLICIES Constant

IT_ART_API IT_NAMESPACE_STATIC

```
const CORBA::ULong INVOCATION_POLICIES;
```

A service context containing a sequence of quality of service policies in effect for the invocation. The quality of service framework abstract model includes this mechanism for transporting Policy values as part of interoperable object references and within requests.

Messaging::RebindMode Type

typedef CORBA::Short RebindMode;

```
typedef      CORBA::Short_out RebindMode_out;
IT_ART_API IT_NAMESPACE_STATIC CORBA::TypeCode_ptr _tc_RebindMode;
```

This describes the level of transparent rebinding that may occur during the course of an invocation on an object. Values of type `RebindMode` are used in conjunction with a `RebindPolicy`. All non-negative values are reserved for use in OMG specifications and include the following constants:

TRANSPAR ENT	Allows the ORB to silently handle object-forwarding and necessary reconnection during the course of making a remote request.
NO_REBIND	Allows the ORB to silently handle reopening of closed connections while making a remote request, but prevents any transparent object-forwarding that would cause a change in client-visible effective QoS policies. When the <code>RebindPolicy</code> has this mode in effect, only explicit rebinding is allowed by calling <code>CORBA :: Object :: _validate_connection()</code> .

<code>NO_RECONNECT</code>	Prevents the ORB from silently handling object-forwards or the reopening of closed connections. When the <code>RebindPolicy</code> has this mode in effect, only explicit rebinding is allowed by calling <code>CORBA::Object::_validate_connection()</code> .

Any negative value for a `RebindMode` is considered a vendor extension.

See Also `Messaging::RebindPolicy`

`Messaging::RoutingType` Type

`typedef CORBA::Short RoutingType;`

```
typedef CORBA::Short_out RoutingType_out;
IT_ART_API IT_NAMESPACE_STATIC CORBA::TypeCode_ptr _tc_RoutingType;
```

Describes the type of routing to be used for invocations on an object reference. `RoutingType` values are used in conjunction with a `RoutingPolicy`. All non-negative values are reserved for use in OMG specifications and include the following constants:

<code>ROUTE_NONE</code>	Synchronous or deferred synchronous delivery is used. No routers will be used to aid in the delivery of the request.
<code>ROUTE_FORWARD</code>	Asynchronous delivery is used. The request is made through the use of a router and not delivered directly to the target by the client ORB.
<code>ROUTE_STORE_AND_FORWARD</code>	Asynchronous TII is used. The request is made through the use of a router that persistently stores the request before attempting delivery.

Any negative value for a `RoutingType` is considered a vendor extension.

See Also `Messaging::RoutingTypeRange`

`Messaging::RoutingTypeRange` Structure

`struct RoutingTypeRange;`

```
typedef ITCxxFixLenConstr_var< RoutingTypeRange> RoutingTypeRange_var;
typedef RoutingTypeRange& RoutingTypeRange_out;
struct RoutingTypeRange {
    typedef RoutingTypeRange_var _var_type;
    ::Messaging::RoutingType min;
    ::Messaging::RoutingType max;
};
IT_ART_API IT_NAMESPACE_STATIC CORBA::TypeCode_ptr _tc_RoutingTypeRange;
```

This structure describes a range of routing types. It is invalid for the minimum `RoutingType` to be greater than the maximum `RoutingType`.

`Messaging::SyncScope` Type

```
typedef CORBA::Short SyncScope;
```

```
typedef          CORBA::Short_out SyncScope_out;
IT_ART_API IT_NAMESPACE_STATIC CORBA::TypeCode_ptr _tc_SyncScope;
```

Describes the level of synchronization for a request with respect to the target. Values of type `SyncScope` are used in conjunction with a `SyncScopePolicy` to control the behavior of one way operations. All non-negative values are reserved for use in OMG specifications. Any negative value of `SyncScope` is considered a vendor extension. Valid values include:

<code>SYNC_NONE</code>	This is equivalent to one allowable interpretation of CORBA 2.2 oneway operations. The ORB returns control to the client (that is, returns from the method invocation) before passing the request message to the transport protocol. The client is guaranteed not to block. You cannot do location-forwarding with this level of synchronization because no reply is returned from the server.

SYNC_WITH_TRANSPORT This is equivalent to one allowable interpretation of CORBA 2.2 oneway operations. The ORB returns control to the client only after the transport has accepted the request message. This gives no guarantee that the request will be delivered, but in conjunction with knowledge of the transport it may provide the client with enough assurance.

For example, for a direct message over TCP, **SYNC_WITH_TRANSPORT** is not a stronger guarantee than **SYNC_NONE**. However, for a store and forward transport, this QoS provides a high level of reliability. You cannot do location-forwarding with this level of synchronization because no reply is returned from the server.

SYNC_WITH_SERVER The server-side ORB shall send a reply before invoking the target implementation. If a reply of **NO_EXCEPTION** is sent, any necessary location-forwarding has already occurred. Upon receipt of this reply, the client-side ORB returns control to the client application. This form of guarantee is useful where the reliability of the network is substantially lower than that of the server. The client blocks until all location-forwarding has been completed. For a server using a POA, the reply would be sent after invoking any **ServantManager**, but before delivering the request to the target Servant.

SYNC_WITH_TARGET Equivalent to a synchronous, non-oneway operation in CORBA 2.2. The server-side ORB shall only send the reply message after the target has completed the invoked operation. Note that any **LOCATION_FORWARD** reply will already have been sent prior to invoking the target and that a **SYSTEM_EXCEPTION** reply may be sent at anytime (depending on the semantics of the exception). Even though it was declared oneway, the operation actually has the behavior of a synchronous operation. This form of synchronization guarantees that the client knows that the target has seen and acted upon a request. the OTS can only be used with this highest level of synchronization. Any operations invoked with lesser synchronization precludes the target from participating in the client's current transaction.

See Also `Messaging::SyncScopePolicy`

`Messaging::TAG_POLICIES` Constant

`IT_ART_API IT_NAMESPACE_STATIC const CORBA::ULong TAG_POLICIES;`

A profile component containing the sequence of quality of service policies exported with the object reference by an object adapter. The quality of service framework abstract model includes this mechanism for transporting policy values as part of interoperable object references and within requests.

See Also `Messaging::RoutingPolicy`

Messaging::ExceptionHolder Value Type

The messaging callback model uses an `ExceptionHolder` to deliver exceptions. Because the `ReplyHandler` implements an IDL interface, all arguments passed to its operations must be defined in IDL also. However, exceptions cannot be passed as arguments to operations, but are only raised as part of a reply. An `ExceptionHolder` value is created to encapsulate the identity and contents of the exception that might be raised. An instance of this `ExceptionHolder` is passed as the argument to the `ReplyHandler` operation that indicates an exception was raised by the target. In addition to its exception state, the `ExceptionHolder` also has operations that raise the returned exception, so the `ReplyHandler` implementation can have the returned exception re-raised within its own context.

AMI operations do not raise user exceptions. Rather, user exceptions are passed to the implemented type specific `ReplyHandler`. If an AMI operation raises a system exception with a completion status of `COMPLETED_NO`, the request has not been made. This clearly distinguishes exceptions raised by the server (which are returned via the `ReplyHandler`) from the local exceptions that caused the AMI to fail.

The `ExceptionHolder` value class implementation is provided by the ORB. For each interface, a type specific `ExceptionHolder` value is generated by the IDL compiler. This `ExceptionHolder` is implemented by the ORB and passed to an application using the callback model when exception replies are returned from the target. See the *CORBA Programmer's Guide* for more on the generated value types and operations.

The code is as follows:


```

...
class IT_ART_API ExceptionHolder : public virtual CORBA::ValueBase
{
public:
    virtual CORBA::Any* [get_exception()](#messagingexceptionholder-value-
type) = 0;
    virtual CORBA::Any* [get_exception_with_list](#messagingexceptionholder-
value-type)(
        ::CORBA::ExceptionList_ptr exc_list
    ) = 0;
    typedef ITCxxUFixedSeq< CORBA::Octet > [_marshaled_exception_seq]
(#messagingexceptionholder-value-type);
    ...
    static ExceptionHolder* [_downcast](#messagingexceptionholder-value-type)
(
    CORBA::ValueBase* _val
);
    ...
protected:
    [ExceptionHolder()](#messagingexceptionholder-value-type);
    [ExceptionHolder](#messagingexceptionholder-value-type)(
        CORBA::Boolean _itfld_is_system_exception,
        CORBA::Boolean _itfld_byte_order,
        const ITCxxUFixedSeq< CORBA::Octet > & _itfld_marshaled_exception
    );
    virtual [~ExceptionHolder()](#messagingexceptionholder-value-type);
    virtual CORBA::Boolean [is_system_exception()](#messagingexceptionholder-
value-type) const = 0;
    virtual void [is_system_exception](#messagingexceptionholder-value-type)(
        CORBA::Boolean
    ) = 0;
    virtual CORBA::Boolean [byte_order()](#messagingexceptionholder-value-
type) const = 0;
    virtual void [byte_order](#messagingexceptionholder-value-type)(
        CORBA::Boolean
    ) = 0;
    virtual void [marshaled_exception](#messagingexceptionholder-value-type)(
        const _marshaled_exception_seq&
    ) = 0;
    virtual const _marshaled_exception_seq &
        [marshaled_exception()](#messagingexceptionholder-value-type) const =
0;
    virtual _marshaled_exception_seq & [marshaled_exception()]
(#messagingexceptionholder-value-type) = 0;
private:

```

```
...
};
```

EnhancementThe `ExceptionHolder` class is not compliant with the CORBA Messaging specification.

`ExceptionHolder::byte_order()`

`virtual CORBA::Boolean byte_order() const = 0;`

Returns the byte order for the exception.

`virtual void byte_order(`

```
    CORBA::Boolean
) = 0;
```

Sets the byte order for the exception.

`ExceptionHolder::_downcast()`

`static ExceptionHolder* _downcast(`

```
    CORBA::ValueBase* _val
);
```

Returns a pointer to the `ExceptionHolder` type for a derived class. Each value type class provides `_downcast()` as a portable way for applications to cast down the C++ inheritance hierarchy.

Parameters

`_val`

Pointer to the value type class to be downcast.

- If the value type instance pointed to by the argument is an instance of the value type class being downcast to, a pointer to the downcast-to class type is returned.
- If the value type instance pointed to by the argument is not an instance of the value type class being downcast to, a null pointer is returned.
- If a null pointer is passed to `_downcast()`, it returns a null pointer.

This is especially required after an invocation of `_copy_value()`.

EnhancementOrbix enhancement.

See AlsoCORBA::ValueBase::_copy_value()

ExceptionHolder::ExceptionHolder() Constructors

ExceptionHolder();

ExceptionHolder(

```
CORBA::Boolean _itfld_is_system_exception,
CORBA::Boolean _itfld_byte_order,
const ITCxxUFixedSeq< CORBA::Octet > & _itfld_marshaled_exception
);
```

Constructors for the `ExceptionHolder`.

EnhancementOrbix enhancement.

ExceptionHolder::~ExceptionHolder() Destructor

virtual ~ExceptionHolder();

The destructor for the `ExceptionHolder`.

EnhancementOrbix enhancement.

ExceptionHolder::get_exception()

virtual CORBA::Any* get_exception() = 0;

Returns the exception.

See AlsoMessaging::ExceptionHolder::get_exception_with_list()

EnhancementOrbix enhancement.

ExceptionHolder::get_exception_with_list()

virtual CORBA::Any* get_exception_with_list(

```
::CORBA::ExceptionList_ptr exc_list
) = 0;
```

Returns a list of exceptions.

EnhancementOrbix enhancement.

See AlsoMessaging::ExceptionHolder::get_exception()

ExceptionHolder::is_system_exception()

virtual CORBA::Boolean is_system_exception() const = 0;

virtual void is_system_exception(

```

CORBA::Boolean
) = 0;

```

ExceptionHolder::_it_demarshal_value()

```

virtual void _it_demarshal_value(
    CORBA::IT_InStream_ptr _is,
    CORBA::ORB_ptr _orb
);

```

Note

For internal use only.

ExceptionHolder::_it_get_fw_type_id()

```

static const IT_FWString& _it_get_fw_type_id();

```

Note

For internal use only.

ExceptionHolder::_it_get_safe_bases()

```

const char** _it_get_safe_bases() const;

```

Note

For internal use only.

ExceptionHolder::_it_marshal_value()

```

virtual void _it_marshal_value(

```

```

    CORBA::IT_OutStream_ptr _os,
    CORBA::ORB_ptr _orb
);

```

Note

For internal use only.

ExceptionHolder::_it_type()

virtual CORBA::TypeCode_ptr _it_type() const;

 Note

For internal use only.

ExceptionHolder::_local_narrow()

virtual void* _local_narrow(

```
    const char* tag
);
```

 Note

For internal use only.

ExceptionHolder::marshaled_exception()

EnhancementOrbix enhancement.

ExceptionHolder::marshaled_exception_seq Sequence

typedef ITCxxUFixedSeq< CORBA::Octet > _marshaled_exception_seq;

EnhancementOrbix enhancement.

Messaging::RebindPolicy Class

The `RebindPolicy` is a client-side QoS policy that specifies whether or not the ORB is allowed to transparently relocate the target corresponding to an object reference. The default `RebindPolicy` supports this transparent rebind.

Rebinding means changing the client-visible QoS as a result of replacing the IOR profile used by a client's object reference with a new IOR profile. *Transparent rebinding* is when this happens without notice to the client application.

If your application has rigorous QoS requirements, transparent rebinding can cause problems. For instance, unexpected errors may occur if your application sets its QoS policies appropriately for an object reference, and then the ORB transparently changes the application's assumptions about that reference by obtaining a new IOR. Your applications can prevent the ORB from silently changing the IOR Profile and therefore the server-side QoS that you have assumed. A more rigorous value of this policy even precludes the ORB from silently closing and opening connections such as when IIOP is being used.

`RebindPolicy` is a local object derived from `CORBA::Policy`.

```

class RebindPolicy;
typedef RebindPolicy* RebindPolicy_ptr;
typedef ITCxxObjRef_var< RebindPolicy_ptr, RebindPolicy, ITCxxIntfAlloc<
RebindPolicy_ptr, RebindPolicy> > RebindPolicy_var;
typedef ITCxxObjRef_out< RebindPolicy_ptr, RebindPolicy, ITCxxIntfAlloc<
RebindPolicy_ptr, RebindPolicy> > RebindPolicy_out;
...
IT_ART_API IT_NAMESPACE_STATIC CORBA::TypeCode_ptr _tc_RebindPolicy;
class IT_ART_API RebindPolicy : public virtual ::CORBA::Policy {
public:
    typedef Messaging::RebindPolicy_ptr _ptr_type;
    typedef Messaging::RebindPolicy_var _var_type;
    virtual [~RebindPolicy()](#messagingrebindpolicy-class);
    ...
    static RebindPolicy_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static RebindPolicy_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static RebindPolicy_ptr _duplicate(
        RebindPolicy_ptr p
    );
    inline static RebindPolicy_ptr _nil();
    virtual ::Messaging::RebindMode [rebind_mode()](#messagingrebindpolicy-
class) = 0;
    ...
};

```

for descriptions of the standard helper methods:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`RebindPolicy::_local_narrow()`

`virtual void* _local_narrow(`

```
const char* tag
);
```

Note

For internal use only.

RebindPolicy::rebind_mode()

```
virtual ::Messaging::RebindMode rebind_mode() = 0;
```

Returns the effective rebind policy mode. The effective policies of other types for this object reference may change from invocation to invocation.

For GIOP-based protocols an object reference is considered bound once it is in a state where a locate-request message would result in a locate-reply message with status indicating where the object is. If `rebind_mode()` returns an effective policy value of `TRANSPARENT`, the ORB will silently forward any subsequent messages.

Regardless of the rebind policy in effect, you can always explicitly requested rebind or reconnection by calling `Object::_validate_connection()`. When instances of `RebindPolicy` are created, a value of type `RebindMode` is passed to `ORB::create_policy()`.

Exceptions

REBIND

Raised if:

- The effective policy value is `NO_REBIND` and if any rebind handling would cause a client-visible change in policies.
- The effective policy value is `NO_RECONNECT` and if any rebind handling would cause a client-visible change in policies, or if a new connection must be opened.

See Also `Messaging::RebindMode`

```
CORBA::ORB::create_policy()
CORBA::Object::_validate_connection()
```

RebindPolicy::~RebindPolicy() Destructor

```
virtual ~RebindPolicy();
```

The destructor for the object.

Messaging::ReplyHandler Base Class

This is the base class for the messaging callback model. A `ReplyHandler` is a CORBA object, implemented by the client application, which encapsulates the functionality for handling an asynchronous reply. The `ReplyHandler` is used with an asynchronous method invocation (AMI). The `ReplyHandler` is passed to an AMI and it is invoked when the reply to that request is available.

In the callback model, the client passes a reference to a reply handler (a client side CORBA object implementation that handles the reply for a client request), in addition to the normal parameters needed by the request. The reply handler interface defines operations to receive the results of that request (including inout and out values and possible exceptions). The `ReplyHandler` is a normal CORBA object that is implemented by the programmer as with any object implementation.

You must write the implementation for a type-specific `ReplyHandler`. A client obtains an object reference for this `ReplyHandler` and passes it as part of the AMI. When the server completes the request, its reply is delivered as an invocation on the `ReplyHandler` object. This invocation is made on the `ReplyHandler` using the normal POA techniques of servant and object activation. As a result, the callback operation may be handled in a different programming context than that in which the original request was made.

Exceptions can only be raised as part of a reply in the callback model. You use an `ExceptionHolder` to handle these exception replies. You create an `ExceptionHolder` value to encapsulate the identity and contents of an exception that might be raised, and an instance of this `ExceptionHolder` is passed as the argument to the `ReplyHandler` operation to indicate if an exception was raised by the target.

For each operation in an interface, corresponding callback asynchronous method signatures are generated by the IDL compiler. See the *CORBA Programmer's Guide* for generated methods and how to write your asynchronous callback implementations.

```

class ReplyHandler;
class ITGenReplyHandlerStreamable;
typedef ReplyHandler* ReplyHandler_ptr;
typedef ITCxxObjRef_var< ReplyHandler_ptr, ReplyHandler, ITCxxIntfAlloc<
ReplyHandler_ptr, ReplyHandler> > ReplyHandler_var;
typedef ITCxxObjRef_out< ReplyHandler_ptr, ReplyHandler, ITCxxIntfAlloc<
ReplyHandler_ptr, ReplyHandler> > ReplyHandler_out;
...
IT_ART_API IT_NAMESPACE_STATIC CORBA::TypeCode_ptr _tc_ReplyHandler;
class IT_ART_API ReplyHandler : public virtual CORBA::Object {
public:
    typedef Messaging::ReplyHandler_ptr _ptr_type;
    typedef Messaging::ReplyHandler_var _var_type;
    virtual [~ReplyHandler()](#messagingreplyhandler-base-class);
    ...
    static ReplyHandler_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static ReplyHandler_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static ReplyHandler_ptr _duplicate(
        ReplyHandler_ptr p
    );
    inline static ReplyHandler_ptr _nil();
    ...
};

```

for descriptions of the standard helper methods:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`ReplyHandler::_local_narrow()`

`virtual void* _local_narrow(`

```
    const char* tag  
);
```

Note

For internal use only.

ReplyHandler::~~ReplyHandler() Destructor

```
virtual ~ReplyHandler();
```

The destructor for the object.

Messaging::RoutingPolicy Class

The `RoutingPolicy` is a QoS policy that specifies whether or not the ORB must ensure delivery of a request through the use of queueing. This interface is a local object derived from `CORBA::Policy`.

When you create instances of `RoutingPolicy`, you pass a value of type `RoutingTypeRange` to `CORBA::ORB::create_policy()`. An instance of `RoutingPolicy` may be specified when creating a `POA` and therefore may be represented in object references.

In addition, a `POA`'s `RoutingPolicy` is visible to clients through the object references it creates, and reconciled with the client's override. If set on both the client and server, reconciliation is performed by intersecting the server-specified `RoutingPolicy` range with the range of the client's effective override.

```

class RoutingPolicy;
typedef RoutingPolicy* RoutingPolicy_ptr;
typedef ITCxxObjRef_var< RoutingPolicy_ptr, RoutingPolicy, ITCxxIntfAlloc<
RoutingPolicy_ptr, RoutingPolicy> > RoutingPolicy_var;
typedef ITCxxObjRef_out< RoutingPolicy_ptr, RoutingPolicy, ITCxxIntfAlloc<
RoutingPolicy_ptr, RoutingPolicy> > RoutingPolicy_out;
...
IT_ART_API IT_NAMESPACE_STATIC CORBA::TypeCode_ptr _tc_RoutingPolicy;
class IT_ART_API RoutingPolicy : public virtual ::CORBA::Policy {
public:
    typedef Messaging::RoutingPolicy_ptr _ptr_type;
    typedef Messaging::RoutingPolicy_var _var_type;
    virtual [~RoutingPolicy()](#messagingroutingpolicy-class);
    ...
    static RoutingPolicy_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static RoutingPolicy_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static RoutingPolicy_ptr _duplicate(
        RoutingPolicy_ptr p
    );
    inline static RoutingPolicy_ptr _nil();
    virtual ::Messaging::RoutingTypeRange [routing_range()]
    (#messagingroutingpolicy-class) = 0;
    ...
};

```

See [About Standard Functions for all Interfaces](#) for descriptions of the standard helper methods:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`RoutingPolicy::_local_narrow()`

`virtual void* _local_narrow()`

```
    const char* tag  
);
```

Note

For internal use only.

RoutingPolicy::~RoutingPolicy() Destructor

```
virtual ~RoutingPolicy();
```

The destructor for the object.

RoutingPolicy::routing_range()

```
virtual ::Messaging::RoutingTypeRange routing_range() = 0;
```

Returns the routing type range.

Messaging::SyncScopePolicy Class

The `SyncScopePolicy` is an ORB-level QoS policy that modifies the behavior of oneway operations. (Operations are specified in IDL with the `oneway` keyword.) This policy is only applicable as a client-side override. It is applied to oneway operations to indicate the synchronization scope with respect to the target of that operation request. It is ignored when any non-oneway operation is invoked. This policy is also applied when the DII is used with a flag of `INV_NO_RESPONSE` because the DII is not required to consult an interface definition to determine if an operation is declared oneway. The default value of this policy is not defined.

`SyncScopePolicy` is a local object derived from `CORBA::Policy`. You create instances of `SyncScopePolicy` by passing a value of type `Messaging::SyncScope` to `CORBA::ORB::create_policy()`. The client's `SyncScopePolicy` is propagated within a request in the request header's response flags. Your applications must explicitly set a `SyncScopePolicy` to ensure portability across ORB implementations.

```

class SyncScopePolicy;
typedef SyncScopePolicy* SyncScopePolicy_ptr;
typedef ITCxxObjRef_var< SyncScopePolicy_ptr, SyncScopePolicy,
ITCxxIntfAlloc< SyncScopePolicy_ptr, SyncScopePolicy> > SyncScopePolicy_var;
typedef ITCxxObjRef_out< SyncScopePolicy_ptr, SyncScopePolicy,
ITCxxIntfAlloc< SyncScopePolicy_ptr, SyncScopePolicy> > SyncScopePolicy_out;
...
IT_ART_API IT_NAMESPACE_STATIC CORBA::TypeCode_ptr _tc_SyncScopePolicy;
class IT_ART_API SyncScopePolicy :
    public virtual ::CORBA::Policy
{
public:
    typedef Messaging::SyncScopePolicy_ptr _ptr_type;
    typedef Messaging::SyncScopePolicy_var _var_type;
    virtual [~SyncScopePolicy()](#messagingsyncscopepolicy-class);
    ...
    static SyncScopePolicy_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static SyncScopePolicy_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static SyncScopePolicy_ptr _duplicate(
        SyncScopePolicy_ptr p
    );
    inline static SyncScopePolicy_ptr _nil();
    virtual ::Messaging::SyncScope [synchronization()]
    (#messagingsyncscopepolicy-class) = 0;
    ...
};

```

See [About Standard Functions for all Interfaces](#) for descriptions of the standard helper methods:

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`SyncScopePolicy::_local_narrow()`

`virtual void* _local_narrow(`


```
    const char* tag  
);
```

Note

For internal use only.

SyncScopePolicy::synchronization()

virtual ::Messaging::SyncScope synchronization() = 0;

Returns the level of synchronization.

See Also Messaging::SyncScope

SyncScopePolicy::~SyncScopePolicy() Destructor

virtual ~SyncScopePolicy();

The destructor for the object.

OrbixEventsAdmin Module

The previous Orbix implementation of the CORBA event service, OrbixEvents, provided the event channel administration interface, `ChannelManager`, defined in the module `OrbixEventsAdmin`, to allow Orbix 3.x clients to create and manipulate multiple event channels within an OrbixEvents server.

Orbix defines the `ChannelManager` interface for backwards compatibility with OrbixEvents users. This interface is defined in the file `orbixevents.idl` in the `include/idl` directory.

Warning

The `orbixevents.idl` file is deprecated. All new clients using the event service should be using the interfaces provided in the `IT_EventChannelAdmin` module (defined in `event_channel_admin.idl`).

Existing clients can contact the event service by calling `resolve_initial_references("EventService")` and narrowing the reference from `OrbixEventsAdmin::ChannelManager`.

OrbixEventsAdmin::ChannelManager

The previous Orbix implementation of the CORBA event service, OrbixEvents, provided the event channel administration interface, `ChannelManager`, defined in the module `OrbixEventsAdmin`, to allow Orbix 3.x clients to create and manipulate multiple event channels within an OrbixEvents server.

Orbix defines the `ChannelManager` interface for backwards compatibility with OrbixEvents users. This interface is defined in the file `orbixevents.idl` in the `include/idl` directory.

Warning

The `orbixevents.idl` file is deprecated. All new clients using the event service should be using the interfaces provided in the `IT_EventChannelAdmin` module (defined in `event_channel_admin.idl`).

Existing clients can contact the event service by calling `resolve_initial_references("EventService")` and narrowing the reference from `OrbixEventsAdmin::ChannelManager`.

`ChannelManager::create()`

```
CosEventChannelAdmin::EventChannel create(in string channel_id)
raises(duplicateChannel);
```

Creates an event channel.

Parameters

`channel_id`

The channel identifier for the event channel. The exception `duplicateChannel` is raised if the channel identifier specified in `channel_id` names an existing channel.

“Assigning Identifiers to Event Channels” on page 87 describes the format of channel identifiers.

`ChannelManager::find()`

```
CosEventChannelAdmin::EventChannel find(in string channel_id)
raises (noSuchChannel);
```

Finds the event channel associated with the channel identifier `channel_id`.

Parameters

```
channel_id
```

The channel identifier for the event channel. The exception `noSuchChannel` is raised if the channel identifier specified in `channel_id` does not exist.

“Assigning Identifiers to Event Channels” on page 87 describes the format of channel identifiers.

ChannelManager::findByRef()

```
string findByRef(
    in CosEventChannelAdmin::EventChannel channel_ref)
raises (noSuchChannel);
```

Finds the channel identifier of the event channel specified in `channel_ref`.

Parameters

```
channel_ref
```

The object reference for the event channel. If `channel_ref` does not exist within the event server, `findByRef()` raises the exception `noSuchChannel`.

ChannelManager::list()

```
stringSeq list ();
```

Lists the generic event channels contained within the channel manager’s event server.

ChannelManager::createTyped()

```

CosTypedEventChannelAdmin::TypedEventChannel createTyped(in string
channel_id)
raises(duplicateChannel);

```

Creates a typed event channel.

Parameters

```
channel_id
```

The channel identifier for the typed event channel. The exception `duplicateChannel` is raised if the channel identifier specified in `channel_id` names an existing typed event channel.

ChannelManager::findTyped()

```

CosTypedEventChannelAdmin::TypedEventChannel findTyped(in string channel_id)
raises (noSuchChannel);

```

Finds the typed event channel associated with the channel identifier `channel_id`.

Parameters

```
channel_id
```

The channel identifier for the typed event channel. The exception `noSuchChannel` is raised if the channel identifier specified in `channel_id` does not exist.

ChannelManager::findTypedByRef()

```

string findTypedByRef(in CosTypedEventChannelAdmin::TypedEventChannel
channel_ref)
raises (noSuchChannel);

```

Finds the channel identifier of the typed event channel specified in `channel_ref`.

Parameters

```
channel_ref
```

The object reference for the typed event channel. If `channel_ref` does not exist within the event server, `findByRef()` raises the exception `noSuchChannel`.

```
ChannelManager::listTyped()
```

```
stringSeq listTyped();
```

Lists the typed event channels contained within the channel manager's event server.

Unsupported Operations

The Application Server Platform event service does not support finding channels by reference. Therefore the `ChannelManager` reference will throw `NO_IMPLEMENT` for the following operations:

- `findByRef()`
- `findByTypedRef()`

PortableInterceptor Module

The `PortableInterceptor` module consists of these interfaces:

```
ClientRequestInfo
ClientRequestInterceptor
Current
Interceptor
IORInfo
IORInterceptor
ORBInitializer
ORBInitInfo
PolicyFactory
RequestInfo
ServerRequestInfo
ServerRequestInterceptor
```

The `PortableInterceptor` module also has the following exceptions and data types:

- `InvalidSlot` exception
- `ForwardRequest` exception
- `ReplyStatus` type
- `SlotId` type

`PortableInterceptor::ForwardRequest` Exception

// IDL

```
exception ForwardRequest {
    Object forward;
    boolean permanent;
};
```

The `ForwardRequest` exception allows an Interceptor to indicate to the ORB that a retry of the request should occur with the new object given in the exception. The **permanent** flag indicates whether the **forward** object is to become permanent or used only on the forwarded request.

If an Interceptor raises a `ForwardRequest` exception, no other Interceptors are called for that interception point. The remaining Interceptors in the Flow Stack have their appropriate ending interception point called: `receive_other` on the client, or `send_other` on the server. The `reply_status`

in the `receive_other` or `send_other` would be `LOCATION_FORWARD` or `LOCATION_FORWARD_PERMANENT`, depending on the value of the `permanent` element of `ForwardRequest`.

PortableInterceptor::InvalidSlot Exception

// IDL

```
exception InvalidSlot {};
```

Raised when a slot ID does not match an allocated slot.

PortableInterceptor::ReplyStatus Type

// IDL

```
typedef short ReplyStatus;
// Valid reply_status values:
const ReplyStatus SUCCESSFUL = 0;
const ReplyStatus SYSTEM_EXCEPTION = 1;
const ReplyStatus USER_EXCEPTION = 2;
const ReplyStatus LOCATION_FORWARD = 3;
const ReplyStatus LOCATION_FORWARD_PERMANENT = 4;
const ReplyStatus TRANSPORT_RETRY = 5;
```

This type is used to define an attribute describing the state of the result of an operation invocation.

See Also `RequestInfo::reply_status`

PortableInterceptor::SlotId Type

// IDL

```
typedef unsigned long SlotId;
```

This type is used to define a slot ID, identifying a slot within its table.

PortableInterceptor::ClientRequestInfo Interface

This is a locally constrained interface.

```
// IDL
local interface ClientRequestInfo : RequestInfo {
    readonly attribute Object [target] (#portableinterceptorclientrequestinfo-
interface);
    readonly attribute Object [effective_target]
(#portableinterceptorclientrequestinfo-interface);
    readonly attribute IOP::TaggedProfile [effective_profile]
(#portableinterceptorclientrequestinfo-interface);
    readonly attribute any [received_exception]
(#portableinterceptorclientrequestinfo-interface);
    readonly attribute CORBA::RepositoryId [received_exception_id]
(#portableinterceptorclientrequestinfo-interface);
    IOP::TaggedComponent [get_effective_component]
(#portableinterceptorclientrequestinfo-interface)(
    in IOP::ComponentId id
    );
    IOP_N::TaggedComponentSeq [get_effective_components]
(#portableinterceptorclientrequestinfo-interface)(
    in IOP::ComponentId id
    );
    CORBA::Policy [get_request_policy] (#portableinterceptorclientrequestinfo-
interface)(
    in CORBA::PolicyType type
    );
    void [add_request_service_context] (#portableinterceptorclientrequestinfo-
interface)(
    in IOP::ServiceContext service_context,
    in boolean replace
    );
};
```

`ClientRequestInfo` is an object through which the client-side Interceptor can access request information. It is passed to the client-side interception points, just as `ServerRequestInfo` is passed to server-side interception points. As there is information that is common to both, they both inherit from a common interface— `RequestInfo`.

Some attributes and operations on ClientRequestInfo are not valid at all interception points. [Table 22](#) shows the validity of each attribute or operation. If it is not valid, attempting to access it will result in a BAD_INV_ORDER being raised with a standard minor code of 10.

Table 22: ClientRequestInfo Validity

	send_request	send_poll	receive_reply	receive_exception	receive_other
<code>request_id</code>	Yes	Yes	Yes	Yes	Yes
<code>operation</code>	Yes	Yes	Yes	Yes	Yes
<code>arguments</code>	Yes (note 1)	No	Yes	No	No
<code>exceptions</code>	Yes	No	Yes	Yes	Yes
<code>contexts</code>	Yes	No	Yes	Yes	Yes
<code>operation_context</code>	Yes	No	Yes	Yes	Yes
<code>result</code>	No	No	Yes	No	No
<code>response_expected</code>	Yes	Yes	Yes	Yes	Yes
<code>sync_scope</code>	Yes	No	Yes	Yes	Yes
<code>reply_status</code>	No	No	Yes	Yes	Yes
<code>forward_reference</code>	No	No	No	No	Yes (note 2)
<code>get_slot</code>	Yes	Yes	Yes	Yes	Yes

	send_request	send_poll	receive_reply	receive_exception	receive_other
get_request_service_context	Yes	No	Yes	Yes	Yes
get_reply_service_context	No	No	Yes	Yes	Yes
target	Yes	Yes	Yes	Yes	Yes
effective_target	Yes	Yes	Yes	Yes	Yes
effective_profile	Yes	Yes	Yes	Yes	Yes
received_exception	No	No	No	Yes	No
received_exception_id	No	No	No	Yes	No
get_effective_component	Yes	No	Yes	Yes	Yes
get_effective_components	Yes	No	Yes	Yes	Yes
get_request_policy	Yes	No	Yes	Yes	Yes

	send_request	send_poll	receive_reply	receive_exception	receive_other
add_request_service_context	Yes	No	No	No	No

Note

When **ClientRequestInfo** is passed to `send_request`, there is an entry in the list for every argument, whether in, inout, or out. But only the in and inout arguments are available.

If the `reply_status` attribute is not `LOCATION_FORWARD` or `LOCATION_FORWARD_PERMANENT`, accessing this attribute raises `BAD_INV_ORDER` with a standard minor code of 10.

See Also `ServerRequestInfo : RequestInfo`; `RequestInfo`

`ClientRequestInfo::add_request_service_context()`

// IDL

```
void add_request_service_context(
    in IOP::ServiceContext service_context,
    in boolean replace
);
```

This operation allows Interceptors to add service contexts to a request for information. There is no declaration of the order of the service contexts. They may or may not appear in the order that they are added.

Parameters

<code>service_context</code>	The IOP::ServiceContext to be added to the request.

replace	Indicates the behavior of this operation when a service context already exists with the given ID: - true : the existing service context is replaced by the new one. - false : BAD_INV_ORDER with minor code of 11 is raised.

ClientRequestInfo::effective_profile Attribute

// IDL

```
readonly attribute IOP::TaggedProfile effective_profile;
```

This attribute is the profile that is used to send a request for information. If a location forward has occurred for this operation's object and that object's profile changed accordingly, then this profile is that located profile.

ClientRequestInfo::effective_target Attribute

// IDL

```
readonly attribute Object effective_target;
```

This attribute is the actual object on which a request for information is invoked. If the **reply_status** is **LOCATION_FORWARD**, then on subsequent requests, **effective_target** contains the forwarded IOR while **target** remains unchanged. If the **reply_status** is **LOCATION_FORWARD_PERMANENT**, then on subsequent requests, both **effective_target** and **target** contains the forwarded IOR.

ClientRequestInfo::get_effective_component()

// IDL

```
IOP::TaggedComponent get_effective_component(
    in IOP::ComponentId id
);
```

This operation returns the **IOP::TaggedComponent** with the given ID from the profile selected for this request. If there is more than one component for a given component ID, it is undefined which component this operation returns.

If there is more than one component for a given component ID, call `get_effective_components` instead.

Parameters

`id`

The `IOP::ComponentId` of the component that is to be returned.

Exceptions

`BAD_PARAM`, minor code `25`

No component exists for the given component ID.

`ClientRequestInfo::get_effective_components()`

// IDL

```
IOP_N::TaggedComponentSeq get_effective_components(
    in IOP::ComponentId id
);
```

This operation returns all the tagged components with the given ID from the profile elected for this request. This sequence is in the form of an **IOP::TaggedComponentSeq**.

Parameters

`id`

The **IOP::ComponentId** of the components which are to be returned.

Exceptions

`BAD_PARAM`, minor code `25`

No component exists for the given component ID.

`ClientRequestInfo::get_request_policy()`

// IDL

```
CORBA::Policy get_request_policy(
    in CORBA::PolicyType type
);
```

This operation returns the given policy in effect for the current request for information.

Parameters

type

The **CORBA::PolicyType** that specifies the policy to be returned.

Exceptions

INV_POLICY, minor code 1

The policy type is not valid either because the specified type is not supported by this ORB or because a policy object of that type is not associated with this Object.

ClientRequestInfo::received_exception Attribute

// IDL

```
readonly attribute any received_exception;
```

This attribute is an **any** that contains the exception to be returned to the client.

If the exception is a user exception which cannot be inserted into an **any** (for example, it is unknown or the bindings do not provide the **TypeCode**, this attribute will be an **any** containing the system exception UNKNOWN with a standard minor code of 1.

However, the RepositoryId of the exception is available in the **received_exception_id** attribute.

ClientRequestInfo::received_exception_id Attribute

// IDL

```
readonly attribute CORBA::RepositoryId received_exception_id;
```

This attribute is the **CORBA::RepositoryId** of the exception to be returned to the client.

ClientRequestInfo::target Attribute

// IDL

```
readonly attribute Object target;
```

This attribute is the object that the client called to perform the operation.

PortableInterceptor::ClientRequestInterceptor Interface

This is a locally constrained interface.

```
// IDL
local interface ClientRequestInterceptor : Interceptor {
    void [send_request](#portableinterceptorclientrequestinterceptor-
interface)(
        in ClientRequestInfo ri
    ) raises (ForwardRequest);
    void [send_poll](#portableinterceptorclientrequestinterceptor-interface)(
        in ClientRequestInfo ri
    );
    void [receive_reply](#portableinterceptorclientrequestinterceptor-
interface)(
        in ClientRequestInfo ri
    );
    void [receive_exception](#portableinterceptorclientrequestinterceptor-
interface)(
        in ClientRequestInfo ri
    ) raises (ForwardRequest);
    void [receive_other](#portableinterceptorclientrequestinterceptor-
interface)(
        in ClientRequestInfo ri
    ) raises (ForwardRequest);
};
```

A request Interceptor is designed to intercept the flow of a request/reply sequence through the ORB at specific points so that services can query the request information and manipulate the service contexts which are propagated between clients and servers.

The primary use of request Interceptors is to enable ORB services to transfer context information between clients and servers. ClientRequestInterceptor provides the client-side request interceptor.

See Also [Interceptor](#)

ClientRequestInterceptor::receive_exception()

// IDL

```
void receive_exception(
    in ClientRequestInfo ri
) raises (ForwardRequest);
```

This interception point is called when an exception occurs. It allows an Interceptor to query the exception's information before it is raised to the client. This interception point can raise a system exception. This has the effect of changing the exception that successive Interceptors popped from the Flow Stack `receive` on their calls to `receive_exception`. The exception raised to the client is the last exception raised by an Interceptor, or the original exception if no Interceptor changes the exception.

This interception point can also raise a ForwardRequest exception (see [PortableInterceptor::ForwardRequest Exception](#) for details on this exception). If an Interceptor raises this exception, no other Interceptors' `receive_exception` operations are called. The remaining Interceptors in the Flow Stack are popped and have their `receive_other` interception point called.

If the `completion_status` of the exception is not `COMPLETED_NO`, then it is inappropriate for this interception point to raise a ForwardRequest exception. The request's at-most-once semantics would be lost.

Compliant Interceptors that follow `completion_status` semantics raise a system exception from this interception point. If the original exception is a system exception, the `completion_status` of the new exception is the same as the original. If the original exception is a user exception, then the `completion_status` of the new exception is `COMPLETED_YES`.

Under some conditions, depending on what policies are in effect, an exception (such as `COMM_FAILURE`) can result in a retry of the request. While this retry is a new request with respect to Interceptors, there is one point of correlation between the original request and the retry: because control has not returned to the client, the `PortableInterceptor::Current` for both the original request and the retrying request is the same.

`ClientRequestInterceptor::receive_other()`

// IDL

```
void receive_other(
    in ClientRequestInfo ri
) raises (ForwardRequest);
```

This interception point allows an Interceptor to query the information available when a request results in something other than a normal reply or an exception.

For example, a request could result in a retry (for example, a GIOP Reply with a LOCATION_FORWARD status was received); or on asynchronous calls, the reply does not immediately follow the request, but control returns to the client and an ending interception point is called.

For retries, depending on the policies in effect, a new request may or may not follow when a retry has been indicated. If a new request does follow there is one point of correlation between the original request and the retry, with respect to Interceptors, and for as long as this request is a new request. This is because control has not returned to the client, and so the request scoped PortableInterceptor::Current for both the original request and the retrying request is the same.

This interception point can raise a system exception. If it does, no other Interceptors' receive_other operations are called. The remaining Interceptors in the Flow Stack are popped and have their receive_exception interception point called.

This interception point can also raise a ForwardRequest exception (see [PortableInterceptor::ForwardRequest Exception](#) for details on this exception). If an Interceptor raises this exception, successive Interceptors' receive_other operations are called with the new information provided by the ForwardRequest exception.

Compliant Interceptors properly follow completion_status semantics if they raise a system exception from this interception point. The completion_status must be COMPLETED_NO. If the target invocation had completed, this interception point would not be called.

ClientRequestInterceptor::receive_reply()

// IDL

```
void receive_reply(
    in ClientRequestInfo ri
);
```

This interception point allows an Interceptor to query the information on a reply, after it is returned from the server, and before control is returned to the client. This interception point can raise a system exception. If it does, no other Interceptors' **receive_reply** operations are called. The remaining Interceptors in the Flow Stack have their **receive_exception** interception point called.

Compliant Interceptors properly follow completion_status semantics if they raise a system exception from this interception point. The completion_status is COMPLETED_YES.

ClientRequestInterceptor::send_poll()

// IDL

```
void send_poll(
    in ClientRequestInfo ri
);
```

This interception point allows an Interceptor to query information during a Time-Independent Invocation (TII) polling get reply sequence. With TII, an application can poll for a response to a request sent previously by the polling client or some other client. This poll is reported to Interceptors through the **send_poll** interception point and the response is returned through the **receive_reply** or **receive_exception** interception points. If the response is not available before the poll time-out expires, the system exception **TIMEOUT** is raised and **receive_exception** is called with this exception.

This interception point can raise a system exception. If it does, no other Interceptors' **send_poll** operations are called. Those Interceptors on the Flow Stack are popped and their **receive_exception** interception points are called. Compliant Interceptors properly follow **completion_status** semantics if they raise a system exception from this interception point. The **completion_status** is **COMPLETED_NO**.

ClientRequestInterceptor::send_request()

// IDL

```
void send_request(
    in ClientRequestInfo ri
) raises (ForwardRequest);
```

This interception point allows an Interceptor to query request information and modify the service context before the request is sent to the server. This interception point can raise a system exception. If it does, no other Interceptors' **send_request** operations are called. Those Interceptors on the Flow Stack are popped and their **receive_exception** interception points are called.

This interception point may also raise a **ForwardRequest** exception (see [PortableInterceptor::ForwardRequest Exception](#) for details of this exception). If an Interceptor raises this exception, no other Interceptors' **send_request** operations are called. Those Interceptors on the Flow Stack are popped and their **receive_other** interception points are called.

Compliant Interceptors follow **completion_status** semantics if they raise a system exception from this interception point. The **completion_status** is **COMPLETED_NO**.

PortableInterceptor::Interceptor Interface

This is a locally constrained interface.

```
// IDL
local interface Interceptor {
    readonly attribute string [name](#portableinterceptorinterceptor-
interface);
};
```

Portable Interceptor interfaces and related type definitions reside in the module `PortableInterceptor`. All portable Interceptors inherit from the local interface `Interceptor`.

Interceptor::name Attribute

```
// IDL
```

```
readonly attribute string name;
```

Each Interceptor can have a name that is used to order the lists of Interceptors. Only one Interceptor of a given name can be registered with the ORB for each Interceptor type. An Interceptor can be anonymous, that is, have an empty string as the name attribute. Any number of anonymous Interceptors can be registered with the ORB.

PortableInterceptor::IORInfo Interface

This is a locally constrained interface.

```
// IDL
local interface IORInfo {
    CORBA::Policy [get_effective_policy](#portableinterceptoriorinfo-
interface)(
        in CORBA::PolicyType type
    );
    void [add_ior_component](#portableinterceptoriorinfo-interface)(
        in IOP::TaggedComponent a_component
    );
    void [add_ior_component_to_profile](#portableinterceptoriorinfo-
interface)(
        in IOP::TaggedComponent a_component,
        in IOP::ProfileId profile_id
    );
};
```

In some cases, a portable ORB service implementation has to add information describing the server's or object's ORB service capabilities to object references. This permits the ORB service implementation in the client to function properly.

This is supported through the IORInterceptor and IORInfo interfaces. The IOR Interceptor is used to establish tagged components in the profiles within an IOR.

IORInfo::add_ior_component()

// IDL

```
void add_ior_component(
    in IOP::TaggedComponent a_component
);
```

A portable ORB service implementation can call **add_ior_component** from its implementation of **establish_components** to add a tagged component to the set that is included when constructing IORs. The components in this set is included in all profiles.

Any number of components can exist with the same component ID.

Parameters

a_component

The **IOP::TaggedComponent** to add.

IORInfo::add_ior_component_to_profile()

// IDL

```
void add_ior_component_to_profile(
    in IOP::TaggedComponent a_component,
    in IOP::ProfileId profile_id
);
```

A portable ORB service can call **add_ior_component_to_profile** from its implementation of **establish_components** to add a tagged component to the set that is included when constructing IORs. The components in this set included in the specified profile.

Any number of components can exist with the same component ID.

Exceptions

BAD_PARAM, minor code 26

The given profile ID does not define a known profile or it is impossible to add components to that profile.

Parameters

a_component	The IOP::TaggedComponent to add.
profile_id	The IOP::ProfileId of the profile to which this component is to be added.

.IORInfo::get_effective_policy()

// IDL

```
CORBA::Policy get_effective_policy(  
    in CORBA::PolicyType type  
);
```

An ORB service implementation can determine what server side policy of a particular type is in effect for an IOR being constructed by calling **get_effective_policy ()**. The returned **CORBA::Policy** object can only be a policy whose type was registered with **ORBInitInfo::register_policy_factory** (see [ORBInitInfo::register_policy_factory\(\)](#)).

The return value is the effective CORBA::Policy object of the requested type.

Parameters

type

The **CORBA::PolicyType** specifying the type of policy to return.

Exceptions

INV_POLICY, minor code 2

A policy for the given type was not registered with **register_policy_factory()**.

PortableInterceptor::IORInterceptor Interface

This is a locally constrained interface.

```
// IDL
local interface IORInterceptor : Interceptor {
    void [establish_components](#portableinterceptoriorinterceptor-interface)
    (
        in IORInfo info
    );
};
```

In some cases, a portable ORB service implementation has to add information describing the server's or object's ORB service capabilities to object references. This permits the ORB service implementation in the client to function properly.

This is supported through the IORInterceptor and IORInfo interfaces. The IOR Interceptor is used to establish tagged components in the profiles within an IOR.

IORInterceptor::establish_components()

// IDL

```
void establish_components(
    in IORInfo info
);
```

A server side ORB calls `establish_components()` on all registered `IORInterceptor` instances when it is assembling the list of components that to be included in the profile or profiles of an object reference.

This operation is not necessarily called for each individual object reference. For example, the POA specifies policies at POA granularity and therefore, this operation might be called once per POA rather than once per object. In any case, `establish_components` is guaranteed to be called at least once for each distinct set of server policies.

An implementation of `establish_components` must not throw exceptions. If it does, the ORB ignores the exception and proceeds to call the next IOR Interceptor's `establish_components()` operation.

Parameters

info

The **IORInfo** instance used by the ORB service to query applicable policies and add components to be included in the generated IORs.

PortableInterceptor::ORBInitializer Interface

This is a locally constrained interface.

```
// IDL
local interface ORBInitializer {
    void [pre_init](#portableinterceptororbinitializer-interface)(
        in ORBInitInfo info
    );
    void [post_init](#portableinterceptororbinitializer-interface)(
        in ORBInitInfo info
    );
};
```

Interceptors are a means by which ORB services gain access to ORB processing, effectively becoming part of the ORB. Since Interceptors are part of the ORB, when `ORB_init` returns an ORB, the Interceptors have been registered.

Interceptors cannot be registered on an ORB after it has been returned by a call to `ORB_init`.

An Interceptor is registered by registering an associated `ORBInitializer` object that implements the `ORBInitializer` interface. When an ORB initializes, it calls each registered `ORBInitializer`, passing it an `ORBInitInfo` object that is used to register its Interceptor.

`ORBInitializer::post_init()`

// IDL

```
void post_init(
    in ORBInitInfo info
);
```

This operation is called during ORB initialization. If a service must resolve initial references as part of its initialization, it can assume that all initial references are available at this point.

Parameters

```
info
```

This object provides initialization attributes and operations by which Interceptors can be registered.

ORBInitializer::pre_init()

// IDL

```
void pre_init(  
    in ORBInitInfo info  
);
```

This operation is called during ORB initialization. All calls to **ORBInitInfo::register_initial_reference** must be made at this point so that the list of initial references is complete for the **post_init** point.

Parameters

```
info
```

This object provides initialization attributes and operations by which Interceptors can be registered.

PortableInterceptor::ORBInitInfo Interface

This is a locally constrained interface.

```

// IDL
local interface ORBInitInfo {
    typedef string [ObjectId](#portableinterceptororbinitinfo-interface);
    exception [DuplicateName](#portableinterceptororbinitinfo-interface) {
        string name;
    };
    exception [InvalidName](#portableinterceptororbinitinfo-interface) {};
    readonly attribute CORBA::StringSeq [arguments]
    (#portableinterceptorrequestinfo-interface);
    readonly attribute string [orb_id](#portableinterceptororbinitinfo-
interface);
    readonly attribute IOP_N::CodecFactory [codec_factory]
    (#portableinterceptororbinitinfo-interface);
    void [register_initial_reference](#portableinterceptororbinitinfo-
interface)(
        in ObjectId id,
        in Object obj
    ) raises (InvalidName);
    void [resolve_initial_references](#portableinterceptororbinitinfo-
interface)(
        in ObjectId id
    ) raises (InvalidName);
    void [add_client_request_interceptor](#portableinterceptororbinitinfo-
interface)(
        in ClientRequestInterceptor interceptor
    ) raises (DuplicateName);
    void [add_server_request_interceptor](#portableinterceptororbinitinfo-
interface)(
        in ServerRequestInterceptor interceptor
    ) raises (DuplicateName);
    void [add_ior_interceptor](#portableinterceptororbinitinfo-interface)(
        in IORInterceptor interceptor
    ) raises (DuplicateName);
    SlotId [allocate_slot_id()](#portableinterceptororbinitinfo-interface);
    void [register_policy_factory](#portableinterceptororbinitinfo-interface)
    (
        in CORBA::PolicyType type,
        in PolicyFactory policy_factory
    );
};

```

Interceptors are a means by which ORB services gain access to ORB processing, effectively becoming part of the ORB. Since Interceptors are part of the ORB, when `ORB_init` returns an ORB, the Interceptors have been registered.

Interceptors cannot be registered on an ORB after it has been returned by a call to `ORB_init`.

An Interceptor is registered by registering an associated `ORBInitializer` object that implements the `ORBInitializer` interface. When an ORB initializes, it calls each registered `ORBInitializer`, passing it an `ORBInitInfo` object that is used to register its Interceptor.

`ORBInitInfo::add_client_request_interceptor()`

// IDL

```
void add_client_request_interceptor(
    in ClientRequestInterceptor interceptor
) raises (DuplicateName);
```

This operation is used to add a client-side request Interceptor to the list of client-side request Interceptors.

Parameters

interceptor

The **ClientRequestInterceptor** to be added.

Exceptions

DuplicateName

A client-side request Interceptor has already been registered with this Interceptor's name.

`ORBInitInfo::add_ior_interceptor()`

// IDL

```
void add_ior_interceptor(
    in IORInterceptor interceptor
) raises (DuplicateName);
```

This operation is used to add an IOR Interceptor to the list of IOR Interceptors.

Parameters

```
interceptor
```

The **IORInterceptor** to be added.

Exceptions

```
DuplicateName
```

An IOR Interceptor has already been registered with this Interceptor's name.

```
ORBInitInfo::add_server_request_interceptor()
```

```
// IDL
```

```
void add_server_request_interceptor(
    in ServerRequestInterceptor interceptor
) raises (DuplicateName);
```

This operation is used to add a server-side request Interceptor to the list of server-side request Interceptors.

If a server-side request Interceptor has already been registered with this Interceptor's name, DuplicateName is raised.

Parameters

```
interceptor
```

The **ServerRequestInterceptor** to be added.

```
ORBInitInfo::allocate_slot_id()
```

```
// IDL
```

```
SlotId allocate_slot_id();
```

A service calls `allocate_slot_id` to allocate a slot on **PortableInterceptor::Current**.

The return value is the allocated slot index.

ORBInitInfo::arguments Attribute

// IDL

```
readonly attribute CORBA::StringSeq arguments;
```

This attribute contains the arguments passed to **ORB_init**. They may or may not contain the ORB's arguments.

ORBInitInfo::codec_factory Attribute

// IDL

```
readonly attribute IOP_N::CodecFactory codec_factory;
```

This attribute is the **IOP::CodecFactory**. The **CodecFactory** is normally obtained with a call to **ORB::resolve_initial_references ("CodecFactory")**, but as the ORB is not yet available and Interceptors, particularly when processing service contexts, require a **Codec**, a means of obtaining a **Codec** is necessary during ORB initialization.

ORBInitInfo::DuplicateName Exception

// IDL

```
exception DuplicateName {
    string name;
};
```

Only one Interceptor of a given name can be registered with the ORB for each Interceptor type. If an attempt is made to register a second Interceptor with the same name, **DuplicateName** is raised.

An Interceptor can be anonymous, that is, have an empty string as the name attribute.

Any number of anonymous Interceptors may be registered with the ORB so, if the Interceptor being registered is anonymous, the registration operation will not raise DuplicateName.

ORBInitInfo::InvalidName Exception

// IDL

```
exception InvalidName {};
```

This exception is raised by `register_initial_reference` and `resolve_initial_references`.

`register_initial_reference` raises `InvalidName` if this operation is called with an empty string `id`; or this operation is called with an `id` that is already registered, including the default names defined by OMG.

`resolve_initial_references` raises `InvalidName` if the name to be resolved is invalid.

ORBInitInfo::ObjectId Type

// IDL

```
typedef string ObjectId;
```

See Also `ORBInitInfo::register_initial_reference()`

ORBInitInfo::orb_id Attribute

// IDL

```
readonly attribute string orb_id;
```

This attribute is the ID of the ORB being initialized.

ORBInitInfo::register_initial_reference()

// IDL

```
void register_initial_reference(
    in ObjectId id,
    in Object obj
) raises (InvalidName);
```

If this operation is called with an `id`, "Y", and an object, YY, then a subsequent call to

`ORB::resolve_initial_references ("Y")` will return object YY.

Parameters

<code>id</code>	The ID by which the initial reference will be known.

<code>obj</code>	The initial reference itself.

Exceptions

<code>BAD_PARAM</code> , minor code 24	The <code>Object</code> parameter is null.
<code>InvalidName</code>	Raised if this operation is called with: - an empty string id. - an id that is already registered, including the default names defined by OMG.

Note

This method is identical to an operation is available in the ORB interface. This same functionality exists here because the ORB, not yet fully initialized, is not yet available but initial references may need to be registered as part of Interceptor registration. The only difference is that the version of this operation on the ORB uses PIDL (**CORBA::ORB::ObjectId** and **CORBA::ORB::InvalidName**) whereas the version in this interface uses IDL defined in this interface; the semantics are identical.

ORBInitInfo::register_policy_factory()

// IDL

```
void register_policy_factory(
    in CORBA::PolicyType type,
    in PolicyFactory policy_factory
);
```

Register a **PolicyFactory** for the given **PolicyType**.

Parameters

<code>type</code>	The CORBA::PolicyType that the given PolicyFactory serves.

<code>policy_factory</code>	The factory for the given CORBA::PolicyType .

Exceptions

`BAD_INV_ORDER` with minor code `12`

A `PolicyFactory` already exists for the given `PolicyType`.

`ORBInitInfo::resolve_initial_references()`

// IDL

```
void resolve_initial_references(
    in ObjectId id
) raises (InvalidName);
```

This operation is only valid during `post_init`. It is identical to **ORB::resolve_initial_references**. This same functionality exists here because the ORB, not yet fully initialized, is not yet available but initial references can be required from the ORB as part of Interceptor registration. The only difference is that the version of this operation on the ORB uses PIDL (**CORBA::ORB::ObjectId** and **CORBA::ORB::InvalidName**) whereas the version in this interface uses IDL defined in this interface; the semantics are identical.

PortableInterceptor::PolicyFactory Interface

This is a locally constrained interface.

```
// IDL
local interface PolicyFactory {
    CORBA::Policy [create_policy] (#portableinterceptorpolicyfactory-
interface)(
        in CORBA::PolicyType type,
        in any value
    ) raises (CORBA::PolicyError);
};
```

A portable ORB service implementation registers an instance of the `PolicyFactory` interface during ORB initialization in order to enable its policy types to be constructed using `CORBA::ORB::create_policy`. The POA is required to preserve any policy which is registered with `ORBInitInfo` in this manner.

`PolicyFactory::create_policy()`

// IDL

```
CORBA::Policy create_policy(
    in CORBA::PolicyType type,
    in any value
) raises (CORBA::PolicyError);
```

The ORB calls **create_policy** on a registered **PolicyFactory** instance when **CORBA::ORB::create_policy** is called for the **PolicyType** under which the **PolicyFactory** has been registered.

`create_policy` returns an instance of the appropriate interface derived from `CORBA::Policy` whose value corresponds to the specified `any`. If it cannot, it raises an exception as described for `CORBA::ORB::create_policy`.

Parameters

type	A CORBA::PolicyType specifying the type of policy being created.

value	An any containing data with which to construct the CORBA::Policy .

PortableInterceptor::RequestInfo Interface

This is a locally constrained interface.

```
// IDL
local interface RequestInfo {
    readonly attribute unsigned long [request_id]
    (#portableinterceptorrequestinfo-interface);
    readonly attribute string [operation](#portableinterceptorrequestinfo-
interface);
    readonly attribute Dynamic::ParameterList [arguments]
    (#portableinterceptorrequestinfo-interface);
    readonly attribute Dynamic::ExceptionList [exceptions]
    (#portableinterceptorrequestinfo-interface);
    readonly attribute Dynamic::ContextList [contexts]
    (#portableinterceptorrequestinfo-interface);
    readonly attribute Dynamic::RequestContext [operation_context]
    (#portableinterceptorrequestinfo-interface);
    readonly attribute any ;
    readonly attribute boolean [response_expected]
    (#portableinterceptorrequestinfo-interface);
    readonly attribute Messaging::SyncScope [sync_scope]
    (#portableinterceptorrequestinfo-interface);
    readonly attribute ReplyStatus [reply_status]
    (#portableinterceptorrequestinfo-interface);
    readonly attribute Object ;
    any [get_slot](#portableinterceptorrequestinfo-interface)(
        in SlotId id
    ) raises (InvalidSlot);
    IOP::ServiceContext [get_request_service_context]
    (#portableinterceptorrequestinfo-interface)(
        in IOP::ServiceId id
    );
    IOP::ServiceContext [get_reply_service_context]
    (#portableinterceptorrequestinfo-interface)(
        in IOP::ServiceId id
    );
};
```

Each interception point is given an object through which the Interceptor can access request information. Client-side and server-side interception points are concerned with different information, so there are two information objects. `ClientRequestInfo` is passed to the client-side interception points and `ServerRequestInfo` is passed to the server-side interception points. But as there is information that is common to both, so they both inherit from a common interface: `RequestInfo`.

See Also `ClientRequestInfo` ; `ServerRequestInfo`

`RequestInfo::arguments` Attribute

// IDL

```
readonly attribute Dynamic::ParameterList arguments;
```

This attribute is a **Dynamic::ParameterList** containing the arguments on the operation being invoked. If there are no arguments, this attribute is a zero length sequence.

Exceptions

`NO_RESOURCES`, minor code 1

The environment does not provide access to the arguments—for example, in the case of Java portable bindings.

RequestInfo::contexts Attribute

// IDL

```
readonly attribute Dynamic::ContextList contexts;
```

This attribute is a **Dynamic::ContextList** describing the contexts that can be passed on this operation invocation. If there are no contexts, this attribute is a zero length sequence.

Exceptions

`NO_RESOURCES`, minor code 1

The environment does not provide access to the context list—for example, in the case of Java portable bindings.

RequestInfo::exceptions Attribute

// IDL

```
readonly attribute Dynamic::ExceptionList exceptions;
```

This attribute is a **Dynamic::ExceptionList** describing the **TypeCodes** of the user exceptions that this operation invocation can raise. If there are no user exceptions, this attribute is a zero length sequence.

Exceptions

`NO_RESOURCES`, minor code 1

The environment does not provide access to the exception list—for example, in the case of Java portable bindings.

// IDL

```
readonly attribute Object forward_reference;
```

If the **reply_status** attribute is **LOCATION_FORWARD** or **LOCATION_FORWARD_PERMANENT**, then this attribute contains the object to which the request is to be forwarded. It is indeterminate whether a forwarded request actually occurs.

RequestInfo::get_reply_service_context()

// IDL

```
IOP::ServiceContext get_reply_service_context(
    in IOP::ServiceId id
);
```

This operation returns a copy of the service context with the given ID that is associated with the reply.

The return value is the IOP::ServiceContext obtained with the given identifier.

Parameters

```
id
```

The `IOP::ServiceId` of the service context which is to be returned.

Exceptions

`BAD_PARAM` with minor code `23`

The request's service context does not contain an entry for the specified ID.

RequestInfo::get_request_service_context()

// IDL

```
IOP::ServiceContext get_request_service_context(
    in IOP::ServiceId id
);
```

This operation returns a copy of the service context with the given ID that is associated with the request.

The return value is the `IOP::ServiceContext` obtained with the given identifier.

Parameters

```
id
```

The **IOP::ServiceId** of the service context which is to be returned.

Exceptions

`BAD_PARAM` with minor code `23`

The request's service context does not contain an entry for the specified ID.

RequestInfo::get_slot()

// IDL

```
any get_slot(
    in SlotId id
) raises (InvalidSlot);
```

This operation returns the data from the given slot of the **PortableInterceptor::Current** that is in the scope of the request. If the given slot has not been set, then an **any** containing a type code with a **TCKind** value of **tk_null** is returned.

The return value is the slot data, in the form of an any, obtained with the given identifier.

Parameters

```
id
```

The `SlotId` of the slot that is to be returned.

Exceptions

InvalidSlot

The ID does not define an allocated slot.

RequestInfo::operation Attribute

// IDL

```
readonly attribute string operation;
```

This attribute is the name of the operation being invoked.

RequestInfo::operation_context Attribute

// IDL

```
readonly attribute Dynamic::RequestContext operation_context;
```

This attribute is a **Dynamic::RequestContext** containing the contexts being sent on the request

Exceptions

`NO_RESOURCES`, minor code 1

The environment does not provide access to the context—for example, in the case of Java portable bindings.

RequestInfo::reply_status Attribute

// IDL

```
readonly attribute ReplyStatus reply_status;
```

This attribute describes the state of the result of the operation invocation. Its value can be one of the following:

```

PortableInterceptor::SUCCESSFUL
PortableInterceptor::SYSTEM_EXCEPTION
PortableInterceptor::USER_EXCEPTION
PortableInterceptor::LOCATION_FORWARD
PortableInterceptor::LOCATION_FORWARD_PERMANENT
PortableInterceptor::TRANSPORT_RETRY

```

On the client:

- Within the `receive_reply` interception point, this attribute is only `SUCCESSFUL`.
- Within the `receive_exception` interception point, this attribute is either `SYSTEM_EXCEPTION` or `USER_EXCEPTION`.
- Within the `receive_other` interception point, this attribute is any of `SUCCESSFUL`, `LOCATION_FORWARD`, `LOCATION_FORWARD_PERMANENT`, or `TRANSPORT_RETRY`.

`SUCCESSFUL` means an asynchronous request returned successfully.

`LOCATION_FORWARD` and `LOCATION_FORWARD_PERMANENT` mean that a reply came back with one of these as its status.

`TRANSPORT_RETRY` means that the transport mechanism indicated a retry: a GIOP reply with a status of `NEEDS_ADDRESSING_MODE`, for instance.

On the server:

- Within the `send_reply` interception point, this attribute is only `SUCCESSFUL`.
- Within the `send_exception` interception point, this attribute is either `SYSTEM_EXCEPTION` or `USER_EXCEPTION`.
- Within the `send_other` interception point, this attribute is any of: `SUCCESSFUL`, `LOCATION_FORWARD`, or `LOCATION_FORWARD_PERMANENT`. `SUCCESSFUL` means an asynchronous request returned successfully. `LOCATION_FORWARD` and `LOCATION_FORWARD_PERMANENT` mean that a reply came back with one of these as its status.

`RequestInfo::request_id` Attribute

// IDL

```
readonly attribute unsigned long request_id;
```

This ID uniquely identifies an active request/reply sequence. Once a request/reply sequence is concluded this ID may be reused.

Note that this id is not the same as the GIOP `request_id`. If GIOP is the transport mechanism used, then these IDs may very well be the same, but this is not guaranteed nor required.

RequestInfo::response_expected Attribute

// IDL

```
readonly attribute boolean response_expected;
```

This boolean attribute indicates whether a response is expected. On the client:

- A reply is not returned when `response_expected` is false, so `receive_reply` cannot be called.
- If an exception occurs, `receive_exception` is called.
- Otherwise `receive_other` is called.

On the client, within `send_poll`, this attribute is true.

RequestInfo::result Attribute

// IDL

```
readonly attribute any result;
```

This attribute is an `any` containing the result of the operation invocation.

If the operation return type is `void`, this attribute is an `any` containing a type code with a TCKind value of `tk_void` and no value.

Exceptions

`NO_RESOURCES`, minor code 1

The environment does not provide access to the result—for example, in the case of Java portable bindings.

RequestInfo::sync_scope Attribute

// IDL

```
readonly attribute Messaging::SyncScope sync_scope;
```

This attribute, defined in the Messaging specification, is pertinent only when **`response_expected`** is `false`. If **`response_expected`** is `true`, the value of **`sync_scope`** is undefined. It defines how far the request progresses before control is returned to the client. This attribute may have one of the following values:

```
Messaging::SYNC_NONE  
Messaging::SYNC_WITH_TRANSPORT  
Messaging::SYNC_WITH_SERVER  
Messaging::SYNC_WITH_TARGET
```

On the server, for all scopes, a reply is created from the return of the target operation call, but the reply does not return to the client. Although it does not return to the client, it does occur, so the normal server-side interception points are followed (that is, **receive_request_service_contexts**, `receive_request`, **send_reply** or `send_exception`). For **SYNC_WITH_SERVER** and `SYNC_WITH_TARGET`, the server does send an empty reply back to the client before the target is invoked. This reply is not intercepted by server-side Interceptors.

PortableInterceptor::ServerRequestInfo Interface

This is a locally constrained interface.

```
// IDL
local interface ServerRequestInfo : RequestInfo {
    readonly attribute any [sending_exception]
    (#portableinterceptorserverrequestinfo-interface);
    readonly attribute CORBA::OctetSeq [object_id]
    (#portableinterceptorserverrequestinfo-interface);
    readonly attribute CORBA::OctetSeq [adapter_id]
    (#portableinterceptorserverrequestinfo-interface);
    readonly attribute
        CORBA::RepositoryId [target_most_derived_interface]
    (#portableinterceptorserverrequestinfo-interface);
    CORBA::Policy [get_server_policy] (#portableinterceptorserverrequestinfo-
interface)(
        in CORBA::PolicyType type
    );
    void [set_slot] (#portableinterceptorserverrequestinfo-interface)(
        in SlotId id,
        in any data
    ) raises (InvalidSlot);
    boolean [target_is_a] (#portableinterceptorserverrequestinfo-interface)(
        in CORBA::RepositoryId id
    );
    void [add_reply_service_context] (#portableinterceptorserverrequestinfo-
interface)(
        in IOP::ServiceContext service_context,
        in boolean replace
    );
};
```

`ServerRequestInfo` is an object through which the server-side Interceptor can access request information. It is passed to the server-side interception points, just as `ClientRequestInfo` is passed to client-side interception points. As there is information that is common to both, they both inherit from a common interface- `RequestInfo`.

ServerRequestInfo::adapter_id Attribute


```
// IDL
```

```
readonly attribute CORBA::OctetSeq adapter_id;
```

This attribute is the opaque identifier for the object adapter.

ServerRequestInfo::add_reply_service_context()

```
// IDL
```

```
void add_reply_service_context(
    in IOP::ServiceContext service_context,
    in boolean replace
);
```

This operation allows Interceptors to add service contexts to the request. There is no declaration of the order of the service contexts. They may or may not appear in the order that they are added.

Parameters

<code>service_context</code>	The IOP::ServiceContext to add to the reply.
<code>replace</code>	Indicates the behavior of this operation when a service context already exists with the given ID. If <code>false</code> , then BAD_INV_ORDER with a standard minor code of 11 is raised. If true, then the existing service context is replaced by the new one.

ServerRequestInfo::get_server_policy()

```
// IDL
```

```
CORBA::Policy get_server_policy(
    in CORBA::PolicyType type
);
```

This operation returns the policy in effect for this operation for the given policy type. The returned **CORBA::Policy** object is a policy whose type was registered using **register_policy_factory**

Parameters

type

The **CORBA::PolicyType** which specifies the policy to be returned.

Exceptions

`INV_POLICY`, minor code `2`

A policy for the given type was not registered using `register_policy_factory()`.

ServerRequestInfo::object_id Attribute

// IDL

```
readonly attribute CORBA::OctetSeq object_id;
```

This attribute is the opaque **object_id** describing the target of the operation invocation.

ServerRequestInfo::sending_exception Attribute

// IDL

```
readonly attribute any sending_exception;
```

This attribute is an **any** that contains the exception to be returned to the client.

If the exception is a user exception which cannot be inserted into an any (that is, it is unknown or the bindings do not provide the `TypeCode`), this attribute is an any containing the system exception `UNKNOWN` with a standard minor code of `1`.

ServerRequestInfo::set_slot()

// IDL

```
void set_slot(
    in SlotId id,
    in any data
) raises (InvalidSlot);
```

This operation allows an Interceptor to set a slot in the **PortableInterceptor::Current** that is in the scope of the request. If data already exists in that slot, it is overwritten.

Parameters

<code>id</code>	The SlotId of the slot.
<code>data</code>	The data, in the form of an <code>any</code> , to store in that slot.

Exceptions

`InvalidSlot`

The ID does not define an allocated slot.

`ServerRequestInfo::target_is_a()`

// IDL

```
boolean target_is_a(
    in CORBA::RepositoryId id
);
```

This operation returns **true** if the servant is the given **RepositoryId**, and **false** if it is not.

Parameters

`id`

The caller wants to know if the servant is this **CORBA::RepositoryId**.

`ServerRequestInfo::target_most_derived_interface` Attribute

// IDL

```
readonly attribute
    CORBA::RepositoryId target_most_derived_interface;
```

This attribute is the `RepositoryID` for the most derived interface of the servant.

PortableInterceptor::ServerRequestInterceptor Interface

This is a locally constrained interface.

```
// IDL
local interface ServerRequestInterceptor : Interceptor {
    void [receive_request_service_contexts]
    (#portableinterceptorserverrequestinterceptor-interface)(
        in ServerRequestInfo ri
    ) raises (ForwardRequest);
    void [receive_request](#portableinterceptorserverrequestinterceptor-
interface)(
        in ServerRequestInfo ri
    ) raises (ForwardRequest);
    void [send_reply](#portableinterceptorserverrequestinterceptor-interface)
    (
        in ServerRequestInfo ri
    );
    void [send_exception](#portableinterceptorserverrequestinterceptor-
interface)(
        in ServerRequestInfo ri
    ) raises (ForwardRequest);
    void [send_other](#portableinterceptorserverrequestinterceptor-interface)
    (
        in ServerRequestInfo ri
    ) raises (ForwardRequest);
};
```

A request Interceptor is designed to intercept the flow of a request/reply sequence through the ORB at specific points so that services can query the request information and manipulate the service contexts which are propagated between clients and servers.

The primary use of request Interceptors is to enable ORB services to transfer context information between clients and servers. ServerRequestInterceptor provides the server-side request interceptor.

ServerRequestInterceptor::receive_request()

```
// IDL
```

```
void receive_request(
    in ServerRequestInfo ri
) raises (ForwardRequest);
```

This interception point allows an Interceptor to query request information after all the information, including operation parameters, is available. This interception point may or may not execute in the same thread as the target invocation.

In the DSI model, as the parameters are first available when the user code calls `arguments`, `receive_request` is called from within `arguments`. It is possible that `arguments` is not called in the DSI model. The target can call `set_exception` before calling `arguments`.

The ORB guarantees that `receive_request` is called once, either through `arguments` or through `set_exception`. If it is called through `set_exception`, requesting the arguments results in `NO_RESOURCES` being raised with a standard minor code of 1. This interception point can raise a system exception. If it does, no other Interceptors' `receive_request` operations are called. Those Interceptors on the Flow Stack are popped and their `send_exception` interception points are called.

This interception point can also raise a `ForwardRequest` exception. If an Interceptor raises this exception, no other Interceptors' `receive_request` operations are called. Those Interceptors on the Flow Stack are popped and their `send_other` interception points are called.

Compliant Interceptors follow `completion_status` semantics if they raise a system exception from this interception point. The `completion_status` shall be `COMPLETED_NO`.

`ServerRequestInterceptor::receive_request_service_contexts()`

// IDL

```
void receive_request_service_contexts(
    in ServerRequestInfo ri
) raises (ForwardRequest);
```

At this interception point, Interceptors must get their service context information from the incoming request transfer it to **PortableInterceptor::Current** slots. This interception point is called before the servant manager is called. Operation parameters are not yet available at this point. This interception point may or may not execute in the same thread as the target invocation.

This interception point can raise a system exception. If it does, no other Interceptors' `receive_request_service_contexts` operations are called. Those Interceptors on the Flow Stack are popped and their `send_exception` interception points are called.

This interception point can also raise a `ForwardRequest` exception (see [PortableInterceptor::ForwardRequest Exception](#)). If an Interceptor raises this exception, no other Interceptors' `receive_request_service_contexts` operations are called. Those Interceptors on the Flow Stack are popped and their `send_other` interception points are called.

Compliant Interceptors follow `completion_status` semantics if they raise a system exception from this interception point. The `completion_status` is `COMPLETED_NO`.

`ServerRequestInterceptor::send_exception()`

// IDL

```
void send_exception(
    in ServerRequestInfo ri
) raises (ForwardRequest);
```

This interception point is called when an exception occurs. It allows an Interceptor to query the exception information and modify the reply service context before the exception is raised to the client.

This interception point can raise a system exception. This has the effect of changing the exception that successive Interceptors popped from the Flow Stack receive on their calls to `send_exception`. The exception raised to the client is the last exception raised by an Interceptor, or the original exception if no Interceptor changes the exception.

This interception point also raises a `ForwardRequest` exception (see [PortableInterceptor::ForwardRequest Exception](#)). If an Interceptor raises this exception, no other Interceptors' `send_exception` operations are called. The remaining Interceptors in the Flow Stack have their `send_other` interception points called.

If the `completion_status` of the exception is not `COMPLETED_NO`, then it is inappropriate for this interception point to raise a `ForwardRequest` exception. The request's at-most-once semantics would be lost.

Compliant Interceptors follow `completion_status` semantics if they raise a system exception from this interception point. If the original exception is a system exception, the `completion_status` of the new exception is the same as on the original. If the original exception is a user exception, then the `completion_status` of the new exception shall be `COMPLETED_YES`.

`ServerRequestInterceptor::send_other()`

// IDL

```
void send_other(
    in ServerRequestInfo ri
) raises (ForwardRequest);
```

This interception point allows an Interceptor to query the information available when a request results in something other than a normal reply or an exception. For example, a request could result in a retry (for example, a GIOP Reply with a **LOCATION_FORWARD** status was received).

This interception point can raise a system exception. If it does, no other Interceptors' `send_other` operations are called. The remaining Interceptors in the Flow Stack have their `send_exception` interception points called.

This interception point can also raise a ForwardRequest exception (see [PortableInterceptor::ForwardRequest Exception](#)). If an Interceptor raises this exception, successive Interceptors' operations are called with the new information provided by the ForwardRequest exception.

Compliant Interceptors follow `completion_status` semantics if they raise a system exception from this interception point. The `completion_status` is `COMPLETED_No`.

ServerRequestInterceptor::send_reply()

// IDL

```
void send_reply(
    in ServerRequestInfo ri
);
```

This interception point allows an Interceptor to query reply information and modify the reply service context after the target operation has been invoked and before the reply is returned to the client.

This interception point can raise a system exception. If it does, no other Interceptors' `send_reply` operations are called. The remaining Interceptors in the Flow Stack have their `send_exception` interception point called.

Compliant Interceptors follow `completion_status` semantics if they raise a system exception from this interception point. The `completion_status` is `COMPLETED_YES`.

PortableServer Overview

The `PortableServer` module includes a number of data structures and classes that are specific to a portable object adapter, or POA. This chapter describes the following:

- [PortableServer conversion functions](#)
- [PortableServer Data Types, Constants, and Exceptions](#)

The rest of the `PortableServer` classes and interfaces are described in subsequent chapters as follows:

- [PortableServer::AdapterActivator Interface](#)
- [PortableServer::DynamicImplementation Class](#)
- [PortableServer::POA Interface](#)
- [PortableServer::POAManager Interface](#)
- [PortableServer::ServantActivator Interface](#)
- [PortableServer::ServantLocator Interface](#)
- [PortableServer::ServantManager Interface](#)

The `PortableServer` policy classes are described in subsequent chapters as follows:

- [PortableServer::IdAssignmentPolicy Interface](#)
- [PortableServer::IdUniquenessPolicy Interface](#)
- [PortableServer::ImplicitActivationPolicy Interface](#)
- [PortableServer::LifespanPolicy Interface](#)
- [PortableServer::RequestProcessingPolicy Interface](#)
- [PortableServer::ServantRetentionPolicy Interface](#)
- [PortableServer::ThreadPolicy Interface](#)

PortableServer conversion functions

Objects that are registered with POAs are identified by `ObjectId` types, which are sequences of octets. The PortableServer module contains several conversion functions that let you use strings as object identifiers.

```
// C++
namespace PortableServer {
char* [ObjectId_to_string](#)(const ObjectId&);
wchar_t* [ObjectId_to_wstring](#)(const ObjectId&);
ObjectId* [string_to_ObjectId](#)(const char*);
ObjectId* [wstring_to_ObjectId](#)(const wchar_t*);
}
```

`ObjectId_to_string()`

```
char* ObjectId_to_string(
const ObjectId&
);
```

Converts an `ObjectId` to a string.

`ObjectId_to_wstring()`

```
wchar_t* ObjectId_to_wstring(
const ObjectId&
);
```

Converts an `ObjectId` to a wide string.

`string_to_ObjectId()`

```
ObjectId* string_to_ObjectId(
const char*
);
```

Converts a string to an `ObjectId`.

`wstring_to_ObjectId()`

```

ObjectId* wstring_to_ObjectId(
const wchar_t*
);

```

Converts a wide string to an ObjectId.

PortableServer Data Types, Constants, and Exceptions

The `PortableServer` module contains the following common exceptions and data types:

Table 23: PortableServer Common Types

Common Types and Exceptions	Policy value enumerations	Policy
<code>ForwardRequest</code>	<code>IdAssignmentPolicyValue</code>	<code>ID_A</code>
<code>ObjectID</code>	<code>IdUniquenessPolicyValue</code>	<code>ID_U</code>
<code>POAList</code>	<code>#p_d35570e1_d35571e1_d35572e1_d35573e1ImplicitActivationPolicyValue</code>	<code>IMPL</code>
<code>Servant</code>	<code>LifespanPolicyValue</code>	<code>LIFE</code>
	<code>#p_d35678e1_d35679e1_d35680e1_d35681e1RequestProcessingPolicyValue</code>	<code>REQ</code>
	<code>#p_d35730e1_d35731e1_d35732e1_d35733e1ServantRetentionPolicyValue</code>	<code>SERV</code>
	<code>ThreadPolicyValue</code>	<code>THRE</code>

PortableServer::ForwardRequest Exception

```

//IDL
exception ForwardRequest {
Object forward_reference;
};

```

In addition to standard CORBA exceptions, a servant manager is capable of raising a `ForwardRequest` exception. This exception includes an object reference.

PortableServer::ID_ASSIGNMENT_POLICY_ID Constant

```
//IDL
const CORBA::PolicyType ID_ASSIGNMENT_POLICY_ID = 19;
```

Defines an ID for the policy `IdAssignmentPolicy`.

PortableServer::IdAssignmentPolicyValue Enumeration

```
// IDL
enum IdAssignmentPolicyValue {
    USER_ID,
    SYSTEM_ID
};
```

One of the following values can be supplied when creating an `IdAssignmentPolicy` policy.

USER_ID

Objects created with the POA are assigned an `ObjectId` only by the application.

SYSTEM_ID

PortableServer::ID_UNIQUENESS_POLICY_ID Constant

```
//IDL
const CORBA::PolicyType ID_UNIQUENESS_POLICY_ID = 18;
```

Defines an ID for the policy `IdUniquenessPolicy`.

PortableServer::IdUniquenessPolicyValue Enumeration

```
// IDL
enum IdUniquenessPolicyValue {
    UNIQUE_ID,
    MULTIPLE_ID
};
```

One of the following values can be supplied when creating an `IdUniquenessPolicy` policy.

UNIQUE_ID

Servants activated with the POA support exactly one `ObjectId`.

MULTIPLE_ID

PortableServer::IMPLICIT_ACTIVATION_POLICY_ID Constant

```
//IDL
const CORBA::PolicyType IMPLICIT_ACTIVATION_POLICY_ID = 20;
```

Defines an ID for the policy `ImplicitActivationPolicy`.

PortableServer::ImplicitActivationPolicyValue Enumeration

```
// IDL
enum ImplicitActivationPolicyValue {
    IMPLICIT_ACTIVATION,
    NO_IMPLICIT_ACTIVATION
};
```

One of the following values can be supplied when creating an `ImplicitActivationPolicy` policy.

IMPLICIT_ACTIVATION

The POA will support implicit activation of servants. `IMPLICIT_ACTIVATION` also requires the `SYSTEM_ID` and `RETAIN` policy values.

NO_IMPLICIT_ACTIVATION

PortableServer::LIFESPAN_POLICY_ID Constant

```
//IDL
const CORBA::PolicyType LIFESPAN_POLICY_ID = 17;
```

Defines an ID for the policy `LifeSpanPolicy`.

PortableServer::LifespanPolicyValue Enumeration

```
// IDL
enum LifespanPolicyValue {
    TRANSIENT,
    PERSISTENT
};
```

One of the following values can be supplied when creating a `LifespanPolicy` policy:

TRANSIENT

The objects implemented in the POA cannot outlive the POA instance in which they are first created. Once the POA is deactivated, use of any object references generated from it will result in an `OBJECT_NOT_EXIST` exception.

PERSISTENT

The objects implemented in the POA can outlive the process in which they are first created.

Persistent objects have a POA associated with them which is the POA that created them. When the ORB receives a request on a persistent object, it first searches for the matching POA, based on the names of the POA and all of its ancestors.

See Also `PortableServer::LifespanPolicy`.

`PortableServer::ObjectId` Sequence

```
// IDL
typedef sequence<octet> ObjectId;
//C++
class ObjectId { ...
```

`ObjectIds` are strings that identify a required object reference.

See [About Sequences](#) for a description of the mapping of IDL sequences.

`PortableServer::POAList` Sequence

```
// IDL
typedef sequence<POA> POAList;
//C++
class POAList { ...
```

A `POAList` is a sequence of child POAs.

See [About Sequences](#) for a description of the mapping of IDL sequences.

`PortableServer::REQUEST_PROCESSING_POLICY_ID` Constant

```
//IDL
const CORBA::PolicyType REQUEST_PROCESSING_POLICY_ID = 22;
```

Defines an ID for the policy `RequestProcessingPolicy`.

PortableServer::RequestProcessingPolicyValue Enumeration

```
// IDL
enum RequestProcessingPolicyValue {
    USE_ACTIVE_OBJECT_MAP_ONLY,
    USE_DEFAULT_SERVANT,
    USE_SERVANT_MANAGER
};
```

One of the following values can be supplied when creating a `RequestProcessingPolicy` policy.

USE_ACTIVE_OBJECT_MAP_ONLY

If the `ObjectId` is not found in the active object map, an `OBJECT_NOT_EXIST` exception is returned to the client. The `RETAIN` policy value is also required.

USE_DEFAULT_SERVANT

If the `ObjectId` is not found in the active object map or the `NON_RETAIN` policy value is present, and a default servant has been registered with the POA using `set_servant()`, the request is dispatched to the default servant. If no default servant has been registered, an `OBJ_ADAPTER` exception is returned to the client. The `MULTIPLE_ID` policy value is also required.

USE_SERVANT_MANAGER

If the `ObjectId` is not found in the active object map or the `NON_RETAIN` policy value is present, and a servant manager has been registered with the POA using `set_servant_manager()`, the servant manager is given the opportunity to locate a servant or raise an exception. If no servant manager has been registered, an `OBJECT_ADAPTER` exception is returned to the client.

PortableServer::Servant Native Type

```
// IDL
native Servant;
// C++ in namespace PortableServer
typedef ServantBase* Servant;
```

The native `Servant` type has a language-specific mapping.

PortableServer::SERVANT_RETENTION_POLICY_ID Constant

```
//IDL
const CORBA::PolicyType SERVANT_RETENTION_POLICY_ID = 21;
```

Defines an ID for the policy `ServantRetentionPolicy`.

PortableServer::ServantRetentionPolicyValue Enumeration

```
// IDL
enum ServantRetentionPolicyValue {
    RETAIN,
    NON_RETAIN
};
```

One of the following values can be supplied when creating a `ServantRetentionPolicy` policy.

RETAIN

The POA will retain active servants in its active object map.

NON_RETAIN

Servants are not retained by the POA. The `NON_RETAIN` policy requires either the `USE_DEFAULT_SERVANT` or `USE_SERVANT_MANAGER` policy values.

PortableServer::THREAD_POLICY_ID Constant

```
//IDL
const CORBA::PolicyType THREAD_POLICY_ID = 16;
```

Defines an ID for the policy `ThreadPolicy`.

PortableServer::ThreadPolicyValue Enumeration

```
//IDL
enum ThreadPolicyValue {
    ORB_CTRL_MODEL,
    SINGLE_THREAD_MODEL
};
```

One of the following values can be supplied when creating a `ThreadPolicy` policy.

ORB_CTRL_MODEL

The ORB is responsible for assigning requests for an ORB-controlled POA to threads. In a multi-threaded environment, concurrent requests may be delivered using multiple threads.

SINGLE_THREAD_MODEL

Requests for a single-threaded POA are processed sequentially. In a multi-threaded environment, all up-calls made by this POA to implementation code (servants and servant managers) are made in a manner that is safe for code that is multi-thread-unaware

In some environments, using a value of `SINGLE_THREAD_MODEL` may mean that the POA will use only the main thread, in which case the application programmer is responsible to ensure that the main thread is given to the ORB, using `ORB::perform_work()` or `ORB::run()`. POAs using a value of `SINGLE_THREAD_MODEL` may need to cooperate to ensure that calls are safe even when a servant manager is shared by multiple single-threaded POAs. These models presume that the ORB and the application are using compatible threading primitives in a multi-threaded environment.

PortableServer::AdapterActivator Interface

Adapter activators are associated with POAs. An adapter activator supplies a POA with the ability to create child POAs on demand, as a side-effect of receiving a request that names the child POA (or one of its children), or when `find_POA()` is called with an activate parameter value of TRUE. An application server that creates all its needed POAs at the beginning of execution does not need to use or provide an adapter activator; it is necessary only for the case in which POAs need to be created during request processing.

While a request from the POA to an adapter activator is in progress, all requests to objects managed by the new POA (or any descendant POAs) will be queued. This serialization allows the adapter activator to complete any initialization of the new POA before requests are delivered to that POA.

```
// IDL
interface AdapterActivator {
    boolean [unknown_adapter](#portableserveradapteractivator-interface)(
        in POA Parent,
        in string name);
};
```

AdapterActivator::unknown_adapter()

```
//IDL
boolean
unknown_adapter(
    in POA parent,
    in string name
);
//C++
virtual CORBA::Boolean unknown_adapter(
    POA_ptr parent,
    const char* name
) = 0;
```

Recreates a POA name through the adapter activator of its parent POA. This method returns either true or false:

True

The required POA is created; the ORB continues processing the request.

False

Parameters

`parent`

The parent POA.

`name`

The new name for the POA.

This method is called on the parent POA's adapter activator when the ORB receives a request for an object reference whose POA does not exist. If the POA of the requested object has ancestor POAs that also no longer exist, the ORB calls this method on the adapter activator of each POA that must be recreated. The ORB iterates over the ancestral tree of the missing POA, starting with the most immediate existing ancestor—that is, the parent of the first missing POA. For each missing child POA (specified in parameter `name`), the ORB invokes this method on its parent's adapter activator until `name` resolves to the POA that contains the requested object reference.

For example, the ORB might seek an object reference in POA *x*, where *x* is descended from POA *b*, which in turn is a child of the root POA. If *b* and *x* no longer exist, the ORB must restore both POAs in order to recreate the context of the target object reference. By evaluating the object reference, it determines which POAs it needs to restore and calls `unknown_adapter()` on each one's parent:

1. Calls `unknown_adapter()` on the adapter activator of the root POA to recreate POA *b*.
2. If the first call to `unknown_adapter()` returns TRUE, the ORB calls `unknown_adapter()` on POA *b*'s adapter activator in order to recreate POA *x*.

Until this method returns, all requests to objects managed by the POAs that it creates are queued. If `unknown_adapter()` returns FALSE, ART replies to all queued requests with `OBJECT_NOT_EXIST`.

Note

`POA::find_POA()` calls this method if the POA to be found does not exist and its `activate_it` parameter is set to TRUE. If `unknown_adapter()` creates the POA and returns TRUE, `find_POA()` returns the required POA.

Exceptions

`OBJECT_NOT_EXIST`

Raised by the ORB to the client if the parent of a POA that needs to be recreated does not have an adapter activator.

`OBJ_ADAPTER`

Raised by the ORB if the adapter activator raises a system exception.

See Also `PortableServer::POA::find_POA()`

PortableServer::DynamicImplementation Class

In C++, DSI servants inherit from the standard `DynamicImplementation` class. This class inherits from the `ServantBase` class and is also defined in the `PortableServer` namespace. The Dynamic Skeleton Interface (DSI) is implemented through servants that are members of classes that inherit from dynamic skeleton classes.

```
// C++
namespace PortableServer {
class DynamicImplementation : public virtual ServantBase {
public:
CORBA::Object_ptr [_this()](#portableserverdynamicimplementation-class);
virtual void [invoke](#portableserverdynamicimplementation-class)
(CORBA::ServerRequest_ptr request) = 0;
virtual CORBA::RepositoryId [_primary_interface]
(#portableserverdynamicimplementation-class)(
const ObjectId& oid,
POA_ptr poa
) = 0;
};
}
```

`DynamicImplementation::invoke()`

//C++

```
virtual void invoke(
CORBA::ServerRequest_ptr request
) = 0;
```

The `invoke()` method receives requests issued to any CORBA object incarnated by the DSI servant and performs the processing necessary to execute the request.

The `invoke()` method should only be invoked by the POA in the context of serving a CORBA request. Invoking this method in other circumstances may lead to unpredictable results.

`DynamicImplementation::_primary_interface()`

```
virtual CORBA::RepositoryId _primary_interface(
    const ObjectId& oid,
    POA_ptr poa
) = 0;
```

The `_primary_interface()` method returns a valid `RepositoryId` representing the most-derived interface for that `oid`.

Parameters

`oid`

An object identifier.

`poa`

A POA reference

The `_primary_interface()` method should only be invoked by the POA in the context of serving a CORBA request. Invoking this method in other circumstances may lead to unpredictable results.

`DynamicImplementation::_this()`

`CORBA::Object_ptr _this();`

The `_this()` method returns a `CORBA::Object_ptr` for the target object. Unlike `_this()` for static skeletons, its return type is not interface-specific because a DSI servant may very well incarnate multiple CORBA objects of different types.

Exceptions

`PortableServer::WrongPolicy`

`DynamicImplementation::_this()` is invoked outside of the context of a request invocation on a target object being served by the DSI servant.

PortableServer::IdAssignmentPolicy Interface

You obtain an `IdAssignmentPolicy` object by using `POA::create_id_assignment_policy()` and passing the policy to `POA::create_POA()` to specify whether `ObjectId` values in the created POA are generated by the application or by the ORB. This is a policy class derived from `CORBA::Policy`.

If no `IdAssignmentPolicy` value is specified at POA creation, the default value is `SYSTEM_ID`.

// IDL

```
interface IdAssignmentPolicy : CORBA::Policy {
    readonly attribute IdAssignmentPolicyValue value;
};
```

// C++ in namespace PortableServer

```
class IT_POA_API IdAssignmentPolicy :
public virtual ::CORBA::Policy
{
public:
    typedef PortableServer::IdAssignmentPolicy_ptr _ptr_type;
    typedef PortableServer::IdAssignmentPolicy_var _var_type;
    virtual ~IdAssignmentPolicy();
    static IdAssignmentPolicy_ptr _narrow(
CORBA::Object_ptr obj
    );
    static IdAssignmentPolicy_ptr _unchecked_narrow(
CORBA::Object_ptr obj
    );
    inline static IdAssignmentPolicy_ptr _duplicate(
IdAssignmentPolicy_ptr p
    );
    inline static IdAssignmentPolicy_ptr _nil();
    virtual IdAssignmentPolicyValue value() = 0;
    static const IT_FWString _it_fw_type_id;
};
```

See [About Standard Functions for all Interfaces](#) for descriptions of the standard helper functions.

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`IdAssignmentPolicy::value()`

`//C++`

```
virtual IdAssignmentPolicyValue value() = 0;
```

Returns the value of this POA policy.

PortableServer::IdUniquenessPolicy Interface

You obtain an `IdUniquenessPolicy` object by using `POA::create_id_uniqueness_policy()` and passing the policy to `POA::create_POA()` to specify whether the servants activated in the created POA must have unique object identities. This is a policy class derived from `CORBA::Policy`.

If no `IdUniquenessPolicy` value is specified at POA creation, the default value is `UNIQUE_ID`.

// IDL

```
interface IdUniquenessPolicy : CORBA::Policy {
    readonly attribute IdUniquenessPolicyValue value;
};
```

// C++ in namespace PortableServer

```
class IT_POA_API IdUniquenessPolicy :
public virtual ::CORBA::Policy
{
public:
    typedef PortableServer::IdUniquenessPolicy_ptr _ptr_type;
    typedef PortableServer::IdUniquenessPolicy_var _var_type;
    virtual ~IdUniquenessPolicy();
    static IdUniquenessPolicy_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static IdUniquenessPolicy_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static IdUniquenessPolicy_ptr _duplicate(
        IdUniquenessPolicy_ptr p
    );
    inline static IdUniquenessPolicy_ptr _nil();
    virtual IdUniquenessPolicyValue value() = 0;
    static const IT_FWString _it_fw_type_id;
};
```

See [About Standard Functions for all Interfaces](#) for descriptions of the standard helper functions.

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`IdUniquenessPolicy::value()`

`//C++`

```
virtual IdUniquenessPolicyValue value() = 0;
```

Returns the value of this POA policy.

PortableServer::ImplicitActivationPolicy Interface

You obtain an `ImplicitActivationPolicy` object by using `POA::create_implicit_activation_policy()` and passing the policy to `POA::create_POA()` to specify whether implicit activation of servants is supported in the created POA. This is a policy class derived from `CORBA::Policy`.

If no `ImplicitActivationPolicy` value is specified at POA creation, the default value is `NO_IMPLICIT_ACTIVATION`.

// IDL

```
interface ImplicitActivationPolicy : CORBA::Policy {
    readonly attribute ImplicitActivationPolicyValue value;
};
```

// C++ in namespace PortableServer

```
class IT_POA_API ImplicitActivationPolicy :
public virtual ::CORBA::Policy
{
public:
    typedef PortableServer::ImplicitActivationPolicy_ptr _ptr_type;
    typedef PortableServer::ImplicitActivationPolicy_var _var_type;
    virtual ~ImplicitActivationPolicy();
    static ImplicitActivationPolicy_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static ImplicitActivationPolicy_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static ImplicitActivationPolicy_ptr _duplicate(
        ImplicitActivationPolicy_ptr p
    );
    inline static ImplicitActivationPolicy_ptr _nil();
    virtual ImplicitActivationPolicyValue value() = 0;
    static const IT_FWString _it_fw_type_id;
};
```

See [About Standard Functions for all Interfaces](#) for descriptions of the standard helper functions.

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`ImplicitActivationPolicy::value()`

`//C++`

```
virtual ImplicitActivationPolicyValue value() = 0;
```

Returns the value of this POA policy.

PortableServer::POA Interface

A `POA` object manages the implementation of a collection of objects. The `POA` supports a name space for the objects, which are each identified by an `ObjectId`. A `PPOAOA` also provides a name space for POAs. A `POA` is created as a child of an existing POA, which forms a hierarchy starting with the root POA.

//IDL

```

interface POA {
exception [AdapterAlreadyExists](#portableserverpoa-interface) {};
exception {};
exception {};
exception { unsigned short index; };
exception {};
exception {};
exception {};
exception {};
exception {};
exception {};
exception {};
//-----
// POA creation and destruction
//-----
POA [create_POA](#portableserverpoa-interface)(
in string adapter_name,
in POAManager a_POAManager,
in CORBA::PolicyList policies
)
raises (AdapterAlreadyExists, InvalidPolicy);
POA [find_POA](#portableserverpoa-interface)(
in string adapter_name,
in boolean activate_it
)
raises (AdapterNonExistent);
void [destroy](#portableserverpoa-interface)(
in boolean etherealize_objects,
in boolean wait_for_completion
);
// *****
// Factories for Policy objects
// *****
ThreadPolicy [create_thread_policy](#portableserverpoa-interface)(
in ThreadPolicyValue value
);
LifespanPolicy [create_lifespan_policy](#portableserverpoa-interface)(
in LifespanPolicyValue value
);
IdUniquenessPolicy [create_id_uniqueness_policy](#portableserverpoa-
interface)(
in IdUniquenessPolicyValue value
);
IdAssignmentPolicy [create_id_assignment_policy](#portableserverpoa-
interface)(
in IdAssignmentPolicyValue value

```

```

);
ImplicitActivationPolicy [create_implicit_activation_policy]
(#portableserverpoa-interface)(
in ImplicitActivationPolicyValue value
);
ServantRetentionPolicy [create_servant_retention_policy](#portableserverpoa-
interface)(
in ServantRetentionPolicyValue value
);
RequestProcessingPolicy [create_request_processing_policy]
(#portableserverpoa-interface)(
in RequestProcessingPolicyValue value
);
//-----
// POA attributes
//-----
readonly attribute string [the_name](#portableserverpoa-interface);
readonly attribute POA [the_parent](#portableserverpoa-interface);
readonly attribute POAManager [the_POAManager](#portableserverpoa-interface);
attribute AdapterActivator [the_activator](#portableserverpoa-interface);
//-----
// Servant Manager registration
//-----
ServantManager [get_servant_manager](#portableserverpoa-interface)()
raises (WrongPolicy);
void [set_servant_manager](#portableserverpoa-interface)(in ServantManager
imgr)
raises (WrongPolicy);
//-----
// operations for the USE_DEFAULT_SERVANT policy
//-----
Servant [get_servant](#portableserverpoa-interface)()
raises (NoServant, WrongPolicy);
void [set_servant](#portableserverpoa-interface)(in Servant servant)
raises (WrongPolicy);
// *****
// object activation and deactivation
// *****
ObjectId [activate_object](#portableserverpoa-interface)(in Servant servant)
raises (ServantAlreadyActive, WrongPolicy);
void [activate_object_with_id](#portableserverpoa-interface)(
in ObjectId id,
in Servant servant
)
raises(
ServantAlreadyActive,
ObjectAlreadyActive,

```

```

WrongPolicy
);
void [deactivate_object](#portableserverpoa-interface)(in ObjectId oid)
raises (ObjectNotActive, WrongPolicy);
// *****
// reference creation operations
// *****
Object [create_reference](#portableserverpoa-interface)(in
CORBA::RepositoryId intf)
raises (WrongPolicy);
Object [create_reference_with_id](#portableserverpoa-interface)(
in ObjectId oid,
in CORBA::RepositoryId intf
)
//-----
// Identity mapping operations
//-----
ObjectId [servant_to_id](#portableserverpoa-interface)(in Servant servant)
raises (ServantNotActive, WrongPolicy);
Object [servant_to_reference](#portableserverpoa-interface)(in Servant
servant)
raises (ServantNotActive, WrongPolicy);
Servant [reference_to_servant](#portableserverpoa-interface)(in Object
reference)
raises (ObjectNotActive, WrongAdapter, WrongPolicy);
ObjectId [reference_to_id](#portableserverpoa-interface)(in Object reference)
raises (WrongAdapter, WrongPolicy);
Servant [id_to_servant](#portableserverpoa-interface)(in ObjectId oid)
raises (ObjectNotActive, WrongPolicy);
Object [id_to_reference](#portableserverpoa-interface)(in ObjectId oid)
raises (ObjectNotActive, WrongPolicy);
};

```

The exceptions defined for the POA class consist of the following:

```

AdapterAlreadyExists
AdapterInactive
AdapterNonExistent
InvalidPolicy
NoServant
ObjectAlreadyActive
ObjectNotActive
ServantAlreadyActive
ServantNotActive
WrongAdapter
WrongPolicy

```

The POA methods are described as follows:

POA::activate_object()

//IDL

```

ObjectId activate_object(in Servant servant)
raises(ServantAlreadyActive, WrongPolicy);

```

//C++

```

virtual ObjectId* activate_object(
    Servant servant
) = 0;

```

Returns a system-generated object ID and associates it with `servant` in the POA's active object map. This method `can` only be issued in a POA that has policies of `SYSTEM_ID` and `RETAIN`; otherwise, it raises an exception of `WrongPolicy`.

If the specified servant is already in the active object map and the POA has the `UNIQUE_ID` policy, the `ServantAlreadyActive` exception is raised.

Exceptions `ServantAlreadyActive`, `WrongPolicy`

See Also `PortableServer::POA::deactivate_object()`

POA::activate_object_with_id()

//IDL


```
void activate_object_with_id(
in ObjectId oid,
in Servant servant
)
raises (
ObjectAlreadyActive,
ServantAlreadyActive,
WrongPolicy);
```

//C++

```
virtual void
activate_object_with_id(
const ObjectId & id,
Servant servant
) = 0;
```

Associates object `oid` with servant `servant` in the POA's active object map. This method can only be issued in a POA that has the `RETAIN` policy.

If you call `activate_object_with_id()` on a POA that has a policy of `SYSTEM_ID` policy, the object ID must be generated by that POA. To get the object ID of a system-generated object reference, call `reference_to_id()`.

Exceptions

ObjectAlreadyActive

Object `oid` is already active in this POA—that is, it is associated with a servant in the active object map.

ServantAlreadyActive

The POA has the `UNIQUE_ID` policy and the servant is already associated with another object.

WrongPolicy

The POA has the `NON_RETAIN` policy.

`POA::create_id_assignment_policy()`

//IDL

```
IdAssignmentPolicy create_id_assignment_policy(
in IdAssignmentPolicyValue value
);
```

//C++

```
virtual IdAssignmentPolicy_ptr create_id_assignment_policy(
IdAssignmentPolicyValue value
) = 0;
```

Creates an object of the `IdAssignmentPolicy` interface. This object can be added to the policies list (`CORBA::PolicyList`) of a new POA. The ID assignment policy determines whether object IDs are generated by the POA or the application.

Parameters Specify the POA's ID assignment policy by supplying one of these values for the `value` parameter:

SYSTEM_ID: (default) Only the POA can assign IDs to its objects. If the POA's lifespan policy is set to `PERSISTENT`, object IDs are unique across all instantiations of the same POA.

USER_ID: Only the application can assign object IDs to objects in this POA. The application must ensure that all user-assigned IDs are unique across all instantiations of the same POA.

Typically, a POA with a `SYSTEM_ID` policy manages objects that are active for only a short period of time, and so do not need to outlive their server process. In this case, the POA also has an object lifespan policy of `TRANSIENT`.

`USER_ID` is usually assigned to a POA that has an object lifespan policy of `PERSISTENT`—that is, it generates object references whose validity can span multiple instantiations of a POA or server process, so the application requires explicit control over object IDs.

See Also `PortableServer::POA::create_poa()`

`POA::create_id_uniqueness_policy()`

//IDL

```
IdUniquenessPolicy create_id_uniqueness_policy(
in IdUniquenessPolicyValue value
);
```

//C++

```
virtual IdUniquenessPolicy_ptr create_id_uniqueness_policy(
    IdUniquenessPolicyValue value
) = 0;
```

Creates an object of the `IdUniquenessPolicy` interface. This object can be added to the policies list (`CORBA::PolicyList`) of a new POA. The ID uniqueness policy determines whether a servant can be associated with multiple objects in this POA.

Parameters Specify the POA's ID uniqueness policy by supplying one of these values for the value parameter:

UNIQUE_ID: (default) Each servant in the POA can be associated with only one object ID.

MULTIPLE_ID: Any servant in the POA can be associated with multiple object IDs.

Note

If the same servant is used by different POAs, that servant conforms to the uniqueness policy of each POA. Thus, it is possible for the same servant to be associated with multiple objects in one POA, and be restricted to one object in another.

See Also `PortableServer::POA::create_poa()`

`POA::create_implicit_activation_policy()`

//IDL

```
ImplicitActivationPolicy create_implicit_activation_policy(
    in ImplicitActivationPolicyValue value
);
```

//C++

```
virtual ImplicitActivationPolicy_ptr create_implicit_activation_policy(
    ImplicitActivationPolicyValue value
) = 0;
```

Creates an object of the **ImplicitActivationPolicy** interface. This object can be added to the policies list (`CORBA::PolicyList`) of a new POA. The activation policy determines whether the POA supports implicit activation of servants.

Parameters Specify the POA's activation policy by supplying one of these values for the `value` parameter:

NO_IMPLICIT_ACTIVATION: (default) The POA only supports explicit activation of servants.

IMPLICIT_ACTIVATION: The POA supports implicit activation of servants. This policy requires that the POA's object ID assignment policy be set to `SYSTEM_ID`, and its servant retention policy be set to `RETAIN`.

See Also `PortableServer::POA::create_poa()`

```
PortableServer::POA::create_id_assignment_policy
PortableServer::POA::create_servant_retention_policy
```

`POA::create_lifespan_policy()`

//IDL

```
LifespanPolicy create_lifespan_policy(
in LifespanPolicyValue value
);
```

//C++

```
virtual LifespanPolicy_ptr create_lifespan_policy(
LifespanPolicyValue value
) = 0;
```

Creates an object of the **LifespanPolicyValue** interface. This object can be added to the policies list (`CORBA::PolicyList`) of a new POA. The lifespan policy determines whether object references outlive the process in which they were created.

Parameters Specify the POA's lifespan policy by supplying one of these values for the `value` parameter:

TRANSIENT: (default) Object references do not outlive the POA in which they are created. After a transient object's POA is deactivated, attempts to reference this object yield the exception

`CORBA::OBJECT_NOT_EXIST`.

PERSISTENT: Object references can outlive the POA in which they are created.

When a POA creates an object reference, it encapsulates it within an IOR. If the POA has a `TRANSIENT` policy, the IOR contains the server process's current location—its host address and port. Consequently, that object reference is valid only as long as the server process remains alive. If the server process dies, the object reference becomes invalid.

If the POA has a `PERSISTENT` policy, the IOR contains the address of the location domain's implementation repository, which maps all servers and their POAs to their current locations. Given a request for a persistent object, the Orbix daemon uses the object's "virtual" address first, and looks up the server process's actual location via the implementation repository.

A POA typically correlates its lifespan and ID assignment policies. `TRANSIENT` and `SYSTEM_ID` are the default settings for a new POA, out of recognition that system-assigned ID's are generally sufficient for transient object references.

`PERSISTENT` and `USER_ID` policies are usually set together, inasmuch as an application typically requires explicit control over the object IDs of its persistent object references.

See Also `PortableServer::POA::create_poa()`

```
PortableServer::AdapterActivator::unknown_adapter()
```

`POA::create_POA()`

//IDL

```
POA create_POA(
    in string adapter_name,
    in POAManager a_POAManager,
    in CORBA::PolicyList policies
)
raises(AdapterAlreadyExists, InvalidPolicy);
```

//C++

```
virtual POA_ptr create_POA(
    const char* adapter_name,
    POAManager_ptr a_POAManager,
    const CORBA::PolicyList & policies
) = 0;
```

Creates a portable object adapter (POA). An application calls this method on the parent of the new POA. The name of the new POA `adapter_name` must be unique among the names of all existing sibling POAs.

You control a POA's behavior through the policy objects that are created and attached to it through the policies parameter. A new POA has the following policy defaults:

Table 24: Policy Defaults for POAs

Policy	Default Setting
IdAssignmentPolicy	SYSTEM_ID
IdUniquenessPolicy	UNIQUE_ID
ImplicitActivationPolicy	NO_IMPLICIT_ACTIVATION
LifespanPolicy	TRANSIENT
RequestProcessingPolicy	USE_ACTIVE_OBJECT_MAP_ONLY
ServantRetentionPolicy	RETAIN
ThreadPolicy	ORB_CTRL_MODEL

Policy objects are copied to the POA before this operation returns, so the application can destroy them while the POA is in use.

You can register either an existing POA manager or a new one with the POA through the `a_POAManager` parameter. If `a_POAManager` is null, a new `POAManager` object is registered with the POA. To obtain the `POAManager` object of the current POA, call `PortableServer::the_POAManager()`.

When you create a POA, it is in the state of its POA manager—typically, either active or holding. If you create a new POA manager with the POA, it is initially in a holding state. To process requests, it must be put into an active state through `PortableServer::POAManager::activate()`.

If you register an existing manager with the new POA and the manager is in an active state, the new POA might receive requests for objects before it is prepared to process them—that is, before its adapter activator, servant manager, or default servant is initialized. You can avoid this problem in one of these ways:

- Create the POA indirectly through its parent's adapter activator. For example, call `find_POA()` on the new POA's parent, supplying parameters `adapter_name` and `activate_it` arguments of the new (non-existent) POA and TRUE. Orbix queues all incoming requests on the new POA until the adapter activator returns on successful initialization of the POA.
- Before creating the POA, set its manager to a holding state through `PortableServer::POAManager::hold_requests()`.

Exceptions

AdapterAlreadyExists

The parent POA already has a child POA with the specified name.

InvalidPolicy

Raised for one of these reasons:

- A policy object is not valid for the ORB implementation.
- Conflicting policy objects are specified—for example, `NON_RETAIN` and `USE_ACTIVE_OBJECT_MAP_ONLY`.

The exception index number specifies the first offending policy object through the corresponding index in the policies parameter.

POA::create_reference()

//IDL

```
Object create_reference(
in CORBA::RepositoryId intf
)
```

//C++

```
virtual CORBA::Object_ptr create_reference(
CORBA::RepositoryId const char* intf
) = 0;
```

Creates a CORBA object and returns an object reference. The object reference encapsulates a POA-generated object ID value and the specified interface repository ID. This reference can be passed to clients so it can make requests on the corresponding object.

This operation requires the `SYSTEM_ID` policy. To obtain the generated object ID value call `POA::reference_to_id()` with the created reference. The returned object ID can then be used to associate the servant with an object (and thereby activate the object) by calling

`activate_object_with_id()`.

See Also `PortableServer::POA::create_reference_with_id`

POA::create_reference_with_id()

//IDL

```
Object create_reference_with_id(
in ObjectId oid,
in CORBA::RepositoryId intf
)
```

```
//C++
```

```
virtual CORBA::Object_ptr create_reference_with_id(
const ObjectId & oid,
CORBA::RepositoryId const char* intf
) = 0;
```

Returns an object reference that encapsulates the specified object and interface repository identifiers. The resulting reference can be returned to clients to initiate requests on that object.

See Also `PortableServer::POA::create_reference`

`POA::create_request_processing_policy()`

```
//IDL
```

```
RequestProcessingPolicy create_request_processing_policy(
in RequestProcessingPolicyValue value
);
```

```
//C++
```

```
virtual RequestProcessingPolicy_ptr
create_request_processing_policy(
RequestProcessingPolicyValue value
) = 0;
```

Creates an object of the `RequestProcessingPolicy` interface. This object can be added to the policies list (`CORBA::PolicyList`) of a new POA. This policy determines how the POA finds servants to implement requests.

Specify the POA's request processing policy by supplying one of these values:

- `USE_ACTIVE_OBJECT_MAP_ONLY` (default): Assumes that all object IDs are mapped to a servant in the active object map. The active object map maintains an object-servant mapping until the object is explicitly deactivated through `deactivate_object()`. This policy is typically used for a POA that processes requests for a small number of objects. If the object ID is not found in the active object

map, an `OBJECT_NOT_EXIST` exception is raised to the client. This policy requires that the POA have a servant retention policy of `RETAIN`.

- `USE_DEFAULT_SERVANT` : Dispatch requests to the default servant when the POA cannot find a servant for the requested object. This can occur because the object's ID is not in the active object map, or the POA's servant retention policy is set to `NON_RETAIN`. This policy is typically used for a POA that needs to process many objects that are instantiated from the same class, and thus can be implemented by the same servant. This policy requires that the application register a default servant with the POA via `set_servant()`; otherwise, an `OBJ_ADAPTER` exception is raised to the client. It also requires the POA's ID uniqueness policy be set to `MULTIPLE_ID`, so multiple objects can use the default servant.
- `USE_SERVANT_MANAGER` : The POA's servant manager finds a servant for the requested object when the object's ID is not in the active object map, or when the POA's servant retention policy is set to `NON_RETAIN`. If the servant manager fails to locate a servant, it raises an exception. This policy requires that the application register a servant manager with the POA via `set_servant_manager()`; otherwise, an `OBJ_ADAPTER` exception is returned to the client.

An application can implement either a servant activator or servant locator as a POA's servant manager, according to the POA's servant retention policy:

- " A POA with a policy of `RETAIN` can register a servant activator. The servant activator incarnates servants for inactive objects on request; these objects remain active until the servant activator etherealizes them.
- " A POA with a policy of `NON_RETAIN` can register a servant locator. The servant locator incarnates a servant for an inactive object each time the object is requested; the servant locator must etherealize the object and delete the servant from memory after the request returns.
- " A POA with a of `USE_SERVANT_MANAGER` policy allows the application to manage object activation directly.

See Also `PortableServer::POA::create_poa()`

```
PortableServer::POA::create_servant_retention_policy
PortableServer::POA::create_id_uniqueness_policy
```

`POA::create_servant_retention_policy()`

//IDL

```
ServantRetentionPolicy create_servant_retention_policy(
in ServantRetentionPolicyValue value
);
```

```
//C++
```

```
virtual ServantRetentionPolicy_ptr
create_servant_retention_policy(
ServantRetentionPolicyValue value
) = 0;
```

Creates an object of the `ServantRetentionPolicy` interface. This object can be added to the policies list (`CORBA::PolicyList`) of a new POA. This policy determines whether the POA has an active object map to maintain servant-object associations.

Parameters Specify the servant retention policy by supplying one of these arguments for the `value` parameter:

RETAIN: (default) The POA retains active servants in its active object map. If combined with a policy of `USE_SERVANT_MANAGER`, the POA uses a servant activator as its servant manager.

NON_RETAIN: The POA has no active object map. For each request, the POA relies on the servant manager or default servant to map between an object and its servant; all mapping information is destroyed when request processing returns. Therefore, a `NON_RETAIN` policy also requires that the POA have a request processing policy of `USE_DEFAULT_SERVANT` or `USE_SERVANT_MANAGER`.

See Also `PortableServer::POA::create_poa()`

```
PortableServer::POA::create_request_processing_policy()
```

```
POA::create_thread_policy()
```

```
//IDL
```

```
ThreadPolicy create_thread_policy(
in ThreadPolicyValue value
);
```

```
//C++
```

```
virtual ThreadPolicy_ptr create_thread_policy(
    ThreadPolicyValue value
) = 0;
```

Creates an object of the `ThreadPolicy` interface. This object can be added to the policies list (`CORBA::PolicyList`) of a new POA.

Parameters Specify the POA's thread policy by supplying one of these values for the `value` parameter:

ORB_CTRL_MODEL: (default) The ORB is responsible for assigning requests for an ORB-controlled POA to threads. In a multi-threaded environment, concurrent requests can be delivered using multiple threads.

SINGLE_THREAD_MODEL: Requests for a single-threaded POA are processed sequentially. In a multi-threaded environment, all calls by a single-threaded POA to implementation code (servants and servant managers) are made in a manner that is safe for code that does not account for multi-threading.

Orbix uses the main thread for a single-threaded POA. In this case, make sure that the main thread is given to the ORB via `ORB::perform_work()` or `ORB::run()`. Multiple single-threaded POAs might need to cooperate to ensure that calls are safe when they share implementation code such as a servant manager.

Both threading policies assume that the ORB and the application are using compatible threading primitives in a multi-threaded environment. All uses of the POA within the server must conform to its threading policy.

See Also `PortableServer::POA::create_poa()`

`POA::deactivate_object()`

//IDL

```
void deactivate_object(
    in ObjectId oid
)
raises(ObjectNotActive, WrongPolicy);
```

//C++

```
virtual void
deactivate_object(
const ObjectId & oid
) = 0;
```

Deactivates object `oid` by removing its servant association from the active object map. Call this method only for a POA with a `RETAIN` policy. If the POA has policies of `RETAIN` and `USE_SERVANT_MANAGER`, it calls the servant activator's `etherealize()` method. `deactivate_object()` returns immediately after its call to `etherealize()`.

Exceptions

`ObjectNotActive`

The specified object ID is not associated with a servant.

`WrongPolicy`

The POA has a `NON_RETAIN` policy.

`POA::destroy()`

//IDL

```
void destroy(
in boolean etherealize_objects
in boolean wait_for_completion
);
```

//C++

```
virtual void destroy(
CORBA::Boolean etherealize_objects,
CORBA::Boolean wait_for_completion
) = 0;
```

Destroys the target POA and all its descendant POAs. A POA thus destroyed can be recreated later on the same server process.

When a POA is destroyed, requests that already began execution on it or its descendants continue to completion. Requests that have not started execution are processed as if they were newly arrived—that is, the ORB tries to recreate the destroyed POA after all of its pending requests have finished processing.

`etherealize_objects` can be set to `TRUE` for a POA that has policies of `RETAIN` and `USE_SERVANT_MANAGER`. This parameter determines whether to call the servant activator's

`etherealize()` method on each active object. Orbix perceives the POA to be destroyed, and therefore unavailable to requests, before any calls to `etherealize()` are made.

If `wait_for_completion` is set to `TRUE`, `destroy()` returns only after all requests in process and all calls to `etherealize()` return. If set to `FALSE`, `destroy()` returns after destroying the target POAs.

See Also `PortableServer::POAManager::deactivate()`

`POA::find_POA()`

//IDL

```
POA find_POA(
in string adapter_name,
in boolean activate_it
)
raises(AdapterNonExistent);
```

//C++

```
virtual POA_ptr find_POA(
const char* adapter_name,
CORBA::Boolean activate_it
) = 0;
```

Returns a pointer to POA `adapter_name` if it is a child of the target POA. If the target POA has no child of the specified name and `activate_it` is set to `TRUE`, `find_POA()` invokes the target POA's adapter activator, if one exists. The adapter activator attempts to restore POA `adapter_name`; if successful, `find_POA()` returns the specified POA object.

Exceptions `AdapterNonExistent` No POA is returned

See Also `PortableServer::AdapterActivator::unknown_adapter()`

`POA::get_servant()`

//IDL

```
Servant get_servant()
raises(NoServant, WrongPolicy);
```

//C++

```
virtual Servant get_servant() = 0;
```

Returns the POA's default servant. This method can only be called on a POA that has the `USE_DEFAULT_SERVANT` policy.

Exceptions

`NoServant`

No default servant is associated with the POA.

`WrongPolicy`

The POA should have the `USE_DEFAULT_SERVANT` policy.

POA::get_servant_manager()

//IDL

```
ServantManager get_servant_manager()
raises(WrongPolicy);
```

//C++

```
virtual ServantManager_ptr get_servant_manager() = 0;
```

Returns the POA's servant manager. If no servant manager is associated with the POA, the method returns a null reference.

See Also `PortableServer::AdapterActivator::set_servant_manager()`

POA::id_to_reference()

//IDL

```
Object id_to_reference(
in ObjectId oid
)
raises(ObjectNotActive, WrongPolicy);
```

//C++

```
virtual CORBA::Object_ptr id_to_reference(
const ObjectId & oid
) = 0;
```

Returns an object reference for active object `oid`. The object reference encapsulates the information used to direct requests to this object.

Exceptions

`WrongPolicy`

The POA has the `NON_RETAIN` policy.

`ObjectNotActive`

The active object map does not contain the specified object ID.

POA::id_to_servant()

//IDL

```
Servant id_to_servant(
in ObjectId oid
)
raises(ObjectNotActive, WrongPolicy);
```

//C++

```
virtual Servant id_to_servant(
const ObjectId & oid
) = 0;
```

Returns the servant that is associated with object ID `oid` in the active object map. This method call is valid only for a POA with a `RETAIN` policy.

Exceptions

`WrongPolicy`

The POA has the `NON_RETAIN` policy.

`ObjectNotActive`

The POA's active object map does not contain the specified object ID.

POA::reference_to_id()

//IDL

```

ObjectId reference_to_id(
in Object reference
)
raises WrongAdapter, WrongPolicy);

```

//C++

```

virtual ObjectId* reference_to_id(
CORBA::Object_ptr reference
) = 0;

```

Returns the object ID that is encapsulated by the specified object reference, where `reference` can specify an active or inactive object. Call this method only if the target POA created `reference`.

Exceptions

`WrongAdapter`

The object reference was not created by this POA.

`WrongPolicy`

Reserved for future extensions.

POA::reference_to_servant()

//IDL

```

Servant
reference_to_servant(
in Object reference
)
raises(ObjectNotActive, WrongAdapter, WrongPolicy);

```

//C++

```

virtual Servant reference_to_servant(
CORBA::Object_ptr reference
) = 0;

```

Returns the servant that incarnates the reference-specified object if one of these conditions is true:

- The POA has a policy of `RETAIN` and the specified object is in the active object map.
- The POA has the `USE_DEFAULT_SERVANT` policy and a default servant is registered with the POA.

Exceptions

ObjectNotActive

The POA policies are correct but no servant is associated with the specified object.

WrongAdapter

The object reference was not created by this POA.

WrongPolicy

The POA does not have a policy of either `RETAIN` or `USE_DEFAULT_SERVANT`.

`POA::servant_to_id()`

//IDL

```
ObjectId
servant_to_id(
in Servant servant
)
raises(ServantNotActive, WrongPolicy);
```

//C++

```
virtual ObjectId* servant_to_id(
Servant servant
) = 0;
```

Returns an object ID for an object that is incarnated by `servant`.

Depending on the POA's policies, the method can take one of the following actions:

- Returns the ID of an already active object if the POA has the `UNIQUE_ID` policy and `servant` already incarnates an object.
- Associates `servant` with a POA-generated object ID and returns that ID if the POA has the `IMPLICIT_ACTIVATION` policy and one of these conditions is true:
 - " The POA has the `MULTIPLE_ID` policy.
 - " `servant` is not associated with any object.

Exceptions

WrongPolicy

The POA must have policies of `RETAIN` and either `UNIQUE_ID` or `IMPLICIT_ACTIVATION`; otherwise, it raises this exception. For example, if a POA has a policy of `RETAIN`, `NO_IMPLICIT_ACTIVATION`, and

`MULTIPLE_ID`, `servant_to_id()` cannot tell which of the objects that this servant potentially incarnates it should return.

ServantNotActive

`servant` is not associated with any object and the POA has a `NO_IMPLICIT_ACTIVATION` policy; therefore, no activation occurs.

`POA::servant_to_reference()`

//IDL

```
Object servant_to_reference(
in Servant servant
)
raises (ServantNotActive, WrongPolicy);
```

//C++

```
virtual CORBA::Object_ptr servant_to_reference(
Servant servant
) = 0;
```

Returns an object reference for an object that is incarnated by `servant`.

Depending on the POA's policies, the method can take one of the following actions:

- If the POA has the `UNIQUE_ID` policy and servant already incarnates an active object, the method returns an object reference that encapsulates the information used to activate that object.
- If the POA has the `IMPLICIT_ACTIVATION` policy, and the POA has the `MULTIPLE_ID` policy or servant is not associated with any object, the servant is associated with a POA-generated object ID—thereby activating the object—and a corresponding object reference is returned.

Exceptions

`WrongPolicy`

The POA must have policies of `RETAIN` and either `UNIQUE_ID` or `IMPLICIT_ACTIVATION`; otherwise, it raises this exception. For example, if a POA has a policy of `RETAIN`, `NO_IMPLICIT_ACTIVATION`, and `MULTIPLE_ID`, `servant_to_reference()` cannot tell which of the objects that this servant potentially incarnates it should return.

ServantNotActive

`servant` is not associated with any object and the POA has a `NO_IMPLICIT_ACTIVATION` policy; therefore, no activation occurs.

`POA::set_servant()`

```
//IDL
```

```
void
set_servant(
in Servant servant
)
raises(WrongPolicy);
```

```
//C++
```

```
virtual void set_servant(
Servant servant
) = 0;
```

Registers `servant` with the POA as the default servant. This servant is used in a POA that has the `USE_DEFAULT_SERVANT` policy; it services any requests for objects that are not registered in the active object map.

Exceptions

`WrongPolicy`

The POA does not have the `USE_DEFAULT_SERVANT` policy.

POA::set_servant_manager()

```
//IDL
```

```
void set_servant_manager(
in ServantManager mgr
)
raises(WrongPolicy);
```

```
//C++
```

```
virtual void set_servant_manager(
ServantManager_ptr mgr
) = 0;
```

Sets the default servant manager for the target POA.

Exceptions

`WrongPolicy`

Raised if the POA does not have the `USE_SERVANT_MANAGER` policy.

POA::the_name()

//C++

```
virtual char* the_name() = 0;
```

Returns the name of the target POA.

POA::the_parent()

//C++

```
virtual POA_ptr the_parent() = 0;
```

Returns a pointer to the target POA's parent.

POA::the_POAManager()

//C++

```
virtual POAManager_ptr the_POAManager() = 0;
```

Returns a pointer to the target POA's manager.

POA::the_activator()

//C++

```
virtual AdapterActivator_ptr the_activator() = 0;  
virtual void the_activator(  
    AdapterActivator_ptr _the_activator  
) = 0;
```

Returns or sets a pointer to the target POA's adapter activator.

PortableServer::LifespanPolicy Interface

You obtain a `LifespanPolicy` object by using `POA::create_lifespan_policy()` and passing the policy to `POA::create_POA()` to specify the lifespan of the objects implemented in the created POA. This is a policy class derived from `CORBA::Policy`.

If no `LifespanPolicy` value is specified at POA creation, the lifespan policy value defaults to `TRANSIENT`.

// IDL

```
interface LifespanPolicy : CORBA::Policy {
    readonly attribute LifespanPolicyValue value;
};
```

// C++ in namespace PortableServer

```
class IT_POA_API LifespanPolicy :
public virtual ::CORBA::Policy
{
public:
    typedef PortableServer::LifespanPolicy_ptr _ptr_type;
    typedef PortableServer::LifespanPolicy_var _var_type;
    virtual ~LifespanPolicy();
    static LifespanPolicy_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static LifespanPolicy_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static LifespanPolicy_ptr _duplicate(
        LifespanPolicy_ptr p
    );
    inline static LifespanPolicy_ptr _nil();
    virtual LifespanPolicyValue value() = 0;
    static const IT_FWString _it_fw_type_id;
};
```

See [About Standard Functions for all Interfaces](#) for descriptions of the standard helper functions.

- `_duplicate()`

- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`LifespanPolicy::value()`

`//C++`

```
virtual LifespanPolicyValue value() = 0;
```

Returns the value of this POA policy.

PortableServer::POAManager Interface

A `POAManager` is associated with one or more POA objects. (Each POA object has an associated `POAManager` object.) A POA manager encapsulates the processing state of its POAs. Using operations on the POA manager, an application can cause requests for those POAs to be queued or discarded, and can cause the POAs to be deactivated.

POA managers are created and destroyed implicitly. Unless an explicit `POAManager` object is provided at POA creation time, a POA manager is created when a POA is created and is automatically associated with that POA. A `POAManager` object is implicitly destroyed when all of its associated POAs have been destroyed.

//IDL

```
interface POAManager {
    exception AdapterInactive{};
    enum State { HOLDING, ACTIVE, DISCARDING, INACTIVE };
    void activate()
        raises(AdapterInactive);
    void hold_requests(
        in boolean wait_for_completion)
        raises(AdapterInactive);
    void discard_requests(
        in boolean wait_for_completion)
        raises(AdapterInactive);
    void deactivate(
        in boolean etherealize_objects,
        in boolean wait_for_completion)
        raises(AdapterInactive);
    State get_state();
};
```

POAManager::activate()

//IDL

```
void
activate()
raises (AdapterInactive);
```

//C++

```
virtual void activate() = 0;
```

Changes the state of the POA manager to active so it can process requests. When a POA manager is active, all associated POAs can receive requests.

Note

A POA manager's ability to process requests is dependent on resource limits. Orbix provides queues whose lengths are configurable, and raises a system exception of `TRANSIENT` when the queues are full.

When a POA manager is created, it is initially in a holding state. All requests sent to that POA are queued until you call `activate()` on a POA's manager. `activate()` can also reactivate a POA manager that has reverted to a holding state (due to a `hold_requests()` call) or is in a discarding state (due to a `discard_requests()` call).

If a new POA is associated with an existing active POA manager, it is unnecessary to call this method. However, it is generally a good idea to put a POA manager in a holding state before creating a new POA with it.

Exceptions

AdapterInactive

This method is issued on an inactive POA manager.

See Also `PortableServer::POAManager::activate()` `PortableServer::POAManager::deactivate()`
`PortableServer::POAManager::discard_requests()` `PortableServer::POAManager::hold_requests()`

POAManager::AdapterInactive Exception

// IDL


```
exception AdapterInactive{};
```

Indicates that the `POAManager` is inactive and unable to process requests.

`POAManager::deactivate()`

//IDL

void deactivate(

```
in boolean etherealize_objects,
in boolean wait_for_completion
);
raises(AdapterInactive);
```

//C++

```
virtual void deactivate(
CORBA::Boolean etherealize_objects,
CORBA::Boolean wait_for_completion
) = 0;
```

Causes the POA manager to shut down. A POA manager deactivates before its associated POAs are destroyed. When it is in an inactive state, the POA manager allows all outstanding requests to complete processing, but refuses all incoming requests.

ParametersThe method takes two boolean parameters:

`etherealize_objects`

Determines whether the target POAs etherealize their servants after all request processing is complete. This argument applies only to POAs that have a servant retention policy of `RETAIN` and request processing policy of `USE_SERVANT_MANAGER`.

`wait_for_completion`

Determines whether the method returns immediately or waits until the completion of all requests whose processing began before the call to `deactivate()`.

Exceptions

`AdapterInactive`

This method is issued on a POA manager that is already inactive.

See Also `PortableServer::POA::destroy()`

`POAManager::discard_requests()`

//IDL

```
void discard_requests(
    in boolean wait_for_completion
)
    raises(AdapterInactive);
```

//C++

```
virtual void discard_requests(
    CORBA::Boolean wait_for_completion
) = 0;
```

Causes the POA manager to discard all incoming requests. When a request is discarded, the server raises a `TRANSIENT` system exception to the client so it can reissue the request. This method can return immediately or wait until the return of all requests whose processing had already begun, according to the argument supplied for `wait_for_completion`.

Parameters `wait_for_completion` determines whether the method returns immediately or waits until the completion of all requests whose processing began before the call.

This method is typically called when an application detects that an object or the POA in general is overwhelmed by incoming requests. A POA manager should be in a discarding state only temporarily. On resolution of the problem that required this call, the application should restore the POA manager to its active state with `activate()`.

Exceptions

`AdapterInactive`

This method is issued on an inactive POA manager.

See Also `PortableServer::POAManager::activate()` `PortableServer::POAManager::discard_requests()`

`PortableServer::POAManager::hold_requests()`

`POAManager::get_state()`

//IDL

```
State get_state();
```

```
//C++
```

```
PortableServer::POAManager::State get_state();
```

Returns the current state of the `POAManager`.

```
POAManager::hold_requests()
```

Enhancement//IDL

```
void hold_requests(
  in boolean wait_for_completion
);
raises(AdapterInactive);
```

```
//C++
```

```
virtual void hold_requests(
  CORBA::Boolean wait_for_completion
) = 0;
```

Causes all POAs associated with this manager to queue incoming requests.

The number of requests that can be queued is implementation-dependent. Set `wait_for_completion` to determine whether this method returns immediately or waits until the return of all requests whose processing began before this call.

A POA manager is always created in a holding state.

Exceptions

`AdapterInactive`

This method is issued on an inactive POA manager.

See Also `PortableServer::POAManager::activate()` `PortableServer::POAManager::deactivate()`

`PortableServer::POAManager::discard_requests()`

`POAManager::State` Enumeration

```
//IDL
```

```
enum State { HOLDING, ACTIVE, DISCARDING, INACTIVE };
```

The possible state values consist of the following:

```
HOLDING  
ACTIVE  
DISCARDING  
INACTIVE
```

PortableServer::RequestProcessingPolicy Interface

You obtain a `RequestProcessingPolicy` object by using `POA::create_request_processing_policy()` and passing the policy to `POA::create_POA()` to specify how requests are processed by the created POA. This is a policy class derived from `CORBA::Policy`.

If no `RequestProcessingPolicy` value is specified at POA creation, the default value is `USE_ACTIVE_OBJECT_MAP_ONLY`.

You can define many possible combinations of behaviors with the policies `RequestProcessingPolicy` and `ServantRetentionPolicy`.

- `RETAIN` and `USE_ACTIVE_OBJECT_MAP_ONLY`

This combination represents the situation where the POA does no automatic object activation (that is, the POA searches only the active object map). The server must activate all objects served by the POA explicitly, using either `activate_object()` or `activate_object_with_id()`.

- `RETAIN` and `USE_SERVANT_MANAGER`

This combination represents a very common situation, where there is an active object map and a `ServantManager`. Because `RETAIN` is in effect, the application can call `activate_object()` or `activate_object_with_id()` to establish known servants in the active object map for use in later requests. If the POA doesn't find a servant in the active object map for a given object, it tries to determine the servant by means of invoking `incarnate()` in the `ServantManager` (specifically a `ServantActivator`) registered with the POA. If no `ServantManager` is available, the POA raises the `OBJECT_ADAPTER` system exception.

- `RETAIN` and `USE_DEFAULT_SERVANT`

This combination represents the situation where there is a default servant defined for all requests involving unknown objects. Because `RETAIN` is in effect, the application can call `activate_object()` or `activate_object_with_id()` to establish known servants in the active object map for use in later requests. The POA first tries to find a servant in the active object map for a given object. If it does not find such a servant, it uses the default servant. If no default servant is available, the POA raises the `OBJECT_ADAPTER` system exception.

- `NON-RETAIN` and `USE_SERVANT_MANAGER`

This combination represents the situation where one servant is used per method call. The POA doesn't try to find a servant in the active object map because the active object map does not exist.

In every request, it will call `preinvoke()` on the `ServantManager` (specifically a `ServantLocator`) registered with the POA. If no `ServantManager` is available, the POA will raise the `OBJECT_ADAPTER` system exception.

- `NON-RETAIN` and `USE_DEFAULT_SERVANT`

This combination represents the situation where there is one single servant defined for all CORBA objects. The POA does not try to find a servant in the active object map because the active object map doesn't exist. In every request, the POA will invoke the appropriate operation on the default servant registered with the POA. If no default servant is available, the POA will raise the `OBJECT_ADAPTER` system exception.

//IDL

```
interface RequestProcessingPolicy {
    readonly attribute RequestProcessingPolicyValue value;
};
// C++ in namespace PortableServer
class IT_POA_API RequestProcessingPolicy :
    public virtual ::CORBA::Policy
{
public:
    typedef PortableServer::RequestProcessingPolicy_ptr
        _ptr_type;
    typedef PortableServer::RequestProcessingPolicy_var
        _var_type;
    virtual ~RequestProcessingPolicy();
    static RequestProcessingPolicy_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static RequestProcessingPolicy_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static RequestProcessingPolicy_ptr _duplicate(
        RequestProcessingPolicy_ptr p
    );
    inline static RequestProcessingPolicy_ptr _nil();
    virtual RequestProcessingPolicyValue value() = 0;
    static const IT_FWString _it_fw_type_id;
};
```

See [About Standard Functions for all Interfaces](#) for descriptions of the standard helper functions:

- `_duplicate()`
- `_narrow()`
- `_nil()`

- `_unchecked_narrow()`

`RequestProcessingPolicy::value()`

`//C++`

```
virtual RequestProcessingPolicyValue value() = 0;
```

Returns the value of this POA policy.

PortableServer::ServantActivator Interface

When a POA has the `RETAIN` policy value, it uses the `ServantActivator` type of servant manager.

//IDL

```
interface ServantActivator : ServantManager {
  Servant [incarnate](#portableserverservantactivator-interface)(
    in ObjectId oid,
    in POA adapter
  )
  raises (ForwardRequest);
  void [etherealize](#portableserverservantactivator-interface)(
    in ObjectId oid,
    in POA adapter,
    in Servant serv,
    in boolean cleanup_in_progress,
    in boolean remaining_activations
  );
};
```

ServantActivator::etherealize()

//IDL

```
void etherealize(
  in ObjectId oid,
  in POA adapter,
  in Servant serv
  in boolean cleanup_in_progress
  in boolean remaining_activations
);
```

//C++


```
virtual void etherealize(
    const ObjectId & oid,
    POA_ptr adapter,
    Servant serv,
    CORBA::Boolean cleanup_in_progress,
    CORBA::Boolean remaining_activations
) = 0;
```

Destroys a servant in a POA that has the `RETAIN` and `USE_SERVANT_MANAGER` policy values.

The `cleanup_in_progress` parameter indicates the context in which this method was called. If it is set to `true`, `etherealize()` was called because of calls to either `PortableServer::POAManager::deactivate()` or `PortableServer::POA::destroy()`, with its `etherealize_objects` parameter set to `true`. If `cleanup_in_progress` is false, this method was called for other reasons.

Because a servant can incarnate multiple objects, `etherealize()` checks the `remaining_activations` parameter to determine whether this servant incarnates any other objects within this POA; if `remaining_activations` is set to `FALSE` and the servant is not used by other POAs, the method can safely delete the servant from memory.

Before the POA calls on a servant manager's `etherealize()` method, it takes steps to ensure the safe destruction of servants in a multi-threaded environment:

- Removes the target object and its servant from the active object map. Thus, new requests for the target object cannot be invoked on the servant while it undergoes etherealization.
- Calls `etherealize()` on the servant only after all outstanding requests finish processing.

A servant can be etherealized by a servant activator other than the one that originally incarnated it.

`ServantActivator::incarnate()`

//IDL

```
Servant incarnate(
    in ObjectId oid,
    in POA adapter
)
raises (ForwardRequest);
```

//C++

```
virtual Servant incarnate(
    const ObjectId & oid,
    POA_ptr adapter
) = 0;
```

Called by the POA when it receives a request for object `oid`, where `oid` contains the ID of an inactive object. `incarnate()` returns an appropriate servant for the requested object; this servant is associated with `oid` in the POA's active object map, thereby activating the object. Subsequent requests for this object are mapped directly to the servant.

This method is only called by the POA on a servant activator, which the POA uses as its servant manager when it has policies of `USE_SERVANT_MANAGER` and `RETAIN`. When using a servant activator, the active object map retains a servant-object association until the servant is etherealized. A servant can only incarnate a given object once. If the POA has a policy of `UNIQUE_ID`, `incarnate()` can only return a servant that does not incarnate any object other than `oid` in that POA.

Note

If the same servant is used by different POAs, that servant conforms to the uniqueness policy of each POA. Thus, it is possible for the same servant to be associated with multiple objects in one POA, and be restricted to one object in another.

Exceptions

ForwardRequest

The client is instructed to send this request and subsequent requests for `oid` to the object specified in the exception's `forward_reference` member—in IIOP, through a `LOCATION_FORWARD` reply.

See

Also `PortableServer::ServantActivator::etherealize()` `PortableServer::ServantLocator::preinvoke()`

PortableServer::ServantBase

This is a native abstract C++ base class, from which other classes inherit. It is not itself instantiated, but classes derived from it can be instantiated.

//IDL

```

class IT_POA_API ServantBase
{
public:
virtual ~ServantBase();
virtual POA_ptr _default_POA();
ART_DECL_ABSTRACT_LOCAL_NARROW
typedef void (*_IT_DispatcherPtr)(
ServantBase* servant,
CORBA::ServerRequest_ptr request,
CORBA::CompletionStatus &status
);
virtual void
_dispatch(
CORBA::ServerRequest_ptr request
);
virtual _IT_DispatcherPtr
_lookup_dispatcher(
const char* operation
);
virtual CORBA::InterfaceDef_ptr
_get_interface();
virtual CORBA::Boolean
_is_a(
const char* id
);
virtual CORBA::Boolean
_it_is_a(
const IT_FWString& id
);
virtual CORBA::Boolean
_non_existent();
static void
_is_a_dispatch(
PortableServer::ServantBase* _servant,
CORBA::ServerRequest_ptr _request,
CORBA::CompletionStatus &_status
);
virtual void
_add_ref();
virtual void
_remove_ref();
static void
_non_existent_dispatch(
PortableServer::ServantBase* _servant,
CORBA::ServerRequest_ptr _request,
CORBA::CompletionStatus &_status
);

```

```
);
static void
_get_interface_dispatch(
PortableServer::ServantBase* _servant,
CORBA::ServerRequest_ptr _request,
CORBA::CompletionStatus &_status
);
virtual CORBA::RepositoryId
_primary_interface(
const ObjectId& oid,
POA_ptr poa
) = 0;
protected:
CORBA::Object_ptr
_this_impl(
const char* type_id
);
ServantBase();
ServantBase(
const ServantBase&
);
ServantBase&
operator=(
const ServantBase&
);
};
```

PortableServer::ServantLocator Interface

When a POA has the `NON_RETAIN` policy value, it uses servant locators as its servant managers. Because the POA knows that the servant returned by a `ServantLocator` will be used only for a single request, it can supply extra information to the servant manager's operations. Also, the servant manager's pair of operations may be able to cooperate to do something different than a `ServantActivator`.

//IDL

```
interface ServantLocator : ServantManager {
    native [Cookie](#portableserverservantlocator-interface);
    Servant [preinvoke](#portableserverservantlocator-interface)(
        in ObjectId oid,
        in POA adapter,
        in CORBA::Identifier operation,
        out Cookie the_cookie
    ) raises (ForwardRequest);
    void [postinvoke](#portableserverservantlocator-interface)(
        in ObjectId oid,
        in POA adapter,
        in CORBA::Identifier operation,
        in Cookie the_cookie,
        in Servant the_servant
    );
};
```

ServantLocator::Cookie Native Type

//IDL

```
native Cookie;
```

//C++

```
typedef void* Cookie;
```

The `Cookie` native type is opaque to the POA. It can be set by the servant manager for use later by `postinvoke()`.

ServantLocator::postinvoke()

//IDL

```
void postinvoke(
  in ObjectId oid,
  in POA adapter
  in CORBA::Identifier operation,
  in Cookie the_cookie,
  in Servant the_servant
)
```

//C++

```
virtual void postinvoke(
  const ObjectId & oid,
  POA_ptr adapter
  CORBA::Identifier const char* operation,
  Cookie the_cookie,
  Servant the_servant
) = 0;
```

Called on a POA's servant locator to delete a servant when processing of a request for object `oid` is complete.

Each `postinvoke()` call is paired to an earlier `preinvoke()` call. In order to explicitly map data between the two calls, you set the `preinvoke()` method's `the_cookie` parameter. This can be especially useful in a multi-threaded environment where it is important to ensure that a pair of `preinvoke()` and `postinvoke()` calls operate on the same servant. For example, each `preinvoke()` call can set its `the_cookie` parameter to data that identifies its servant; the `post invoke()` code can then compare that data to its `the_servant` parameter.

The POA calls this method only on a servant locator, which the POA uses as its servant manager when it has policies of `USE_SERVANT_MANAGER` and `NON_RETAIN`.

See Also `PortableServer::ServantLocator::preinvoke()` `PortableServer::POA::create_reference_with_id()`

ServantLocator::preinvoke()

//IDL

```
Servant preinvoke(
in ObjectId oid,
in POA adapter,
in CORBA::Identifier operation,
out Cookie the_cookie
)
raises (ForwardRequest);
```

//C++

```
virtual Servant preinvoke(
const ObjectId & oid,
POA_ptr adapter,
CORBA::Identifier const char* operation,
Cookie& the_cookie
) = 0;
```

Returns an appropriate servant for the requested object. This method is called on a POA's servant locator when the POA receives a request for object `oid`, where `oid` contains the ID of an inactive object.

This method is only called by the POA on a servant locator, which the POA uses as its servant manager when it has policies of `USE_SERVANT_MANAGER` and `NON_RETAIN`.

The lack of an active object map can require the following behavior:

- After processing on the requested object is complete, the POA calls `postinvoke()` on the object and etherealizes its servant.
- Each request for an object is treated independently, irrespective of the status of earlier requests for that object. So, it is possible for a POA to accept multiple requests for the same object concurrently and for its servant locator to incarnate several servants for that object simultaneously.

Alternatively, the application can maintain its own object-servant map in order to allow a servant to process multiple requests for the same object, or to process requests for multiple objects. For example, a database server can use a servant locator to direct concurrent operations to the same servant; database transactions are opened and closed within the `preinvoke()` and `postinvoke()` operations.

Each `preinvoke()` call is paired to an later `postinvoke()` call. In order to explicitly map data between the two calls, set `preinvoke()`'s `the_cookie` parameter. This can be especially useful in a multi-threaded environment where it is important to ensure that a pair of `preinvoke()` and `postinvoke()` calls operate on the same servant. For example, each `preinvoke()` call can set its

cookie parameter to data that identifies its servant; the `postinvoke()` code can then compare that data to its `the_servant` parameter.

Exceptions

`ForwardRequest`

The client is instructed to send this request and subsequent requests for oid to the object specified in the exception's `forward_reference` member—in IIOP, through a `LOCATION_FORWARD` reply.

See Also `PortableServer::ServantLocator::postinvoke()`

PortableServer::ServantManager Interface

A servant manager supplies a POA with the ability to activate objects on demand when the POA receives a request targeted at an inactive object. A servant manager is registered with a POA as a callback object, to be invoked by the POA when necessary.

A servant manager is used in servers only for the case in which an object must be activated during request processing. An application server that activates all its needed objects at the beginning of execution does not need to use a servant manager.

The `ServantManager` interface is an empty base interface that is inherited by the interfaces `ServantActivator` and `ServantLocator`. These two types of servant managers have the following corresponding policy values:

Table 25: Corresponding Policies for Servant Managers

Servant Manager	POA Policy Value
<code>ServantActivator</code>	<code>RETAIN</code>
<code>ServantLocator</code>	<code>NON_RETAIN</code>

//IDL

```
interface ServantManager
{ };
```

See Also `PORTABLESERVER::SERVANTACTIVATOR` `PORTABLESERVER::SERVANTLOCATOR`

PortableServer::ServantRetentionPolicy Interface

You obtain a `ServantRetentionPolicy` object by using `POA::create_servant_retention_policy()` and passing the policy to `POA::create_POA()` to specify whether the created POA retains active servants in an active object map. This is a policy class derived from `CORBA::Policy`.

If no `ServantRetentionPolicy` value is specified at POA creation, the default value is `RETAIN`.

See Also `PortableServer::RequestProcessingPolicy`

// IDL

```
interface ServantRetentionPolicy : CORBA::Policy {  
    readonly attribute ServantRetentionPolicyValue value;  
};
```

// C++ in namespace PortableServer

```

class IT_POA_API ServantRetentionPolicy :
public virtual ::CORBA::Policy
{
public:
typedef PortableServer::ServantRetentionPolicy_ptr _ptr_type;
typedef PortableServer::ServantRetentionPolicy_var _var_type;
virtual ~ServantRetentionPolicy();
static ServantRetentionPolicy_ptr _narrow(
CORBA::Object_ptr obj
);
static ServantRetentionPolicy_ptr _unchecked_narrow(
CORBA::Object_ptr obj
);
inline static ServantRetentionPolicy_ptr _duplicate(
ServantRetentionPolicy_ptr p
);
inline static ServantRetentionPolicy_ptr _nil();
virtual ServantRetentionPolicyValue value() = 0;
static const IT_FWString _it_fw_type_id;
};

```

See [About Standard Functions for all Interfaces](#) for descriptions of the standard helper functions.

- `_duplicate()`
- `_narrow()`
- `_nil()`
- `_unchecked_narrow()`

`ServantRetentionPolicy::value()`

//C++

```
virtual ServantRetentionPolicyValue value() = 0;
```

Returns the value of this POA policy.

PortableServer::ThreadPolicy Interface

You obtain a `ThreadPolicy` object by using `POA::create_thread_policy()` and passing the policy to `POA::create_POA()` to specify the threading model used with the created POA. This is a policy class derived from `CORBA::Policy`.

// IDL

```
interface ThreadPolicy : CORBA::Policy {
    readonly attribute ThreadPolicyValue value;
};
```

// C++ in namespace PortableServer

```
class IT_POA_API ThreadPolicy :
public virtual ::CORBA::Policy
{
public:
    typedef PortableServer::ThreadPolicy_ptr _ptr_type;
    typedef PortableServer::ThreadPolicy_var _var_type;
    virtual ~ThreadPolicy();
    static ThreadPolicy_ptr _narrow(
        CORBA::Object_ptr obj
    );
    static ThreadPolicy_ptr _unchecked_narrow(
        CORBA::Object_ptr obj
    );
    inline static ThreadPolicy_ptr _duplicate(
        ThreadPolicy_ptr p
    );
    inline static ThreadPolicy_ptr _nil();
    virtual ThreadPolicyValue value() = 0;
    static const IT_FWString _it_fw_type_id;
};
```

See [About Standard Functions for all Interfaces](#) for descriptions of the standard helper functions.

- `_duplicate()`
- `_narrow()`
- `_nil()`

- `_unchecked_narrow()`

`ThreadPolicy::value()`

`//C++`

```
virtual ThreadPolicyValue value() = 0;
```

Returns the value of this POA policy.

Security Overview

The standard `Security` module defines data types and constants that are used throughout the CORBA security specification. This section documents only the definitions relevant to Orbix.

There is also a reference in .

Security::AssociationOptions Type

// IDL

```
typedef unsigned short AssociationOptions;
```

A data type that holds a set of association options in its bit fields.

See Also Security::NoProtection

```
Security::Integrity  
Security::Confidentiality  
Security::DetectReplay  
Security::DetectMisordering  
Security::EstablishTrustInTarget  
Security::EstablishTrustInClient  
Security::NoDelegation  
Security::SimpleDelegation  
Security::CompositeDelegation
```

Security::AttributeList Sequence

// IDL

```
typedef sequence <SecAttribute> AttributeList;
```

Security::AuthenticationMethod Type

// IDL

```
typedef unsigned long AuthenticationMethod;
```

Constants of this type are used by the `SecurityLevel2 :: PrincipalAuthenticator :: authenticate()` operation to identify an authentication method. Orbix defines a range of `AuthenticationMethod` constants in the `IT_TLS_API` module—for example, `IT_TLS_API :: IT_TLS_AUTH_METH_PKSC12_FILE`.

Security::AuthenticationMethodList Sequence

// IDL

```
typedef sequence<AuthenticationMethod> AuthenticationMethodList;
```

A list of authentication methods.

Security::AuthenticationStatus Enumeration

// IDL

```
enum AuthenticationStatus {
    SecAuthSuccess,
    SecAuthFailure,
    SecAuthContinue,
    SecAuthExpired
};
```

Used by the `SecurityLevel2 :: PrincipalAuthenticator :: authenticate()` operation to give the status of the returned credentials.

Values

The status of a newly-generated `Credentials` object, `creds`, is indicated as follows:

<code>SecAuthSuccess</code>	A valid <code>Credentials</code> object is available in the <code>creds</code> parameter.
<code>SecAuthFailure</code>	Authentication was in some way inconsistent or erroneous. <code>Credentials</code> have therefore not been created.

<code>SecAuthContinue</code>	The authentication procedure uses a challenge and response mechanism. The <code>creds</code> parameter references a partially initialized <code>Credentials</code> object and the <code>continuation_data</code> indicates details of the challenge. Not supported by Orbix.
<code>SecAuthExpired</code>	The authentication data, <code>auth_data</code> , has expired. Credentials have therefore not been created.

Security::CommunicationDirection Enumeration

// IDL

```
enum CommunicationDirection {
    SecDirectionBoth,
    SecDirectionRequest,
    SecDirectionReply
};
```

Indicates a particular communication direction along a secure association.

See Also `SecurityLevel2::Credentials::get_security_feature()`

Security::CompositeDelegation Constant

// IDL

```
const AssociationOptions CompositeDelegation = 512;
```

Not supported in Orbix.

Security::Confidentiality Constant

// IDL

```
const AssociationOptions Confidentiality = 4;
```

Specifies that an object supports or requires confidentiality-protected invocations.

Security::DetectMisordering Constant

// IDL

```
const AssociationOptions DetectMisordering = 16;
```

Specifies that an object supports or requires error detection on fragments of invocation messages. In Orbix this option can be set only through configuration.

Security::DetectReplay Constant

// IDL

```
const AssociationOptions DetectReplay = 8;
```

Specifies that an object supports or requires replay detection on invocation messages. In Orbix this option can be set only through configuration.

Security::EstablishTrust Structure

// IDL

```
struct EstablishTrust {
    boolean trust_in_client;
    boolean trust_in_target;
};
```

Parameters This structure is used to hold the data associated with the SecurityLevel2 :: EstablishTrustPolicy.

The elements of the structure are, as follows:

<code>trust_in_client</code>	Specifies whether or not an invocation must select credentials and a mechanism that allow the client to be authenticated to the target. (Some mechanisms might not support client authentication).
<code>trust_in_target</code>	Specifies whether or not an invocation must establish trust in the target.

Security::EstablishTrustInClient Constant

// IDL

```
const AssociationOptions EstablishTrustInClient = 64;
```

Specifies that a client supports or requires that the target authenticate its identity to the client.

See Also `SecurityLevel2::EstablishTrustPolicy`

`Security::EstablishTrustInTarget` Constant

// IDL

```
const AssociationOptions EstablishTrustInTarget = 32;
```

Specifies that a target object requires the client to authenticate its privileges to the target.

See Also `SecurityLevel2::EstablishTrustPolicy`

`Security::Integrity` Constant

// IDL

```
const AssociationOptions Integrity = 2;
```

Specifies that an object supports integrity-protected invocations.

`Security::InvocationCredentialsType` Enumeration

// IDL

```
enum InvocationCredentialsType {
    SecOwnCredentials,
    SecReceivedCredentials,
    SecTargetCredentials
};
```

Identifies the underlying type of a `SecurityLevel2 :: Credentials` object, as follows:

<code>SecOwnCredentials</code>	The underlying type is <code>SecurityLevel2 :: Credentials</code> .
<code>SecReceivedCredentials</code>	The underlying type is <code>SecurityLevel2 :: ReceivedCredentials</code> .

SecTargetCredentials

The underlying type is SecurityLevel2 : : TargetCredentials.

Security::MechanismType Type

// IDL

```
typedef string MechanismType;
```

Identifies a security mechanism.

See Also SecurityLevel2::MechanismPolicy

Security::MechanismTypeList Sequence

// IDL

```
typedef sequence<MechanismType> MechanismTypeList;
```

A list of security mechanisms.

See Also SecurityLevel2::MechanismPolicy

Security::NoDelegation Constant

// IDL

```
const AssociationOptions NoDelegation = 128;
```

Not supported in Orbix.

Security::NoProtection Constant

// IDL

```
const AssociationOptions NoProtection = 1;
```

When used with the target secure invocation policy, indicates that the target can accept insecure connections.

When used with the client secure invocation policy, indicates that the client can open insecure connections.

Security::Opaque Type

// IDL

```
typedef sequence <octet> Opaque;
```

A general purpose type that is used to hold binary data.

Security::QOP Enumeration

// IDL

```
enum QOP {
    SecQOPNoProtection,
    SecQOPIntegrity,
    SecQOPConfidentiality,
    SecQOPIntegrityAndConfidentiality
};
```

Identifies the range of security features that can be associated with an individual object reference (quality of protection).

Values

<code>SecQOPNoProtection</code>	The <code>Security::NoProtection</code> association option.
<code>SecQOPIntegrity</code>	The <code>Security::Integrity</code> association option.
<code>SecQOPConfidentiality</code>	The <code>Security::Confidentiality</code> association option.
<code>SecQOPIntegrityAndConfidentiality</code>	Both the <code>Security::Integrity</code> and <code>Security::Confidentiality</code> association options.

Security::SecApplicationAccess Constant

// IDL

```
const CORBA::PolicyType SecApplicationAccess = 3;
```

Not supported in Orbix.

Security::SecAttribute Structure

// IDL

```
struct SecAttribute {
    AttributeType attribute_type;
    OID defining_authority;
    Opaque value;
};
```

Security::SecClientInvocationAccess Constant

// IDL

```
const CORBA::PolicyType SecClientInvocationAccess = 1;
```

Not supported in Orbix.

Security::SecClientSecureInvocation Constant

// IDL

```
const CORBA::PolicyType SecClientSecureInvocation = 8;
```

Defines one of the policy types for the `SecurityAdmin::SecureInvocationPolicy` interface. This policy can only be set through configuration.

Security::SecEstablishTrustPolicy Constant

// IDL

```
const CORBA::PolicyType SecEstablishTrustPolicy = 39;
```

Defines the policy type for the `SecurityLevel2::EstablishTrustPolicy` interface.

Security::SecInvocationCredentialsPolicy Constant

// IDL

```
const CORBA::PolicyType SecInvocationCredentialsPolicy = 13;
```

Defines the policy type for the `SecurityLevel2::InvocationCredentialsPolicy` interface.

Security::SecMechanismsPolicy Constant

// IDL

```
const CORBA::PolicyType SecMechanismsPolicy = 12;
```

Defines the policy type for the `SecurityLevel2::MechanismsPolicy` interface.

See Also `IT_TLS_API::TLS::create_mechanism_policy()`

Security::SecQOPPolicy Constant

// IDL

```
const CORBA::PolicyType SecQOPPolicy = 15;
```

Defines the policy type for the `SecurityLevel2::QOPPolicy` interface.

Security::SecTargetInvocationAccess Constant

// IDL

```
const CORBA::PolicyType SecTargetInvocationAccess = 2;
```

Not supported in Orbix.

Security::SecTargetSecureInvocation Constant

// IDL

```
const CORBA::PolicyType SecTargetSecureInvocation = 9;
```

Defines one of the policy types for the `SecurityAdmin::SecureInvocationPolicy` interface. This policy can only be set through configuration.

Security::SecurityFeature Enumeration

// IDL

```
enum SecurityFeature {
    SecNoDelegation,
    SecSimpleDelegation,
    SecCompositeDelegation,
    SecNoProtection,
    SecIntegrity,
    SecConfidentiality,
    SecIntegrityAndConfidentiality,
    SecDetectReplay,
    SecDetectMisordering,
    SecEstablishTrustInTarget,
    SecEstablishTrustInClient
};
```

Identifies the range of security features that can be associated with a Credentials object, including association options.

Values

This enumeration can have the following values:

SecNoDelegation	The Security::NoDelegation association option.
SecSimpleDelegation	The Security::SimpleDelegation association option. Not supported in Orbix.
SecCompositeDelegation	The Security::CompositeDelegation association option. Not supported in Orbix.
SecNoProtection	The Security::NoProtection association option.
SecIntegrity	The Security::Integrity association option.
SecConfidentiality	The Security::Confidentiality association option.

<code>SecIntegrityAndConfidentiality</code>	Both the <code>Security::Integrity</code> and <code>Security::Confidentiality</code> association options.
<code>SecDetectReplay</code>	The <code>Security::DetectReplay</code> association option.
<code>SecDetectMisordering</code>	The <code>Security::DetectMisordering</code> association option.
<code>SecEstablishTrustInTarget</code>	The <code>Security::EstablishTrustInTarget</code> association option.
<code>SecEstablishTrustInClient</code>	The <code>Security::EstablishTrustInClient</code> association option.

See Also `SecurityLevel2::Credentials::get_security_feature()`

`Security::AssociationOptions`

`Security::SecurityName` Type

// IDL

```
typedef string SecurityName;
```

A string that identifies a principal (for example, a login name).

Not used by Orbix.

`Security::SimpleDelegation` Constant

// IDL

```
const AssociationOptions SimpleDelegation = 256;
```

Not supported in Orbix.

SecurityLevel1 Overview

Because security level 1 is aimed at security-unaware applications, there is little IDL defined at this level —most of the security features are controlled by an administrator. Currently, there is one IDL interface defined at level 1:

```
SecurityLevel1::Current
```

SecurityLevel2 Overview

At security level 2, IDL interfaces are defined to enable security-aware application to access security information and specify security policies. Orbix implements the following IDL interfaces from the

`SecurityLevel2` IDL module:

- `PrincipalAuthenticator` interface.
- `Credentials` interface.
- `ReceivedCredentials` interface.
- `TargetCredentials` interface.
- `QOPPolicy` interface.
- `MechanismPolicy` interface.
- `InvocationCredentialsPolicy` interface.
- `EstablishTrustPolicy` interface.
- `SecurityManager` interface.
- `Current` interface.

`SecurityLevel2::CredentialsList` Sequence

// IDL

```
typedef sequence <Credentials> CredentialsList;
```

A sequence to hold a list of `Credentials` objects.

SecurityLevel2::Credentials Interface

IDL

```
// IDL in module SecurityLevel2
interface Credentials {      // Locality Constrained
# pragma version Credentials 1.7
    Credentials copy();
    void destroy();
    readonly attribute Security::InvocationCredentialsType
        credentials_type;
    readonly attribute Security::AuthenticationStatus
        authentication_state;
    readonly attribute Security::MechanismType
        mechanism;
    attribute Security::AssociationOptions
        accepting_options_supported;
    attribute Security::AssociationOptions
        accepting_options_required;
    attribute Security::AssociationOptions
        invocation_options_supported;
    attribute Security::AssociationOptions
        invocation_options_required;
    boolean get_security_feature(
        in Security::CommunicationDirection direction,
        in Security::SecurityFeature feature
    );
    boolean set_attributes (
        in Security::AttributeList requested_attributes,
        out Security::AttributeList actual_attributes
    );
    Security::AttributeList get_attributes (
        in Security::AttributeTypeList attributes
    );
    boolean is_valid (out Security::UtcT expiry_time);
    boolean refresh(in any refresh_data);
};
```

Description

The `Credentials` interface is used either as a base interface or as a concrete interface (most derived type is `Credentials`). An object of `Credentials` type can represent one of the following kinds of credential:

- *Own credentials*—when the most derived type of the `Credentials` object is `Credentials`.
- *Received credentials*—when the most derived type of the `Credentials` object is `ReceivedCredentials`.
- *Target credentials*—when the most derived type of the `Credentials` object is `TargetCredentials`.

A `Credentials` object holds the security attributes of a principal.

See Also `IT_TLS_API::TLSCredentials`

```
IT_TLS_API::TLSReceivedCredentials
IT_TLS_API::TLSTargetCredentials
```

`Credentials::accepting_options_required` Attribute

IDL

```
attribute Security::AssociationOptions accepting_options_required;
```

Description

Not implemented in Orbix.

`Credentials::accepting_options_supported` Attribute

IDL

```
attribute Security::AssociationOptions accepting_options_supported;
```

Description

Not implemented in Orbix.

`Credentials::authentication_state` Attribute

IDL

```
readonly attribute Security::AuthenticationStatus authentication_state;
```

Description

Specifies how a `Credentials` object is initialized (authentication state) at the time it is created by the `PrincipalAuthenticator` object.

Values

The authentication state can have one of the following values:

<code>SecAuthSuccess</code>	The Credentials object is fully initialized and valid.
<code>SecAuthFailure</code>	Authentication has failed and the credentials are invalid. The Credentials object can be in this state if it was partially initialized in a call to <code>PrincipalAuthenticator::authenticate()</code> and then failed in the <code>PrincipalAuthenticator::continue_authentication()</code> operation.
<code>SecAuthContinue</code>	The Credentials object is partially initialized and not yet valid for use.
<code>SecAuthExpired</code>	The credentials initialization has expired and the credentials are invalid.

`Credentials::copy()`

IDL

```
Credentials copy();
```

Description

Returns a reference to a deep copy of the target `Credentials` object.

Not implemented in Orbix.

`Credentials::credentials_type` Attribute

IDL

```
readonly attribute Security::InvocationCredentialsType
    credentials_type;
```

Description

Indicates whether the `Credentials` object represents an application's own credentials (of `Credentials` type), or received credentials (of `ReceivedCredentials` type), or target credentials (of `TargetCredentials` type).

Values

This attribute can have one of the following values:

<code>Security::SecOwnCredentials</code>	Indicates own credentials

<code>Security::SecReceivedCredentials</code>	Indicates received credentials.
<code>Security::SecTargetCredentials</code>	indicates target credentials

`Credentials::destroy()`

IDL

```
void destroy();
```

Description

Destroys the Credentials object.

Not implemented in Orbix.

`Credentials::get_attributes()`

IDL

```
Security::AttributeList get_attributes(
    in AttributeTypeList attributes
);
```

Description

Returns the security attributes from a `Credentials` object.

Parameters This operation takes the following parameter:

<code>attributes</code>	The set of security attributes (attributes and identities) whose values are desired. If this list is empty, all attributes are returned.

`Credentials::get_security_feature()`

IDL

```
boolean get_security_feature(
    in Security::CommunicationDirection direction,
    in Security::SecurityFeature feature
);
```

Description

Not implemented in Orbix.

Credentials::invocation_options_required Attribute

IDL

```
attribute Security::AssociationOptions
    invocation_options_required;
```

Description

Not implemented in Orbix.

Use `SecurityLevel2::QOFPolicy` programmatically or secure invocation policies in the configuration file instead.

Credentials::invocation_options_supported Attribute

IDL

```
attribute Security::AssociationOptions
    invocation_options_supported;
```

Description

Not implemented in Orbix.

Use `SecurityLevel2::QOFPolicy` programmatically or secure invocation policies in the configuration file instead.

Credentials::is_valid()

IDL

```
boolean is_valid(out Security::UtcT expiry_time);
```

Description

Returns TRUE if the `Credentials` object is valid and FALSE otherwise.

Not implemented in Orbix.

Credentials::mechanism Attribute

IDL

```
readonly attribute Security::MechanismType mechanism;
```

Description

A string, of `Security::MechanismType` type, that identifies the underlying security mechanism.

Values

Orbix returns the string 20 which represents SSL/TLS.

See Also IT_TLS_API::TLS::create_mechanism_policy()

Credentials::refresh()

IDL

```
boolean refresh(in any refresh_data);
```

Description

Not implemented in Orbix.

Some security mechanisms allow you to extend the expiry time of a Credentials object by refreshing the credentials.

Credentials::set_attributes()

IDL

```
boolean set_attributes (
    in Security::AttributeList requested_attributes,
    out Security::AttributeList actual_attributes
);
```

Description

Not implemented in Orbix.

SecurityLevel2::Current Interface

IDL

```
// IDL in module SecurityLevel2
local interface Current : SecurityLevel1::Current {
# pragma version Current 1.7
    // Thread specific
    readonly attribute ReceivedCredentials received_credentials;
};
```

Description

The `Current` object accesses information about the execution context. In Orbix, the level 2 `Current` interface provides received credentials (originating from a client) to a target object's execution context.

Current::received_credentials Attribute

IDL

```
readonly attribute ReceivedCredentials received_credentials;
```

At a target object, this thread-specific attribute is the credentials received from a client. They are the credentials of the authenticated principal that made the invocation.

If you have enabled Common Secure Interoperability (CSIv2), the

`SecurityLevel2::Current::received_credentials()` operation returns the following credentials type:

- Propagated identity credentials, if present
- Authenticated credentials over the transport, if present and propagated identity credentials are not.
- Transport TLS credentials, if present and the above two are not.

See `IT_CSI::CSIReceivedCredentials` for more details.

Exceptions In the case of a pure client, that is, an application that is not servicing an invocation on one of its objects, accessing the `received_credentials` attribute causes a `CORBA::BAD_OPERATION` exception to be raised.

SecurityLevel2::EstablishTrustPolicy Interface

IDL

```
// IDL in module SecurityLevel2
interface EstablishTrustPolicy : CORBA::Policy {
    readonly attribute EstablishTrust trust;
};
```

Description

A policy of this type can be passed to the `set_policy_overrides()` operation to obtain an object reference that obeys the given trust policy.

The `EstablishTrustPolicy` object has a policy type of `Security::SecEstablishTrustPolicy` and is locality constrained.

EstablishTrustPolicy::trust Attribute

IDL

```
readonly attribute EstablishTrust trust;
```

Description

The `trust` attribute is a structure that contains two members, each stipulating whether trust in the client and trust in the target is enabled.

SecurityLevel2::InvocationCredentialsPolicy Interface

IDL

```
// IDL in module SecurityLevel2
interface InvocationCredentialsPolicy : CORBA::Policy {
    readonly attribute CredentialsList creds;
};
```

Description

A policy of this type can be passed to the `set_policy_overrides()` operation to obtain an object reference that uses the given credentials list, `creds`, for operation and attribute invocations.

The `InvocationCredentialsPolicy` object has a policy type of `Security::SecInvocationCredentialsPolicy` and is locality constrained.

InvocationCredentialsPolicy::creds

IDL

```
readonly attribute CredentialsList creds;
```

Description

The list of Credentials objects associated with the `InvocationCredentialsPolicy` object.

SecurityLevel2::MechanismPolicy Interface

IDL

```
// IDL in module SecurityLevel2
interface MechanismPolicy : CORBA::Policy {
    readonly attribute Security::MechanismTypeList mechanisms;
};
```

Description

A policy of this type can be passed to the `set_policy_overrides()` operation to obtain an object reference that uses the specified security mechanisms.

The `MechanismPolicy` object has a policy type of `Security::SecMechanismsPolicy` and is locality constrained.

See Also `IT_TLS_API::TLS::create_mechanism_policy()`

`MechanismPolicy::mechanisms`

IDL

```
readonly attribute Security::MechanismTypeList mechanisms;
```

Description

The mechanisms, in the form of a `Security::MechanismTypeList`, associated with the `MechanismPolicy` object.

SecurityLevel2::PrincipalAuthenticator Interface

IDL

```
// IDL in module SecurityLevel2
interface PrincipalAuthenticator { // Locality Constrained
#   pragma version PrincipalAuthenticator 1.5
    Security::AuthenticationMethodList
    get_supported_authen_methods(
        in Security::MechanismType mechanism
    );
    Security::AuthenticationStatus authenticate (
        in Security::AuthenticationMethod method,
        in Security::MechanismType mechanism,
        in Security::SecurityName security_name,
        in any auth_data,
        in Security::AttributeList privileges,
        out Credentials creds,
        out any continuation_data,
        out any auth_specific_data
    );
    Security::AuthenticationStatus continue_authentication (
        in any response_data,
        in Credentials creds,
        out any continuation_data,
        out any auth_specific_data
    );
};
```

Description

This interface provides operations to authenticate a principal and provide it with credentials. For example, the `authenticate()` operation is typically called when a user logs on to an application.

PrincipalAuthenticator::authenticate()

IDL

```

Security::AuthenticationStatus authenticate (
    in Security::AuthenticationMethod method,
    in Security::MechanismType mechanism,
    in Security::SecurityName security_name,
    in any auth_data,
    in Security::AttributeList privileges,
    out Credentials creds,
    out any continuation_data,
    out any auth_specific_data
);

```

Description

This operation is called to authenticate the principal. It can also request privilege attributes that the principal requires during its capsule-specific session with the system.

It creates a capsule-specific Credentials object including the required attributes and is placed on the SecurityManager object's own_credentials list according to the credential's mechanism type.

In Orbix, a capsule is effectively identified with an ORB object. The main consequence of this is that credentials are not shared between ORB objects. If you create more than one ORB object in your application, you must call `authenticate()` for each ORB object to make credentials available to both ORBs.

Return Value

The return value indicates the status of the `creds` parameter:

<code>SecAuthSuccess</code>	A valid Credentials object is available in the <code>creds</code> parameter.
<code>SecAuthFailure</code>	Authentication was in some way inconsistent or erroneous. Credentials have therefore not been created.
<code>SecAuthContinue</code>	The authentication procedure uses a challenge and response mechanism. The <code>creds</code> parameter references a partially initialized Credentials object and the <code>continuation_data</code> indicates details of the challenge. Not supported by Orbix.

<code>SecAuthExpired</code>	The authentication data, <code>auth_data</code> , has expired. Credentials have therefore not been created.

Parameters

<code>method</code>	The authentication method to use. For example, <code>IT_TLS_API::IT_TLS_AUTH_METH_PKCS12_FILE</code> . See the <code>IT_TLS_API</code> module for the complete list of authentication methods supported by Orbix.
<code>mechanism</code>	The security mechanism for creating the returned Credentials object. Leave this parameter blank. It defaults to SSL/TLS.
<code>security_name</code>	The principal's identification information (such as login name). Not used by Orbix.
<code>auth_data</code>	The principal's authentication information, typically consisting of a certificate, private key and pass phrase. The data inserted into the <code>auth_data</code> parameter depends on the specified authentication method, <code>method</code> .
<code>privileges</code>	The requested privilege attributes. Not supported by Orbix.
<code>creds</code>	This parameter contains the locality constrained object reference of the newly created Credentials object. It is usable and placed on the <code>Current</code> object's <code>own_credentials</code> list only if the return value is <code>SecAuthSuccess</code> .
<code>continuation_data</code>	Not supported by Orbix.
<code>auth_specific_data</code>	Not supported by Orbix.

PrincipalAuthenticator::continue_authentication()

IDL


```
Security::AuthenticationStatus continue_authentication (  
    in any response_data,  
    in Credentials creds,  
    out any continuation_data,  
    out any auth_specific_data  
);
```

Description

Not supported by Orbix.

PrincipalAuthenticator::get_supported_authen_methods()

IDL

```
Security::AuthenticationMethodList  
get_supported_authen_methods(  
    in Security::MechanismType mechanism  
);
```

Description

Not implemented in Orbix.

SecurityLevel2::QOPPolicy Interface

IDL

```
// IDL in module SecurityLevel2
interface QOPPolicy : CORBA::Policy {
    readonly attribute Security::QOP qop;
};
```

Description

A QOP policy object can be passed to the `set_policy_overrides()` operation to obtain an object reference that uses the specified quality of protection policy.

See Also `Security::SecQOPPolicy`

QOPPolicy::qop Attribute

IDL

```
readonly attribute Security::QOP qop;
```

Description

The quality of protection, of `Security::QOP` enumeration type, associated with the `QOPPolicy` object.

SecurityLevel2::ReceivedCredentials Interface

IDL

```
// IDL in module SecurityLevel2
interface ReceivedCredentials : Credentials {
# pragma version ReceivedCredentials 1.5
    readonly attribute Credentials accepting_credentials;
    readonly attribute Security::AssociationOptions
        association_options_used;
    readonly attribute Security::DelegationState delegation_state;
    readonly attribute Security::DelegationMode delegation_mode;
};
```

Description

A `ReceivedCredentials` object stores the security attributes of a remote client. It is made available in an execution context on the server side and can be obtained from a `SecurityLevel2 :: Current` object.

See Also `SecurityLevel2 :: Current`

```
IT_TLS_API::TLSReceivedCredentials
```

ReceivedCredentials::accepting_credentials Attribute

IDL

```
readonly attribute Credentials accepting_credentials;
```

Description

Not implemented in Orbix.

ReceivedCredentials::association_options_used Attribute

IDL

```
readonly attribute Security::AssociationOptions  
    association_options_used;
```

Description

Not implemented in Orbix.

ReceivedCredentials::delegation_mode Attribute

IDL

```
readonly attribute Security::DelegationMode delegation_mode;
```

Description

Not implemented in Orbix.

ReceivedCredentials::delegation_state Attribute

IDL

```
readonly attribute Security::DelegationState delegation_state;
```

Description

Not implemented in Orbix.

SecurityLevel2::SecurityManager Interface

IDL

```
// IDL in module SecurityLevel2
interface SecurityManager {
    readonly attribute Security::MechandOptionsList
        supported_mechanisms;
    readonly attribute CredentialsList own_credentials;
    readonly attribute RequiredRights required_rights_object;
    readonly attribute PrincipalAuthenticator
        principal_authenticator;
    readonly attribute AccessDecision access_decision;
    readonly attribute AuditDecision audit_decision;
    TargetCredentials get_target_credentials (in Object obj_ref);
    void remove_own_credentials(in Credentials creds);
    CORBA::Policy get_security_policy (
        in CORBA::PolicyType policy_type
    );
};
```

Description

In Orbix, this class is used to access ORB-specific information.

SecurityManager::access_decision Attribute

IDL

```
readonly attribute AccessDecision access_decision;
```

Description

Not implemented in Orbix.

SecurityManager::audit_decision Attribute

IDL

```
readonly attribute AuditDecision audit_decision;
```

Description

Not implemented in Orbix.

SecurityManager::get_security_policy()

IDL

```
CORBA::Policy get_security_policy (
    in CORBA::PolicyType policy_type
);
```

Description

Not implemented in Orbix.

SecurityManager::get_target_credentials()

IDL

```
TargetCredentials get_target_credentials(
    in Object target;
};
```

Description

Returns the target credentials for an object referenced by the specified object reference, `target`. For example, this operation is typically used on the client side to obtain the target credentials for a remote object.

Parameters

```
target
```

An object reference.

SecurityManager::own_credentials Attribute

IDL

```
readonly attribute CredentialsList own_credentials;
```

Description

Holds an application's own credentials, which are established by calling `authenticate()` on the application's own `PrincipalAuthenticator` object.

SecurityManager::principal_authenticator Attribute

IDL

```
readonly attribute PrincipalAuthenticator principal_authenticator;
```

Description

Holds a reference to the `PrincipalAuthenticator` object that can be used by the application to authenticate principals and obtain credentials.

SecurityManager::remove_own_credentials()

IDL

```
void remove_own_credentials(
    in Credentials creds
);
```

Description

Removes credentials that were put on the `own_credentials` list using the `PrincipalAuthenticator`. This operation does not manipulate or destroy the objects in any way.

Parameters

```
creds
```

The `Credentials` object to be removed from the list.

SecurityManager::required_rights_object Attribute

IDL

```
readonly attribute RequiredRights required_rights_object;
```

Description

Not implemented in Orbix.

SecurityManager::supported_mechanisms Attribute

IDL

```
readonly attribute Security::MechandOptionsList  
    supported_mechanisms;
```

Description

Not implemented in Orbix.

SecurityLevel2::TargetCredentials Interface

IDL

```
// IDL in module SecurityLevel2
interface TargetCredentials : Credentials {
    readonly attribute Credentials
        initiating_credentials;
    readonly attribute Security::AssociationOptions
        association_options_used;
};
```

Description

A `TargetCredentials` object holds the security attributes of an authenticated target object. To obtain the target credentials for a remote object, call the `SecurityManager::get_target_credentials()` operation.

See Also `ITLS_API::TLSTargetCredentials`

TargetCredentials::association_options_used Attribute

IDL

```
readonly attribute Security::AssociationOptions
    association_options_used;
```

Description

Not implemented in Orbix.

TargetCredentials::initiating_credentials Attribute

IDL

```
readonly attribute Credentials initiating_credentials;
```

Description

Not implemented in Orbix.

System Exceptions

This appendix defines the system exceptions returned by Orbix.

<code>BAD_CONTEXT</code>	This exception is raised if a client invokes an operation but the passed context does not contain the context values required by the operation.
<code>BAD_INV_ORDER</code>	This exception indicates that the caller has invoked operations in the wrong order. For example, it can be raised by an ORB if an application makes an ORB-related call without having correctly initialized the ORB first.
<code>BAD_OPERATION</code>	This exception indicates that an object reference denotes an existing object, but that the object does not support the operation that was invoked.
<code>BAD_PARAM</code>	This exception is raised if a parameter passed to a call is out of range or otherwise considered illegal. For example, an ORB may raise this exception if null values or null pointers are passed to an operation (for language mappings where the concept of a null pointers or null values applies). <code>BAD_PARAM</code> can also be raised as a result of client generating requests with incorrect parameters using the DII.
<code>BAD_TYPECODE</code>	This exception is raised if the ORB encounters a malformed type code (for example, a type code with an invalid <code>TCKind</code> value).
<code>COMM_FAILURE</code>	This exception is raised if communication is lost while an operation is in progress, after the request was sent by the client, but before the reply from the server has been returned to the client.
<code>DATA_CONVERSION</code>	This exception is raised if an ORB cannot convert the representation of data as marshaled into its native representation or vice-versa. For example, <code>DATA_CONVERSION</code> can be raised if wide character codeset conversion fails, or if an ORB cannot convert floating point values between different representations.
<code>FREE_MEM</code>	This exception is raised if the ORB failed in an attempt to free dynamic memory. For example, it is raised because of heap corruption or memory segments being locked.

<code>IMP_LIMIT</code>	This exception indicates that an implementation limit was exceeded in the ORB run time. For example, an ORB may reach the maximum number of references it can hold simultaneously in an address space, the size of a parameter may have exceeded the allowed maximum, or an ORB may impose a maximum on the number of clients or servers that can run simultaneously.
<code>INITIALIZATION_ERROR</code>	This exception is raised if an ORB encounters a failure during its initialization, such as failure to acquire networking resources or detection of a configuration error.
<code>INTERNAL</code>	This exception indicates an internal failure in an ORB. For example, it is raised if an ORB detected corruption of its internal data structures.
<code>INTERFACE_REPOSITORY</code>	This exception is raised if an ORB cannot reach the interface repository, or some other failure relating to the interface repository is detected.
<code>INVALID_FLAG</code>	This exception indicates that an invalid flag was passed to an operation. For example, it is raised when creating a DII request.
<code>INVALID_IDENTIFIER</code>	This exception indicates that an IDL identifier is syntactically invalid. For example it may be raised if an identifier passed to the interface repository does not conform to IDL identifier syntax, or if an illegal operation name is used with the DII.
<code>INVALID_OBJECT_REFERENCE</code>	This exception indicates that an object reference is internally malformed. For example, the repository ID may have incorrect syntax or the addressing information may be invalid. This exception is raised by <code>ORB::string_to_object</code> if the passed string does not decode correctly. An ORB implementation might detect calls via nil references (although it is not obliged to detect them). <code>INV_OBJREF</code> is used to indicate this.
<code>INVALID_POLICY</code>	This exception is raised when an invocation cannot be made due to an incompatibility between policy overrides that apply to the particular invocation.
<code>INVALID_TRANSACTION</code>	This exception indicates that the request carried an invalid transaction context. For example, this exception could be raised if an error occurred when trying to register a resource.

MARSHAL	This exception is raised if a request or reply from the network is structurally invalid. This error typically indicates a bug in either the client-side or server-side run time. For example, if a reply from the server indicates that the message contains 1000 bytes, but the actual message is shorter or longer than 1000 bytes, the ORB raises this exception. MARSHAL can also be caused by using the DII or DSI incorrectly. For example, it is raised if the type of the actual parameters sent does not agree with IDL signature of an operation.
NO_IMPLEMENT	This exception is raised if the operation that was invoked exists (it has an IDL definition) but no implementation for that operation exists. For example, NO_IMPLEMENT can be raised by an ORB if a client asks for an object's type definition from the interface repository, but no interface repository is provided by the ORB.
NO_MEMORY	This exception indicates that the ORB run time has run out of memory.
NO_PERMISSION	This exception is raised if an invocation fails because the caller has insufficient privileges.
NO_RESOURCES	This exception indicates that the ORB has encountered some general resource limitation. For example, the run time may have reached the maximum permissible number of open connections.
NO_RESPONSE	This exception is raised if a client attempts to retrieve the result of a deferred synchronous call but the response for the request is not yet available.
OBJ_ADAPTER	This exception typically indicates an administrative mismatch. For example, a server may have made an attempt to register itself with an implementation repository under a name that is already in use, or a name that is unknown to the repository. OBJ_ADAPTER is also raised by the POA to indicate problems with application-supplied servant managers.

<code>OBJECT_NOT_EXIST</code>	This exception is raised whenever an invocation on a deleted object is performed. It is an authoritative “hard” fault report. Anyone receiving it is allowed (even expected) to delete all copies of this object reference and to perform other appropriate “final recovery” style procedures. Bridges forward this exception to clients, also destroying any records they may hold (for example, proxy objects used in reference translation). The clients could in turn purge any of their own data structures.
<code>PERSIST_STORE</code>	This exception indicates a persistent storage failure. For example, it is raised if there is a failure to establish a database connection or corruption of a database.
<code>REBIND</code>	This exception is raised when the current effective <code>RebindPolicy</code> has a value of <code>NO_REBIND</code> or <code>NO_RECONNECT</code> and an invocation on a bound object reference results in a <code>LocateReply</code> message with status <code>OBJECT_FORWARD</code> or a <code>Reply</code> message with status <code>LOCATION_FORWARD</code>. This exception is also raised if the current effective <code>RebindPolicy</code> has a value of <code>NO_RECONNECT</code> and a connection must be re-opened. The invocation can be retried once the effective <code>RebindPolicy</code> is changed to <code>TRANSPARENT</code> or binding is re-established through an invocation of <code>CORBA::Object::validate_connection()</code>.
<code>TIMEOUT</code>	This system exception is raised when no delivery has been made and the specified time-to-live period has been exceeded. It is a standard system exception because time-to-live QoS can be applied to any invocation.
<code>TRANSACTION_MODE</code>	The <code>CosTransactions</code> module adds the <code>TRANSACTION_MODE</code> exception that can be raised by the ORB when it detects a mismatch between the <code>TransactionPolicy</code> in the IOR and the current transaction mode.
<code>TRANSACTION_REQUIRED</code>	This exception indicates that the request carried a null transaction context, but an active transaction is required.
<code>TRANSACTION_ROLLED_BACK</code>	This exception indicates that the transaction associated with the request has already been rolled back or marked to roll back. The requested operation either could not be performed or was not performed because further computation on behalf of the transaction would be fruitless.

<code>TRANSACTION_UNAVAILABLE</code>	The <code>CosTransactions</code> module adds the <code>TRANSACTION_UNAVAILABLE</code> exception that can be raised by the ORB when it cannot process a transaction service context because its connection to the transaction service has been abnormally terminated.
<code>TRANSIENT</code>	This exception indicates that the ORB attempted to reach an object and failed. It is not an indication that an object does not exist. Instead, it simply means that no further determination of an object's status was possible because it could not be reached. For example, this exception is raised if an attempt to establish a connection fails because the server or the implementation repository is down.
<code>UNKNOWN</code>	This exception is raised if an operation implementation throws a non-CORBA exception (such as an exception specific to the implementation's programming language), or if an operation raises a user exception that does not appear in the operation's <code>raises</code> expression. <code>UNKNOWN</code> is also raised if the server returns a system exception that is unknown to the client. (This can happen if the server uses a later version of CORBA than the client and new system exceptions have been added to the later version.)

Notices

Copyright

© 1996-2025 Rocket Software, Inc. or its affiliates. All Rights Reserved.

Trademarks

Rocket is a registered trademark of Rocket Software, Inc. For a list of Rocket registered trademarks go to: www.rocketsoftware.com/about/legal. All other products or services mentioned in this document may be covered by the trademarks, service marks, or product names of their respective owners.

Examples

This information might contain examples of data and reports. The examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

License agreement

This software and the associated documentation are proprietary and confidential to Rocket Software, Inc. or its affiliates, are furnished under license, and may be used and copied only in accordance with the terms of such license.

Note: This product may contain encryption technology. Many countries prohibit or restrict the use, import, or export of encryption technologies, and current use, import, and export regulations should be followed when exporting this product.

Corporate information

Rocket Software, Inc. develops enterprise infrastructure products in four key areas: storage, networks, and compliance; database servers and tools; business information and analytics; and application development, integration, and modernization.

Website: www.rocketsoftware.com

Contacting Technical Support

The Rocket Community is the primary method of obtaining support. If you have current support and maintenance agreements with Rocket Software, you can access the Rocket Community and report a problem, download an update, or read answers to FAQs. To log in to the Rocket Community or to request a Rocket Community account, go to www.rocketsoftware.com/support. In addition to using the Rocket Community to obtain support, you can use one of the telephone numbers that are listed above or send an email to support@rocketsoftware.com.

Rocket Global Headquarters
77 4th Avenue, Suite 100
Waltham, MA 02451-1468
USA

Country and Toll-free telephone number

To contact Rocket Software by telephone for any reason, including obtaining pre-sales information and technical support, use one of the following telephone numbers.

- United States: 1-855-577-4323
- Australia: 1-800-823-405
- Belgium: 0800-266-65
- Canada: 1-855-577-4323
- China: 400-120-9242
- France: 08-05-08-05-62
- Germany: 0800-180-0882
- Italy: 800-878-295
- Japan: 0800-170-5464
- Netherlands: 0-800-022-2961
- New Zealand: 0800-003210
- South Africa: 0-800-980-818
- United Kingdom: 0800-520-0439